## **NAME**

xdelta3 - VCDIFF (RFC 3284) binary diff tool

## **SYNOPSIS**

xdelta3 [command] [options] [input [output]]

## DESCRIPTION

xdelta3 is a binary diff tool that uses the VCDIFF (RFC 3284) format and compression.

# **COMMANDS**

config prints xdelta3 configuration

decode decompress the input, also set by -d

encode compress the input, also set by -e (default)

**test** run the builtin tests

# printdelta

print information about the entire delta

## printhdr

print information about the first window

# printhdrs

print information about all windows

recode encode with new application/secondary settings

# **OPTIONS**

standard options:

#### -0..-9

compression level

- -c use stdout
- -d decompress
- -e compress
- **-f** force overwrite
- **-h** show help
- -q be quiet
- **-v** be verbose (max 2)
- **-V** show version

# memory options:

- **-B** bytes source window size
- **-W** bytes input window size
- **-P** size compression duplicates window
- -I size instruction buffer size (0 = unlimited)

# compression options:

- -s source source file to copy from (if any)
- $-\mathbf{S}$  [djw|fgk|lzma|none]

enable/disable secondary compression

- -N disable small string-matching compression
- **-D** disable external decompression (encode/decode)
- **-R** disable external recompression (decode)
- **-n** disable checksum (encode/decode)
- **-C** soft config (encode, undocumented)
- -A [apphead]

disable/provide application header (encode)

- **-J** disable output (check/compute only)
- **-T** use alternate code table (test)

#### **NOTES**

The **XDELTA** environment variable may contain extra args:

```
XDELTA="-s source-x.y.tar.gz" \
tar --use-compress-program=xdelta3 -cf \
target-x.z.tar.gz.vcdiff target-x.y/
```

# **EXAMPLES**

Compress the differences between SOURCE and TARGET, yielding OUT, using "djw" secondary compression:

```
xdelta3 -S djw -s SOURCE TARGET OUT
```

Do the same, using standard input and output:

```
xdelta3 -S djw -s SOURCE < TARGET > OUT
```

To decompress OUT, using SOURCE, yielding TARGET:

xdelta3 -d -s SOURCE OUT TARGET

# **AUTHOR**

xdelta3 was written by Josh MacDonald <josh.macdonald@gmail.com>.

This manual page was written by Leo 'costela' Antunes <costela@debian.org> for the Debian project (but may be used by others).