NAME

ecvt_r, fcvt_r, qecvt_r, qfcvt_r − convert a floating-point number to a string

SYNOPSIS

#include <stdlib.h>

int ecvt_r(double *number***, int** *ndigits***, int ****decpt***,**
int **sign***, char ****buf***, size_t** *len***);**

int fcvt_r(double *number***, int** *ndigits***, int ****decpt***,**
int **sign***, char ****buf***, size_t** *len***);**

int qecvt_r(long double *number***, int** *ndigits***, int ****decpt***,**
int **sign***, char ****buf***, size_t** *len***);**

int qfcvt_r(long double *number***, int** *ndigits***, int ****decpt***,**
int **sign***, char ****buf***, size_t** *len***);**

Feature Test Macro Requirements for glibc (see **feature_test_macros**(7)):

ecvt_r(), **fcvt_r**(), **qecvt_r**(), **qfcvt_r**():
/* Glibc since 2.19: */ _DEFAULT_SOURCE
|| /* Glibc versions <= 2.19: */ _SVID_SOURCE || _BSD_SOURCE

DESCRIPTION

The functions **ecvt_r**(), **fcvt_r**(), **qecvt_r**(), and **qfcvt_r**() are identical to **ecvt**(3), **fcvt**(3), **qecvt**(3), and **qfcvt**(3), respectively, except that they do not return their result in a static buffer, but instead use the supplied *buf* of size *len*. See **ecvt**(3) and **qecvt**(3).

RETURN VALUE

These functions return 0 on success, and −1 otherwise.

ATTRIBUTES

For an explanation of the terms used in this section, see **attributes**(7).

Interface	Attribute	Value
ecvt_r(), **fcvt_r**(), **qecvt_r**(), **qfcvt_r**()	Thread safety	MT-Safe

CONFORMING TO

These functions are GNU extensions.

NOTES

These functions are obsolete. Instead, **sprintf**(3) is recommended.

SEE ALSO

ecvt(3), **qecvt**(3), **sprintf**(3)

COLOPHON

This page is part of release 5.02 of the Linux *man-pages* project. A description of the project, information about reporting bugs, and the latest version of this page, can be found at https://www.kernel.org/doc/man−pages/.