



IAdvancedHoleElementData Interface

Allows access to Advanced Hole element data.

.NET Syntax

Visual Basic (Declaration)

```
Public Interface IAdvancedHoleElementData
```

Visual Basic (Usage)

```
Dim instance As IAdvancedHoleElementData
```

C#

```
public interface IAdvancedHoleElementData
```

C++/CLI

```
public interface class IAdvancedHoleElementData
```

Example

[Create Advanced Hole Feature \(VBA\)](#)

[Create Advanced Hole Feature \(VB.NET\)](#)

[Create Advanced Hole Feature \(C#\)](#)

Remarks

IAdvancedHoleElementData is extended by the following:

[ICounterboreElementData](#)

[ICountersinkElementData](#)

[IStraightElementData](#)

[IStraightTapElementData](#)

[ITaperedTapElementData](#)

After accessing the IAdvancedHoleElementData object, cast it to a hole type-specific object using one of the interfaces above and set the hole type-specific properties.

To create an Advanced Hole feature, see the [IFeatureManager::AdvancedHole](#) Remarks.

Accessors

[IModelDocExtension::CreateAdvancedHoleElementData](#)

Access Diagram

[AdvancedHoleElementData](#)

See Also

[IAdvancedHoleElementData Members](#)
[SolidWorks.Interop.sldworks Namespace](#)
[IAdvancedHoleFeatureData Interface](#)



IAdvancedHoleElementData Interface Members

The following tables list the members exposed by [IAdvancedHoleElementData](#).

Public Properties

Name	Description
 BlindDepth	Gets or sets the depth for the blind end condition of this Advanced Hole element.
 CalloutString	Gets or sets the hole callout string for this Advanced Hole element.
 Diameter	Gets or sets the diameter of this Advanced Hole element.
 DiameterOverride	Gets or sets whether to override the diameter of this Advanced Hole element.
 ElementType	Gets the type of this Advanced Hole element.
 EndCondition	Gets or sets the end condition for this Advanced Hole element.
 FastenerType	Gets or sets the fastener type for this Advanced Hole element.
 OffsetDistance	Gets or sets the offset distance for this Advanced Hole element.
 OffsetReverseDirection	Gets or sets whether to reverse the offset direction for this Advanced Hole element.
 Orientation	Gets or sets the orientation of this Advanced Hole element.
 SelectionEntity	Gets or sets the entity used to specify the Up to Selection or Offset from Surface end condition for this Advanced Hole element.
 Size	Gets or sets the size of this Advanced Hole element.
 Standard	Gets or sets the hole standard used for this Advanced Hole element.

[Top](#)

See Also

[IAdvancedHoleElementData Interface](#)
[SolidWorks.Interop.sldworks Namespace](#)
[IAdvancedHoleFeatureData Interface](#)