

PDMWorks API (.NET, legacy) — Reference (1/4): _namespace_hierarchy-IPDMWConnection

SOLIDWORKS API Documentation (converted from CHM)

namespace_hierarchy (Type)

SOLIDWORKS Workgroup PDM API Help

[Send comments on this topic.](#)

PDMWorks.Interop.pdmworks Namespace Inheritance Hierarchy

[See Also](#)



Inheritance Hierarchy

System.Object

See Also

[PDMWorks.Interop.pdmworks.Assembly](#)

IPDMWConfiguration (Type)

IPDMWConfiguration Interface

[See Also](#) [Members](#)



[PDMWorks.Interop.pdmworks Namespace](#) : IPDMWConfiguration Interface

Provides access to SOLIDWORKS configurations.

NOTE: Click the **Members** link, located near the top of the topic, to see this interface's methods and properties.

.NET Syntax

Visual Basic (Declaration)

Public Interface IPDMWConfiguration

Visual Basic (Usage)

Dim instance As [IPDMWConfiguration](#)

C#

public interface IPDMWConfiguration

C++/CLI

public interface class IPDMWConfiguration

Visual Basic for Applications (VBA) Syntax

See [PDMWConfiguration](#).

Accessors

[IPDMWConfigurations::Item](#)

See Also

[IPDMWConfiguration Members](#)
[PDMWorks.Interop.pdmworks Namespace](#)
[IPDMWConfigurations Interface](#)

IPDMWConfiguration Interface Members

[See Also](#) [Properties](#)



[PDMWorks.Interop.pdmworks Namespace](#) : IPDMWConfiguration Interface

The following tables list the members exposed by [IPDMWConfiguration](#).

Public Properties

Name	Description
AlternateName	Gets the alternate name for the configuration.
Comment	Gets comments for the configuration.
docname	Gets the name of the source document for the configuration.
DocRevision	Gets the revision of the source document for the configuration.
Document	Gets the document for this configuration.
ExtReferences	Gets the links to external documents referenced by this configuration.
ExtWhereUsed	Gets the links to external documents that reference this configuration.

 Name	Gets the name for the configuration.
 Properties	Gets the properties for the configuration.
 Quantity	Obsolete. Superseded by IPDMWLink.Quantity .
 References	Gets the links to documents referenced by this configuration.
 WhereUsed	Gets the links to the documents that reference this configuration.

[Top](#)

 See Also

[IPDMWConfiguration Interface](#)
[PDMWorks.Interop.pdmworks Namespace](#)
[IPDMWConfigurations Interface](#)

SOLIDWORKS Workgroup PDM API Help [Send comments on this topic.](#)

IPDMWConfiguration Interface Properties

[See Also](#)



[PDMWorks.Interop.pdmworks Namespace](#) : IPDMWConfiguration Interface

For a list of all members of this type, see [IPDMWConfiguration members](#).

 Public Properties

Name	Description
 AlternateName	Gets the alternate name for the configuration.
 Comment	Gets comments for the configuration.
 docname	Gets the name of the source document for the configuration.
 DocRevision	Gets the revision of the source document for the configuration.
 Document	Gets the document for this configuration.
 ExtReferences	Gets the links to external documents referenced by this configuration.
 ExtWhereUsed	Gets the links to external documents that reference this configuration.
 Name	Gets the name for the configuration.
 Properties	Gets the properties for the configuration.
 Quantity	Obsolete. Superseded by IPDMWLink.Quantity .
 References	Gets the links to documents referenced by this configuration.
 WhereUsed	Gets the links to the documents that reference this configuration.

[Top](#)

 See Also

[IPDMWConfiguration Interface](#)
[PDMWorks.Interop.pdmworks Namespace](#)
[IPDMWConfigurations Interface](#)

SOLIDWORKS Workgroup PDM API Help [Send comments on this topic.](#)

AlternateName Property (IPDMWConfiguration)

[See Also](#)



[PDMWorks.Interop.pdmworks Namespace](#) > [IPDMWConfiguration Interface](#) : AlternateName Property (IPDMWConfiguration)

Gets the alternate name for the configuration.

 .NET Syntax

Visual Basic (Declaration)

Property AlternateName As System.String

Visual Basic (Usage)



```
Dim instance As IPDMWConfiguration  
Dim value As System.String
```

```
instance.AlternateName = value
```

```
value = instance.AlternateName
```

C#

```
System.string AlternateName {get; set;}
```

C++/CLI

```
property System.String^ AlternateName {  
    System.String^ get();  
    void set ( &    System.String^ value);  
}
```

Property Value

Alternate name for the configuration

Visual Basic for Applications (VBA) Syntax

See [PDMWConfiguration::AlternateName](#).

See Also

[IPDMWConfiguration Interface](#)
[IPDMWConfiguration Members](#)

Availability

SOLIDWORKS Workgroup PDM 2003 FCS

SOLIDWORKS Workgroup PDM API Help

[Send comments on this topic.](#)

Comment Property (IPDMWConfiguration)

[See Also](#)



[PDMWorks.Interop.pdmworks Namespace](#) > [IPDMWConfiguration Interface](#) : Comment Property (IPDMWConfiguration)

Gets comments for the configuration.

.NET Syntax

Visual Basic (Declaration)

```
Property Comment As System.String
```

Visual Basic (Usage)



```
Dim instance As IPDMWConfiguration  
Dim value As System.String
```

```
instance.Comment = value
```

```
value = instance.Comment
```

C#

```
System.string Comment {get; set;}
```

C++/CLI

```
property System.String^ Comment {
    System.String^ get();
    void set ( & System.String^ value);
}
```

Property Value

Comments

Visual Basic for Applications (VBA) Syntax

See [PDMWConfiguration::Comment](#).

See Also

[IPDMWConfiguration Interface](#)
[IPDMWConfiguration Members](#)

Availability

SOLIDWORKS Workgroup PDM 2003 FCS

SOLIDWORKS Workgroup PDM API Help

[Send comments](#) on this topic.

docname Property (IPDMWConfiguration)

[See Also](#)



[PDMWorks.Interop.pdmworks Namespace](#) > [IPDMWConfiguration Interface](#) : docname Property (IPDMWConfiguration)

Gets the name of the source document for the configuration.

.NET Syntax

Visual Basic (Declaration)

```
Property docname As System.String
```

Visual Basic (Usage)



```
Dim instance As IPDMWConfiguration
Dim value As System.String
```

```
instance.docname = value
```

```
value = instance.docname
```

C#

```
System.string docname {get; set;}
```

C++/CLI

```
property System.String^ docname {
    System.String^ get();
    void set ( & System.String^ value);
}
```

Property Value

Name of the source document

Visual Basic for Applications (VBA) Syntax

See [PDMWConfiguration::docname](#).

See Also

Availability

SOLIDWORKS Workgroup PDM 2003 FCS

SOLIDWORKS Workgroup PDM API Help

[Send comments on this topic.](#)

DocRevision Property (IPDMWConfiguration)

[See Also](#)



[PDMWorks.Interop.pdmworks Namespace](#) > [IPDMWConfiguration Interface](#) : DocRevision Property (IPDMWConfiguration)

Gets the revision of the source document for the configuration.

.NET Syntax

Visual Basic (Declaration)

Property DocRevision As System.String

Visual Basic (Usage)



```
Dim instance As IPDMWConfiguration  
Dim value As System.String
```

```
instance.DocRevision = value
```

```
value = instance.DocRevision
```

C#

```
System.string DocRevision {get; set;}
```

C++/CLI

```
property System.String^ DocRevision {  
    System.String^ get();  
    void set ( & System.String^ value);  
}
```

Property Value

Revision of the source document for the configuration

Visual Basic for Applications (VBA) Syntax

See [PDMWConfiguration::DocRevision](#).

See Also

[IPDMWConfiguration Interface](#)
[IPDMWConfiguration Members](#)

Availability

SOLIDWORKS Workgroup PDM 2003 FCS

SOLIDWORKS Workgroup PDM API Help

[Send comments on this topic.](#)

Document Property (IPDMWConfiguration)

[See Also](#)



[PDMWorks.Interop.pdmworks Namespace](#) > [IPDMWConfiguration Interface](#) : Document Property (IPDMWConfiguration)

Gets the document for this configuration.

.NET Syntax

Visual Basic (Declaration)

ReadOnly Property Document As PDMWDocument

Visual Basic (Usage)



```
Dim instance As IPDMWConfiguration  
Dim value As PDMWDocument
```

```
value = instance.Document
```

C#

```
PDMWDocument Document {get;}
```

C++/CLI

```
property PDMWDocument^ Document {  
    PDMWDocument^ get();  
}
```

Property Value

[Document for this configuration](#)

Visual Basic for Applications (VBA) Syntax

See [PDMWConfiguration::Document](#).

See Also

[IPDMWConfiguration Interface](#)
[IPDMWConfiguration Members](#)
[IPDMWDocument Interface](#)

Availability

SOLIDWORKS Workgroup PDM 2003 FCS

SOLIDWORKS Workgroup PDM API Help

[Send comments on this topic.](#)

ExtReferences Property (IPDMWConfiguration)

[See Also](#)



[PDMWorks.Interop.pdmworks Namespace](#) > [IPDMWConfiguration Interface](#) : ExtReferences Property (IPDMWConfiguration)

Gets the links to external documents referenced by this configuration.

.NET Syntax

Visual Basic (Declaration)

ReadOnly Property ExtReferences As PDMWLinks

Visual Basic (Usage)



```
Dim instance As IPDMWConfiguration  
Dim value As PDMWLinks
```

```
value = instance.ExtReferences
```

C#

```
PDMWLinks ExtReferences {get;}
```

C++/CLI

```
property PDMWLinks^ ExtReferences {  
    PDMWLinks^ get();  
}
```


Property Value

Collection of [links](#) to external documents referenced by this configuration

Visual Basic for Applications (VBA) Syntax

See [PDMWConfiguration::ExtReferences](#).

Remarks

An external document is any type of derived part, parent or child, including base, mirrored, and component parts.

See Also

[IPDMWConfiguration Interface](#)
[IPDMWConfiguration Members](#)
[IPDMWLinks Interface](#)

Availability

SOLIDWORKS Workgroup PDM 2003 FCS

SOLIDWORKS Workgroup PDM API Help

[Send comments](#) on this topic.

ExtWhereUsed Property (IPDMWConfiguration)

[See Also](#)



[PDMWorks.Interop.pdmworks Namespace](#) > [IPDMWConfiguration Interface](#) : ExtWhereUsed Property (IPDMWConfiguration)

Gets the links to external documents that reference this configuration.

.NET Syntax

Visual Basic (Declaration)

ReadOnly Property ExtWhereUsed As PDMWLinks

Visual Basic (Usage)



```
Dim instance As IPDMWConfiguration
Dim value As PDMWLinks
```

```
value = instance.ExtWhereUsed
```

C#

```
PDMWLinks ExtWhereUsed {get;}
```

C++/CLI

```
property PDMWLinks^ ExtWhereUsed {
    PDMWLinks^ get();
}
```

Property Value

Collection of [links](#) to external documents that reference this configuration

Visual Basic for Applications (VBA) Syntax

See [PDMWConfiguration::ExtWhereUsed](#).

Remarks

An external document is any type of derived part, parent or child, including base, mirrored, and component parts.

See Also

[IPDMWConfiguration Interface](#)
[IPDMWConfiguration Members](#)
[IPDMWLinks Interface](#)

Availability

SOLIDWORKS Workgroup PDM 2003 FCS

SOLIDWORKS Workgroup PDM API Help

[Send comments on this topic.](#)

Name Property (IPDMWConfiguration)

[See Also](#)



[PDMWorks.Interop.pdmworks Namespace](#) > [IPDMWConfiguration Interface](#) : Name Property (IPDMWConfiguration)

Gets the name for the configuration.

.NET Syntax

Visual Basic (Declaration)

Property Name As System.String

Visual Basic (Usage)



```
Dim instance As IPDMWConfiguration  
Dim value As System.String
```

```
instance.Name = value
```

```
value = instance.Name
```

C#

```
System.string Name {get; set;}
```

C++/CLI

```
property System.String^ Name {  
    System.String^ get();  
    void set ( & System.String^ value);  
}
```

Property Value

Name for the configuration

Visual Basic for Applications (VBA) Syntax

See [PDMWConfiguration::Name](#).

See Also

[IPDMWConfiguration Interface](#)
[IPDMWConfiguration Members](#)

Availability

SOLIDWORKS Workgroup PDM 2003 FCS

SOLIDWORKS Workgroup PDM API Help

[Send comments on this topic.](#)

Properties Property (IPDMWConfiguration)

[See Also](#)



[PDMWorks.Interop.pdmworks Namespace](#) > [IPDMWConfiguration Interface](#) : Properties Property (IPDMWConfiguration)

Gets the properties for the configuration.

.NET Syntax

Visual Basic (Declaration)

ReadOnly Property Properties As PDMWProperties

Visual Basic (Usage)



```
Dim instance As IPDMWConfiguration
Dim value As PDMWProperties
```

```
value = instance.Properties
```

C#

```
PDMWProperties Properties {get;}
```

C++/CLI

```
property PDMWProperties^ Properties {
    PDMWProperties^ get();
}
```

Property Value

Collection of [properties](#) for the configuration

Visual Basic for Applications (VBA) Syntax

See [PDMWConfiguration::Properties](#).

See Also

[IPDMWConfiguration Interface](#)
[IPDMWConfiguration Members](#)
[IPDMWProperties Interface](#)

Availability

SOLIDWORKS Workgroup PDM 2003 FCS

SOLIDWORKS Workgroup PDM API Help

[Send comments on this topic.](#)

Quantity Property (IPDMWConfiguration)

[See Also](#)



[PDMWorks.Interop.pdmworks Namespace](#) > [IPDMWConfiguration Interface](#) : Quantity Property (IPDMWConfiguration)

Obsolete. Superseded by [IPDMWLink::Quantity](#).

.NET Syntax

Visual Basic (Declaration)

```
Property Quantity As System.Integer
```

Visual Basic (Usage)



```
Dim instance As IPDMWConfiguration
Dim value As System.Integer
```

```
instance.Quantity = value
```

```
value = instance.Quantity
```

C#

```
System.int Quantity {get; set;}
```

C++/CLI

```
property System.int Quantity {
    System.int get();
}
```

```
void set ( & System.int value);  
}
```

Visual Basic for Applications (VBA) Syntax

See [PDMWConfiguration::Quantity](#).

See Also

[IPDMWConfiguration Interface](#)
[IPDMWConfiguration Members](#)

Availability

SOLIDWORKS Workgroup PDM 2003 FCS

SOLIDWORKS Workgroup PDM API Help

[Send comments](#) on this topic.

References Property (IPDMWConfiguration)

[See Also](#)



[PDMWorks.Interop.pdmworks Namespace](#) > [IPDMWConfiguration Interface](#) : References Property (IPDMWConfiguration)

Gets the links to documents referenced by this configuration.

.NET Syntax

Visual Basic (Declaration)

ReadOnly Property References As PDMWLinks

Visual Basic (Usage)



```
Dim instance As IPDMWConfiguration  
Dim value As PDMWLinks
```

```
value = instance.References
```

C#

```
PDMWLinks References {get;}
```

C++/CLI

```
property PDMWLinks^ References {  
    PDMWLinks^ get();  
}
```

Property Value

Collection of [links](#) to documents referenced by this configuration

Visual Basic for Applications (VBA) Syntax

See [PDMWConfiguration::References](#).

See Also

[IPDMWConfiguration Interface](#)
[IPDMWConfiguration Members](#)
[IPDMWLinks interface](#)

Availability

SOLIDWORKS Workgroup PDM 2003 FCS

SOLIDWORKS Workgroup PDM API Help

[Send comments](#) on this topic.

WhereUsed Property (IPDMWConfiguration)

[See Also](#)



[PDMWorks.Interop.pdmworks Namespace](#) > [IPDMWConfiguration Interface](#) : WhereUsed Property (IPDMWConfiguration)

Gets the links to the documents that reference this configuration.

.NET Syntax

Visual Basic (Declaration)

ReadOnly Property WhereUsed As PDMWLinks

Visual Basic (Usage)



```
Dim instance As IPDMWConfiguration  
Dim value As PDMWLinks
```

```
value = instance.WhereUsed
```

C#

```
PDMWLinks WhereUsed {get;}
```

C++/CLI

```
property PDMWLinks^ WhereUsed {  
    PDMWLinks^ get();  
}
```

Property Value

Collection of [links](#) of documents that reference this configuration

Visual Basic for Applications (VBA) Syntax

See [PDMWConfiguration::WhereUsed](#).

See Also

[IPDMWConfiguration Interface](#)
[IPDMWConfiguration Members](#)
[IPDMWLinks Interface](#)

Availability

SOLIDWORKS Workgroup PDM 2003 FCS

IPDMWConfigurations (Type)

IPDMWConfigurations Interface

[See Also](#) [Members](#)



[PDMWorks.Interop.pdmworks Namespace](#) : IPDMWConfigurations Interface

Contains [IPDMWConfiguration](#) objects.

NOTE: Click the **Members** link, located near the top of the topic, to see this interface's methods and properties.

.NET Syntax

Visual Basic (Declaration)

Public Interface IPDMWConfigurations

Visual Basic (Usage)

Dim instance As [IPDMWConfigurations](#)

C#

public interface IPDMWConfigurations

C++/CLI

public interface class IPDMWConfigurations

Visual Basic for Applications (VBA) Syntax

See [PDMWConfigurations](#).

Accessors

[IPDMWDocument::Configurations](#)

See Also

[IPDMWConfigurations Members](#)
[PDMWorks.Interop.pdmworks Namespace](#)
[IPDMWConfiguration Interface](#)

IPDMWConfigurations Interface Members

[See Also](#) [Properties](#)



[PDMWorks.Interop.pdmworks Namespace](#) : IPDMWConfigurations Interface

The following tables list the members exposed by [IPDMWConfigurations](#).

Public Properties

Name	Description
Count	Gets the number of configurations.
Item	Gets a configuration.

[Top](#)

See Also

[IPDMWConfigurations Interface](#)
[PDMWorks.Interop.pdmworks Namespace](#)
[IPDMWConfiguration Interface](#)

IPDMWConfigurations Interface Properties

[See Also](#)



[PDMWorks.Interop.pdmworks Namespace](#) : IPDMWConfigurations Interface

For a list of all members of this type, see [IPDMWConfigurations members](#).

Public Properties

Name	Description
 Count	Gets the number of configurations.
 Item	Gets a configuration.

[Top](#)

See Also

[IPDMWConfigurations Interface](#)
[PDMWorks.Interop.pdmworks Namespace](#)
[IPDMWConfiguration Interface](#)

SOLIDWORKS Workgroup PDM API Help

[Send comments on this topic.](#)

Count Property (IPDMWConfigurations)

[See Also](#)



[PDMWorks.Interop.pdmworks Namespace](#) > [IPDMWConfigurations Interface](#) : Count Property (IPDMWConfigurations)

Gets the number of configurations.

.NET Syntax

Visual Basic (Declaration)

ReadOnly Property Count As System.Integer

Visual Basic (Usage)



```
Dim instance As IPDMWConfigurations  
Dim value As System.Integer
```

```
value = instance.Count
```

C#

```
System.int Count {get;}
```

C++/CLI

```
property System.int Count {  
    System.int get();  
}
```

Property Value

Number of configurations

Visual Basic for Applications (VBA) Syntax

See [PDMWConfigurations::Count](#).

See Also

[IPDMWConfigurations Interface](#)
[IPDMWConfigurations Members](#)
[IPDMWConfigurations::Item Property](#)

Availability

SOLIDWORKS Workgroup PDM 2003 FCS

Item Property (IPDMWConfigurations)

[See Also](#)



[PDMWorks.Interop.pdmworks Namespace](#) > [IPDMWConfigurations Interface](#) : Item Property (IPDMWConfigurations)

Gets a configuration.

.NET Syntax

Visual Basic (Declaration)

```
ReadOnly Default Property Item( _  
    ByVal Index As System.Object _  
) As System.Object
```

Visual Basic (Usage)



```
Dim instance As IPDMWConfigurations  
Dim Index As System.Object  
Dim value As System.Object  
  
value = instance.Item(Index)
```

C#

```
System.object this[  
    System.object Index  
]; {get;}
```

C++/CLI

```
property System.Object^ default [System.Object^] {  
    System.Object^ get(System.Object^ Index);  
}
```

Parameters

Index

Number or name indicating which configuration to get

Property Value

An [IPDMWConfiguration](#)

Visual Basic for Applications (VBA) Syntax

See [PDMWConfigurations::Item](#).

See Also

[IPDMWConfigurations Interface](#)
[IPDMWConfigurations Members](#)
[PDMWConfigurations::Count](#)

Availability

SOLIDWORKS Workgroup PDM 2003 FCS

IPDMWConnection (Type)

IPDMWConnection Interface

[See Also](#) [Members](#) [Example](#)



[PDMWorks.Interop.pdmworks Namespace](#) : IPDMWConnection Interface

Allows you to log in and out of SOLIDWORKS Workgroup PDM and get projects and documents.

NOTE: Click the **Members** link, located near the top of the topic, to see this interface's methods and properties.

.NET Syntax

Visual Basic (Declaration)

```
Public Interface IPDMWConnection
```

Visual Basic (Usage)



```
Dim instance As IPDMWConnection
```

C#

```
public interface IPDMWConnection
```

C++/CLI

```
public interface class IPDMWConnection
```

Visual Basic for Applications (VBA) Syntax

See [PDMWConnection](#).

Example

[Get Specific Document \(VBA\)](#)
[Extract Embedded eDrawings Data \(VBA\)](#)
[List Assemblies Where Part Used \(VBA\)](#)
[Get Names of Projects for All Documents in Vault \(VB.NET\)](#)

See Also

[IPDMWConnection Members](#)
[PDMWorks.Interop.pdmworks Namespace](#)

IPDMWConnection Interface Members

[See Also](#) [Properties](#) [Methods](#)



[PDMWorks.Interop.pdmworks Namespace](#) : IPDMWConnection Interface

The following tables list the members exposed by [IPDMWConnection](#).

Public Properties

Name	Description
 AdminDefinedProperties	Gets a collection of vault administrator-defined custom properties.
 DocumentList	Gets a the list of document names for the specified project.
 Documents	Gets the documents for the specified project.
 Groups	Gets a collection of groups.
 Projects	Gets the SOLIDWORKS Workgroup PDM projects.
 Statuses	Gets the defined lifecycle statuses.
 Users	Gets a collection of users.

[Top](#)

Public Methods

Name	Description
 CheckIn	Checks the specified closed document into the vault.
 CreateGroup	Creates a new group.
 CreateProject	Creates a new project.
 CreateUser	Creates a new user.
 DeleteDocument	Deletes the specified document from the vault.
 DeleteGroup	Deletes the specified group.
 DeleteProject	Deletes the specified project.
 DeleteUser	Deletes the specified user.
 FreeCacheMemory	Frees the cache memory.
 GetSearchOptionsObject	Gets the search options.
 GetSpecificDocument	Gets the specified document and version of that document.
 Login	Logs the user into SOLIDWORKS Workgroup PDM and is required to initialize the IPDMWConnection object for subsequent method calls.
 Logout	Logs the user out of SOLIDWORKS Workgroup PDM and releases user-specific resources.
 Refresh	Refreshes the object model using the data in the vault.
 Search	Searches the vault using the specified search options.

[Top](#)

See Also

[IPDMWConnection Interface](#)
[PDMWorks.Interop.pdmworks Namespace](#)

SOLIDWORKS Workgroup PDM API Help

[Send comments on this topic.](#)

IPDMWConnection Interface Methods

[See Also](#)

 [PDMWorks.Interop.pdmworks Namespace](#) : IPDMWConnection Interface

For a list of all members of this type, see [IPDMWConnection members](#).

Public Methods

Name	Description
 CheckIn	Checks the specified closed document into the vault.
 CreateGroup	Creates a new group.
 CreateProject	Creates a new project.
 CreateUser	Creates a new user.
 DeleteDocument	Deletes the specified document from the vault.
 DeleteGroup	Deletes the specified group.
 DeleteProject	Deletes the specified project.
 DeleteUser	Deletes the specified user.
 FreeCacheMemory	Frees the cache memory.
 GetSearchOptionsObject	Gets the search options.
 GetSpecificDocument	Gets the specified document and version of that document.
 Login	Logs the user into SOLIDWORKS Workgroup PDM and is required to initialize the IPDMWConnection object for subsequent method calls.
 Logout	Logs the user out of SOLIDWORKS Workgroup PDM and releases user-specific resources.

 Refresh	Refreshes the object model using the data in the vault.
 Search	Searches the vault using the specified search options.

[Top](#)

 See Also

[IPDMWConnection Interface](#)
[PDMWorks.Interop.pdmworks Namespace](#)

SOLIDWORKS Workgroup PDM API Help [Send comments on this topic.](#)

IPDMWConnection Interface Properties

[See Also](#)


PDMWorks.Interop.pdmworks Namespace : IPDMWConnection Interface

For a list of all members of this type, see [IPDMWConnection members](#).

 Public Properties

Name	Description
 AdminDefinedProperties	Gets a collection of vault administrator-defined custom properties.
 DocumentList	Gets a the list of document names for the specified project.
 Documents	Gets the documents for the specified project.
 Groups	Gets a collection of groups.
 Projects	Gets the SOLIDWORKS Workgroup PDM projects.
 Statuses	Gets the defined lifecycle statuses.
 Users	Gets a collection of users.

[Top](#)

 See Also

[IPDMWConnection Interface](#)
[PDMWorks.Interop.pdmworks Namespace](#)

SOLIDWORKS Workgroup PDM API Help [Send comments on this topic.](#)

AdminDefinedProperties Property (IPDMWConnection)

[See Also](#)

 
PDMWorks.Interop.pdmworks Namespace > IPDMWConnection Interface : AdminDefinedProperties Property (IPDMWConnection)
Gets a collection of vault administrator-defined custom properties.

 .NET Syntax

Visual Basic (Declaration)

ReadOnly Property AdminDefinedProperties As PDMWProperties

Visual Basic (Usage)



```
Dim instance As IPDMWConnection  
Dim value As PDMWProperties  
  
value = instance.AdminDefinedProperties
```

C#

```
PDMWProperties AdminDefinedProperties {get;}
```

C++/CLI

```
property PDMWProperties^ AdminDefinedProperties {  
    PDMWProperties^ get();  
}
```

Property Value

[IPDMWProperties](#) collection

Visual Basic for Applications (VBA) Syntax

See [PDMWConnection::AdminDefinedProperties](#).

Remarks

These properties are read-only. [IPDMWProperties::Add](#) does nothing when used in this context.

See Also

[IPDMWConnection Interface](#)
[IPDMWConnection Members](#)

Availability

SOLIDWORKS Workgroup PDM 2004 FCS

SOLIDWORKS Workgroup PDM API Help

[Send comments on this topic.](#)

CheckIn Method (IPDMWConnection)

[See Also](#)



[PDMWorks.Interop.pdmworks Namespace](#) > [IPDMWConnection Interface](#) : CheckIn Method (IPDMWConnection)

Checks the specified closed document into the vault.

.NET Syntax

Visual Basic (Declaration)

```
Function CheckIn( _  
    ByVal filename As System.String, _  
    ByVal project As System.String, _  
    ByVal Number As System.String, _  
    ByVal Description As System.String, _  
    ByVal note As System.String, _  
    ByVal i\_revOption As PDMWRevisionOptionType, _  
    ByVal Revision As System.String, _  
    ByVal lifecycle As System.String, _  
    ByVal RetainOwnership As System.Boolean, _  
    ByVal References As System.Object _  
) As PDMWDocument
```

Visual Basic (Usage)



Copy Code

```

Dim instance As IPDMWConnection
Dim filename As System.String
Dim project As System.String
Dim Number As System.String
Dim Description As System.String
Dim note As System.String
Dim i_revOption As PDMWRevisionOptionType
Dim Revision As System.String
Dim lifecycle As System.String
Dim RetainOwnership As System.Boolean
Dim References As System.Object
Dim value As PDMWDocument

```

```

value = instance.CheckIn(filename, project, Number, Description, note, i_revOption, Revision,
lifecycle, RetainOwnership, References)

```

C#

```

PDMWDocument CheckIn(
    System.string filename,
    System.string project,
    System.string Number,
    System.string Description,
    System.string note,
    PDMWRevisionOptionType i\_revOption,
    System.string Revision,
    System.string lifecycle,
    System.bool RetainOwnership,
    System.object References
)

```

C++/CLI

```

PDMWDocument^ CheckIn(
    & System.String^ filename,
    & System.String^ project,
    & System.String^ Number,
    & System.String^ Description,
    & System.String^ note,
    & PDMWRevisionOptionType i\_revOption,
    & System.String^ Revision,
    & System.String^ lifecycle,
    & System.bool RetainOwnership,
    & System.Object^ References
)

```

Parameters

filename

Name of the closed document to check in

project

Name of the project to which the document belongs

Number

Document number

Description

Document description

note

Document notes

i_revOption

Revision option as defined in [PDMWRevisionOptionType](#) (see **Remarks**)

Revision

Document revision

lifecycle

Document lifecycle status

RetainOwnership

True to retain ownership of the document in the vault, false to not

References

Array of the full paths and filenames of any referenced documents to check in (see **Remarks**)

Return Value

[IPDMWDocument](#) object

See [PDMWConnection::CheckIn](#).

Remarks

The document to check in must be closed before calling this method.

IMPORTANT: Because this method is dependent on **pdmworks_libFNP.dll**, you must ensure that your application can find this DLL. The simplest way for your application to find **pdmworks_libFNP.dll** is to add its location to the PATH environmental variable. See [Microsoft Corp's Dynamic-Link Library Search Order](#) for details.

This method only works on computers where both the SOLIDWORKS Workgroup PDM Contributor or Addin client software and SOLIDWORKS Workgroup PDM API DLL are installed.

This method can check in multiple file types, e.g., SOLIDWORKS, eDrawings, Microsoft Word, text, bitmap, PDF, etc.; however, only SOLIDWORKS documents saved in SOLIDWORKS 99 and later are supported by this method.

You must own the document before you can check it in. See [IPDMWDocument::TakeOwnership](#) for details about how to take ownership of a document.

If `i_revOption` is set to `PDMWRevisionOptionType.Other`, then the revision argument is used.

If checking in a document that references...	Then...
Non-Microsoft Word or Excel documents	The references argument is ignored. Instead, you must use <code>IPDMWConnection::CheckIn</code> to check in each referenced document individually.
Microsoft Word or Excel documents	The array of references is used.

See Also

[IPDMWConnection Interface](#)
[IPDMWConnection Members](#)

Availability

SOLIDWORKS Workgroup PDM 2005 FCS

SOLIDWORKS Workgroup PDM API Help

[Send comments on this topic.](#)

CreateGroup Method (IPDMWConnection)

[See Also](#)



[PDMWorks.Interop.pdmworks Namespace](#) > [IPDMWConnection Interface](#) : CreateGroup Method (IPDMWConnection)

Creates a new group.

.NET Syntax

Visual Basic (Declaration)

```
Function CreateGroup( _  
    ByVal Name As System.String _  
) As PDMWGroup
```

Visual Basic (Usage)

```
Dim instance As IPDMWConnection  
Dim Name As System.String  
Dim value As PDMWGroup  
  
value = instance.CreateGroup(Name)
```

C#

```
PDMWGroup CreateGroup(  
    System.string Name  
)
```

C++/CLI

```
PDMWGroup^ CreateGroup(  
& System.String^ Name  
)
```

Parameters

Name
Name of new group

Return Value

[IPDMWGroup](#) object

Visual Basic for Applications (VBA) Syntax

See [PDMWConnection::CreateGroup](#).

Remarks

Only a vault administrator can use this method.

See Also

[IPDMWConnection Interface](#)
[IPDMWConnection Members](#)
[IPDMWConnection::DeleteGroup Method](#)

Availability

SOLIDWORKS Workgroup PDM 2006 FCS

SOLIDWORKS Workgroup PDM API Help

[Send comments](#) on this topic.

CreateProject Method (IPDMWConnection)

[See Also](#)



[PDMWorks.Interop.pdmworks Namespace](#) > [IPDMWConnection Interface](#) : CreateProject Method (IPDMWConnection)

Creates a new project.

.NET Syntax

Visual Basic (Declaration)

```
Function CreateProject(  
    ByVal Name As System.String, _  
    ByVal Description As System.String, _  
    ByVal Parent As System.String _  
) As PDMWProject
```

Visual Basic (Usage)

```
Dim instance As IPDMWConnection  
Dim Name As System.String  
Dim Description As System.String  
Dim Parent As System.String  
Dim value As PDMWProject
```

```
value = instance.CreateProject(Name, Description, Parent)
```

C#

```
PDMWProject CreateProject(  
    System.string Name,  
    System.string Description,  
    System.string Parent  
)
```

C++/CLI

```
PDMWProject^ CreateProject(  
& System.String^ Name,  
& System.String^ Description,  
& System.String^ Parent  
)
```

Parameters

Name

Name of new project

Description

Description of new project

Parent

Name of parent project of new project or an empty string if the new project is at the root level

Return Value

[IPDMWProject](#) object

Visual Basic for Applications (VBA) Syntax

See [PDMWConnection::CreateProject](#).

Remarks

Only a vault administrator can use this method.

See Also

[IPDMWConnection Interface](#)

[IPDMWConnection Members](#)

[IPDMWConnection::DeleteProject Method](#)

[IPDMWProject::SetUserPermissions Method](#)

Availability

SOLIDWORKS Workgroup PDM 2006 FCS

SOLIDWORKS Workgroup PDM API Help

[Send comments](#) on this topic.

CreateUser Method (IPDMWConnection)

[See Also](#)



[PDMWorks.Interop.pdmworks Namespace](#) > [IPDMWConnection Interface](#) : CreateUser Method (IPDMWConnection)

Creates a new user.

.NET Syntax

Visual Basic (Declaration)

```
Function CreateUser( _  
    ByVal Name As System.String, _  
    ByVal password As System.String, _  
    ByVal DisplayName As System.String, _  
    ByVal Email As System.String, _  
    ByVal Comment As System.String, _  
    ByVal PropertyFilterName As System.String, _  
    ByVal PropertyFilterValue As System.String _  
) As PDMWUser
```

Visual Basic (Usage)



```
Dim instance As IPDMWConnection  
Dim Name As System.String  
Dim password As System.String  
Dim DisplayName As System.String  
Dim Email As System.String  
Dim Comment As System.String  
Dim PropertyFilterName As System.String
```



```
Dim PropertyFilterValue As System.String
Dim value As PDMWUser
```

```
value = instance.CreateUser(Name, password, DisplayName, Email, Comment, PropertyFilterName,
PropertyFilterValue)
```

C#

```
PDMWUser CreateUser(
    System.string Name,
    System.string password,
    System.string DisplayName,
    System.string Email,
    System.string Comment,
    System.string PropertyFilterName,
    System.string PropertyFilterValue
)
```

C++/CLI

```
PDMWUser^ CreateUser(
    & System.String^ Name,
    & System.String^ password,
    & System.String^ DisplayName,
    & System.String^ Email,
    & System.String^ Comment,
    & System.String^ PropertyFilterName,
    & System.String^ PropertyFilterValue
)
```

Parameters

Name

Name of new user

password

Password for new user required at login

DisplayName

Name of new user for vault administrator's purposes

Email

Email of new user for vault administrator's purposes

Comment

Comments for vault administrator's purposes

PropertyFilterName

Name of property to use to restrict access to files and projects or an empty string to indicate that properties are not in use to restrict access

PropertyFilterValue

Values for properties (use a comma between values) to restrict access to files and projects or an empty string to indicate that properties are not in use to restrict access

Return Value

[IPDMWUser](#) object

Visual Basic for Applications (VBA) Syntax

See [PDMWConnection::CreateUser](#).

Remarks

Only a vault administrator can use this method.

See Also

[IPDMWConnection Interface](#)

[IPDMWConnection Members](#)

[IPDMWConnection::DeleteUser Method](#)

[IPDMGroup::AddUser Method](#)

[IPDMProject::RemoveUser Method](#)

[IPDMGroup::SetUserPermissions Method](#)

Availability

SOLIDWORKS Workgroup PDM 2006 FCS

DeleteDocument Method (IPDMWConnection)

[See Also](#)



[PDMWorks.Interop.pdmworks Namespace](#) > [IPDMWConnection Interface](#) : DeleteDocument Method (IPDMWConnection)

Deletes the specified document from the vault.

.NET Syntax

Visual Basic (Declaration)

```
Function DeleteDocument( _  
    ByVal docname As System.String _  
) As System.Integer
```

Visual Basic (Usage)



```
Dim instance As IPDMWConnection  
Dim docname As System.String  
Dim value As System.Integer
```

```
value = instance.DeleteDocument(docname)
```

C#

```
System.int DeleteDocument(  
    System.string docname  
)
```

C++/CLI

```
System.int DeleteDocument(  
& System.String^ docname  
)
```

Parameters

docname

Name of the document to delete from the vault

Return Value

0 if successful, non-0 if not

Visual Basic for Applications (VBA) Syntax

See [PDMWConnection::DeleteDocument](#).

See Also

[IPDMWConnection Interface](#)
[IPDMWConnection Members](#)

Availability

SOLIDWORKS Workgroup PDM 2006 SP4

SOLIDWORKS Workgroup PDM API Help

[Send comments on this topic.](#)

DeleteGroup Method (IPDMWConnection)

[See Also](#)



[PDMWorks.Interop.pdmworks Namespace](#) > [IPDMWConnection Interface](#) : DeleteGroup Method (IPDMWConnection)

Deletes the specified group.

.NET Syntax

Visual Basic (Declaration)

```
Sub DeleteGroup(  
    ByVal Name As System.String _  
)
```

Visual Basic (Usage)



```
Dim instance As IPDMWConnection  
Dim Name As System.String  
  
instance.DeleteGroup(Name)
```

C#

```
void DeleteGroup(  
    System.string Name  
)
```

C++/CLI

```
void DeleteGroup(  
& System.String^ Name  
)
```

Parameters

Name
Name of the group to delete

Visual Basic for Applications (VBA) Syntax

See [PDMWConnection::DeleteGroup](#).

Remarks

Only a vault administrator can use this method.

See Also

[IPDMWConnection Interface](#)
[IPDMWConnection Members](#)
[IPDMWConnection::CreateGroup](#)

Availability

SOLIDWORKS Workgroup PDM 2006 FCS

SOLIDWORKS Workgroup PDM API Help

[Send comments](#) on this topic.

DeleteProject Method (IPDMWConnection)

[See Also](#)



[PDMWorks.Interop.pdmworks Namespace](#) > [IPDMWConnection Interface](#) : DeleteProject Method (IPDMWConnection)

Deletes the specified project.

.NET Syntax

Visual Basic (Declaration)

```
Sub DeleteProject(  
    ByVal Name As System.String _  
)
```

Visual Basic (Usage)



```
Dim instance As IPDMWConnection  
Dim Name As System.String
```

```
instance.DeleteProject(Name)
```

C#

```
void DeleteProject(  
    System.string Name  
)
```

C++/CLI

```
void DeleteProject(  
& System.String^ Name  
)
```

Parameters

Name
Name of project to delete

Visual Basic for Applications (VBA) Syntax

See [PDMWConnection::DeleteProject](#).

Remarks

Only a vault administrator can use this method.

See Also

[IPDMWConnection Interface](#)
[IPDMWConnection Members](#)
[IPDMWConnection::CreateProject](#)
[IPDMWProject::SetUserPermissions](#)
[IPDMWProject::CreateSubProject Method](#)

Availability

SOLIDWORKS Workgroup PDM 2006 FCS

SOLIDWORKS Workgroup PDM API Help

[Send comments](#) on this topic.

DeleteUser Method (IPDMWConnection)

[See Also](#)



[PDMWorks.Interop.pdmworks Namespace](#) > [IPDMWConnection Interface](#) : DeleteUser Method (IPDMWConnection)

Deletes the specified user.

.NET Syntax

Visual Basic (Declaration)

```
Sub DeleteUser( _  
    ByVal Name As System.String _  
)
```

Visual Basic (Usage)



```
Dim instance As IPDMWConnection  
Dim Name As System.String  
  
instance.DeleteUser(Name)
```

C#

```
void DeleteUser(  
    System.string Name  
)
```

C++/CLI

```
void DeleteUser(  
& System.String^ Name  
)
```

Parameters

Name
Name of user to delete

Visual Basic for Applications (VBA) Syntax

See [PDMWConnection::DeleteUser](#).

Remarks

Only a vault administrator can use this method.

See Also

[IPDMWConnection Interface](#)
[IPDMWConnection Members](#)
[IPDMWConnection::CreateUser Method](#)
[IPDMWProject::SetUserPermissions Method](#)
[IPDMWGroup::AddUser Method](#)
[IPDMWGroup::RemoveUser Method](#)

Availability

SOLIDWORKS Workgroup PDM 2006 FCS

SOLIDWORKS Workgroup PDM API Help

[Send comments on this topic.](#)

DocumentList Property (IPDMWConnection)

[See Also](#)



[PDMWorks.Interop.pdmworks Namespace](#) > [IPDMWConnection Interface](#) : DocumentList Property (IPDMWConnection)

Gets a the list of document names for the specified project.

.NET Syntax

Visual Basic (Declaration)

```
ReadOnly Property DocumentList( _  
    Optional ByVal project As System.String _  
) As System.Object
```

Visual Basic (Usage)



```
Dim instance As IPDMWConnection  
Dim project As System.String  
Dim value As System.Object
```

```
value = instance.DocumentList(project)
```

C#

```
System.object DocumentList(  
    System.string project  
) {get;}
```

C++/CLI

```
property System.Object^ DocumentList {  
    System.Object^ get(System.String^ project);  
}
```

Parameters

project

Name of the project to which the documents belong

Property Value

Array of the list of documents belonging to the specified project

Visual Basic for Applications (VBA) Syntax

See [PDMWConnection::DocumentList](#).

See Also

[IPDMWConnection Interface](#)
[IPDMWConnection Members](#)
[IPDMWConnection::Documents Property](#)
[IPDMWProject::DocumentCount Property](#)
[IPDMWProject::DocumentList Property](#)
[IPDMWProject::Documents Property](#)

Availability

SOLIDWORKS Workgroup PDM 2007 FCS

SOLIDWORKS Workgroup PDM API Help

[Send comments on this topic.](#)

Documents Property (IPDMWConnection)

[See Also](#) [Example](#)



[PDMWorks.Interop.pdmworks Namespace](#) > [IPDMWConnection Interface](#) : Documents Property (IPDMWConnection)

Gets the documents for the specified project.

.NET Syntax

Visual Basic (Declaration)

```
ReadOnly Property Documents(  
    Optional ByVal project As System.String _  
) As PDMWDocuments
```

Visual Basic (Usage)



```
Dim instance As IPDMWConnection  
Dim project As System.String  
Dim value As PDMWDocuments
```

```
value = instance.Documents(project)
```

C#

```
PDMWDocuments Documents(  
    System.string project  
) {get;}
```

C++/CLI

```
property PDMWDocuments^ Documents {  
    PDMWDocuments^ get(System.String^ project);  
}
```

Parameters

project

Name of the project

Property Value

[Collection of documents](#)

Visual Basic for Applications (VBA) Syntax

See [PDMWConnection::Documents](#).

Example

[Extract Embedded eDrawings Data \(VBA\)](#)
[Get Specific Document \(VBA\)](#)
[List Assemblies Where Part Used \(VBA\)](#)
[Get Names of Projects for All Documents in Vault \(VB.NET\)](#)

Remarks

If...	Then...
A project is passed	The documents that exist within the project are returned
An empty string is passed	The contents of the vault are returned

See Also

[IPDMWConnection Interface](#)
[IPDMWConnection Members](#)
[IPDMWConnection::DocumentList Property](#)
[IPDMWProject::DocumentCount Property](#)
[IPDMWProject::DocumentList Property](#)
[IPDMWProject::Documents Property](#)

Availability

SOLIDWORKS Workgroup PDM 2003 FCS

SOLIDWORKS Workgroup PDM API Help

[Send comments on this topic.](#)

FreeCacheMemory Method (IPDMWConnection)

[See Also](#)



[PDMWorks.Interop.pdmworks Namespace](#) > [IPDMWConnection Interface](#) : FreeCacheMemory Method (IPDMWConnection)

Frees the cache memory.

.NET Syntax

Visual Basic (Declaration)

```
Sub FreeCacheMemory()
```

Visual Basic (Usage)



```
Dim instance As IPDMWConnection  
instance.FreeCacheMemory()
```

C#

```
void FreeCacheMemory()
```

C++/CLI

```
void FreeCacheMemory();
```

Visual Basic for Applications (VBA) Syntax

See [PDMWConnection::FreeCacheMemory](#).

Example

```
Set PDMW_conn = CreateObject("PDMWorks.PDMWConnection")  
PDMW_conn.Login "pdmwadmin", "pdmwadmin", "localhost"  
PDMW_conn.FreeCacheMemory
```

Remarks

Only a vault administrator can use this method.

See Also

[IPDMWConnection Interface](#)
[IPDMWConnection Members](#)

Availability

SOLIDWORKS Workgroup PDM 2009 FCS

SOLIDWORKS Workgroup PDM API Help

[Send comments on this topic.](#)

GetSearchOptionsObject Method (IPDMWConnection)

[See Also](#) [Example](#)



[PDMWorks.Interop.pdmworks Namespace](#) > [IPDMWConnection Interface](#) : GetSearchOptionsObject Method (IPDMWConnection)

Gets the search options.

.NET Syntax

Visual Basic (Declaration)

```
Function GetSearchOptionsObject() As PDMWSearchOptions
```

Visual Basic (Usage)



```
Dim instance As IPDMWConnection
Dim value As PDMWSearchOptions

value = instance.GetSearchOptionsObject()
```

C#

```
PDMWSearchOptions GetSearchOptionsObject()
```

C++/CLI

```
PDMWSearchOptions^ GetSearchOptionsObject();
```

Return Value

[IPDMWSearchOptions](#) object

Visual Basic for Applications (VBA) Syntax

See [PDMWConnection::GetSearchOptionsObject](#).

Example

[Create Search Criteria and Search Vault \(VBA\)](#)

See Also

[IPDMWConnection Interface](#)
[IPDMWConnection Members](#)

Availability

SOLIDWORKS Workgroup PDM 2006 FCS

SOLIDWORKS Workgroup PDM API Help

[Send comments on this topic.](#)

GetSpecificDocument Method (IPDMWConnection)

[See Also](#) [Example](#)



[PDMWorks.Interop.pdmworks Namespace](#) > [IPDMWConnection Interface](#) : GetSpecificDocument Method (IPDMWConnection)

Gets the specified document and version of that document.

.NET Syntax

Visual Basic (Declaration)

```
Function GetSpecificDocument( _  
    ByVal Name As System.String, _  
    Optional ByVal Revision As System.String _  
    ) As PDMWDocument
```

Visual Basic (Usage)



```
Dim instance As IPDMWConnection  
Dim Name As System.String  
Dim Revision As System.String  
Dim value As PDMWDocument  
  
value = instance.GetSpecificDocument(Name, Revision)
```

C#

```
PDMWDocument GetSpecificDocument(  
    System.string Name,  
    System.string Revision  
)
```

C++/CLI

```
PDMWDocument^ GetSpecificDocument(  
& System.String^ Name,  
& System.String^ Revision  
)
```

Parameters

Name

Name of the document to get

Revision

Version of the document to get; if not specified, the most recent version of the specified document is used

Return Value

Pointer to the specified document

Visual Basic for Applications (VBA) Syntax

See [PDMWConnection::GetSpecificDocument](#).

Example

[Get Specific Document \(VBA\)](#)

See Also

[IPDMWConnection Interface](#)
[IPDMWConnection Members](#)
[IPDMWDocument Interface](#)

Availability

SOLIDWORKS Workgroup PDM 2003 FCS

Groups Property (IPDMWConnection)

[See Also](#)



[PDMWorks.Interop.pdmworks Namespace](#) > [IPDMWConnection Interface](#) : Groups Property (IPDMWConnection)

Gets a collection of groups.

.NET Syntax

Visual Basic (Declaration)

```
ReadOnly Property Groups As PDMWGroups
```

Visual Basic (Usage)



```
Dim instance As IPDMWConnection  
Dim value As PDMWGroups
```

```
value = instance.Groups
```

C#

```
PDMWGroups Groups {get;}
```

C++/CLI

```
property PDMWGroups^ Groups {  
    PDMWGroups^ get();  
}
```

Property Value

[IPDMWGroups](#) collection

Visual Basic for Applications (VBA) Syntax

See [PDMWConnection::Groups](#).

See Also

[IPDMWConnection Interface](#)
[IPDMWConnection Members](#)

Availability

SOLIDWORKS Workgroup PDM 2004 FCS

[SOLIDWORKS Workgroup PDM API Help](#)

[Send comments](#) on this topic.

Login Method (IPDMWConnection)

[See Also](#) [Example](#)



[PDMWorks.Interop.pdmworks Namespace](#) > [IPDMWConnection Interface](#) : Login Method (IPDMWConnection)

Logs the user into SOLIDWORKS Workgroup PDM and is required to initialize the [IPDMWConnection](#) object for subsequent method calls.

.NET Syntax

Visual Basic (Declaration)

```
Function Login( _  
    ByVal user As System.String, _  
    ByVal password As System.String, _  
    ByVal server As System.String, _  
    Optional ByVal request\_port As System.Integer, _  
    Optional ByVal data\_port As System.Integer _  
) As System.Integer
```

Visual Basic (Usage)



```

Dim instance As IPDMWConnection
Dim user As System.String
Dim password As System.String
Dim server As System.String
Dim request_port As System.Integer
Dim data_port As System.Integer
Dim value As System.Integer

value = instance.Login(user, password, server, request_port, data_port)

```

C#

```

System.int Login(
    System.string user,
    System.string password,
    System.string server,
    System.int request\_port,
    System.int data\_port
)

```

C++/CLI

```

System.int Login(
    & System.String^ user,
    & System.String^ password,
    & System.String^ server,
    & System.int request\_port,
    & System.int data\_port
)

```

Parameters

user
Name of user in SOLIDWORKS Workgroup PDM

password
Password of user in SOLIDWORKS Workgroup PDM

server
Name of the server (DNS name or IP address)

request_port
Request port number; defaults to 40000

data_port
Data port number; defaults to 30000

Return Value

0 if successful, non-0 if not

Visual Basic for Applications (VBA) Syntax

See [PDMWConnection::Login](#).

Example

[Extract Embedded eDrawings Data \(VBA\)](#)
[Get Specific Document \(VBA\)](#)
[List Assemblies Where Part Used \(VBA\)](#)
[Get Names of Projects for All Documents in Vault \(VB.NET\)](#)

See Also

[IPDMWConnection Interface](#)
[IPDMWConnection Members](#)
[IPDMWConnection::Logout Method](#)

Availability

SOLIDWORKS Workgroup PDM 2003 FCS

[See Also](#) [Example](#)



[PDMWorks.Interop.pdmworks Namespace](#) > [IPDMWConnection Interface](#) : Logout Method (IPDMWConnection)

Logs the user out of SOLIDWORKS Workgroup PDM and releases user-specific resources.

.NET Syntax

Visual Basic (Declaration)

```
Sub Logout()
```

Visual Basic (Usage)



```
Dim instance As IPDMWConnection  
  
instance.Logout()
```

C#

```
void Logout()
```

C++/CLI

```
void Logout();
```

Visual Basic for Applications (VBA) Syntax

See [PDMWConnection::Logout](#).

Example

[Extract Embedded eDrawings Data \(VBA\)](#)
[Get Specific Document \(VBA\)](#)
[List Assemblies Where Part Used \(VBA\)](#)
[Get Names of Projects for All Documents in Vault \(VB.NET\)](#)

See Also

[IPDMWConnection Interface](#)
[IPDMWConnection Members](#)
[IPDMWConnection::Login Method](#)

Availability

SOLIDWORKS Workgroup PDM 2003 FCS

SOLIDWORKS Workgroup PDM API Help

[Send comments on this topic.](#)

Projects Property (IPDMWConnection)

[See Also](#)



[PDMWorks.Interop.pdmworks Namespace](#) > [IPDMWConnection Interface](#) : Projects Property (IPDMWConnection)

Gets the SOLIDWORKS Workgroup PDM projects.

.NET Syntax

Visual Basic (Declaration)

```
ReadOnly Property Projects As PDMWProjects
```

Visual Basic (Usage)



```
Dim instance As IPDMWConnection  
Dim value As PDMWProjects  
  
value = instance.Projects
```

C#

```
PDMWProjects Projects {get;}
```

C++/CLI

```
property PDMWProjects^ Projects {  
    PDMWProjects^ get();  
}
```

Property Value

Collection of [SOLIDWORKS Workgroup PDM projects](#)

Visual Basic for Applications (VBA) Syntax

See [PDMWConnection::Projects](#).

See Also

[IPDMWConnection Interface](#)
[IPDMWConnection Members](#)

Availability

SOLIDWORKS Workgroup PDM 2003 FCS

SOLIDWORKS Workgroup PDM API Help

[Send comments on this topic.](#)

Refresh Method (IPDMWConnection)

[See Also](#)



[PDMWorks.Interop.pdmworks Namespace](#) > [IPDMWConnection Interface](#) : Refresh Method (IPDMWConnection)

Refreshes the object model using the data in the vault.

.NET Syntax

Visual Basic (Declaration)

```
Sub Refresh()
```

Visual Basic (Usage)



```
Dim instance As IPDMWConnection  
instance.Refresh()
```

C#

```
void Refresh()
```

C++/CLI

```
void Refresh();
```

Visual Basic for Applications (VBA) Syntax

See [PDMWConnection::Refresh](#).

See Also

[IPDMWConnection Interface](#)
[IPDMWConnection Members](#)
[IPDMWDocument Interface](#)

Availability

SOLIDWORKS Workgroup PDM 2003 FCS

Search Method (IPDMWConnection)

[See Also](#) [Example](#)



[PDMWorks.Interop.pdmworks Namespace](#) > [IPDMWConnection Interface](#) : Search Method (IPDMWConnection)

Searches the vault using the specified search options.

.NET Syntax

Visual Basic (Declaration)

```
Function Search( _
    ByVal pSearchOptions As PDMWSearchOptions _
) As PDMWSearchResults
```

Visual Basic (Usage)



```
Dim instance As IPDMWConnection
Dim pSearchOptions As PDMWSearchOptions
Dim value As PDMWSearchResults

value = instance.Search(pSearchOptions)
```

C#

```
PDMWSearchResults Search(
    PDMWSearchOptions pSearchOptions
)
```

C++/CLI

```
PDMWSearchResults^ Search(
    & PDMWSearchOptions^ pSearchOptions
)
```

Parameters

pSearchOptions
[IPDMWSearchOptions](#) object

Return Value

[IPDMWSearchResults](#) object

Visual Basic for Applications (VBA) Syntax

See [PDMWConnection::Search](#).

Example

[Create Search Criteria and Search Vault \(VBA\)](#)

See Also

[IPDMWConnection Interface](#)
[IPDMWConnection Members](#)

Availability

SOLIDWORKS Workgroup PDM 2006 FCS

Statuses Property (IPDMWConnection)

[See Also](#)



[PDMWorks.Interop.pdmworks Namespace](#) > [IPDMWConnection Interface](#) : Statuses Property (IPDMWConnection)

Gets the defined lifecycle statuses.

.NET Syntax

Visual Basic (Declaration)

ReadOnly Property Statuses As System.Object

Visual Basic (Usage)



```
Dim instance As IPDMWConnection
Dim value As System.Object

value = instance.Statuses
```

C#

```
System.Object Statuses {get;}
```

C++/CLI

```
property System.Object^ Statuses {
    System.Object^ get();
}
```

Property Value

Array of strings of defined lifecycle statuses

Visual Basic for Applications (VBA) Syntax

See [PDMWConnection::Statuses](#).

See Also

[IPDMWConnection Interface](#)
[IPDMWConnection Members](#)
[IPDMWDocument::ChangeStatus Method](#)
[IPDMWDocument::GetStatus Method](#)

Availability

SOLIDWORKS Workgroup PDM 2005 FCS

SOLIDWORKS Workgroup PDM API Help

[Send comments](#) on this topic.

Users Property (IPDMWConnection)

[See Also](#)



[PDMWorks.Interop.pdmworks Namespace](#) > [IPDMWConnection Interface](#) : Users Property (IPDMWConnection)

Gets a collection of users.

.NET Syntax

Visual Basic (Declaration)

ReadOnly Property Users As PDMWUsers

Visual Basic (Usage)



```
Dim instance As IPDMWConnection
Dim value As PDMWUsers

value = instance.Users
```

C#

```
PDMWUsers Users {get;}
```

C++/CLI

```
property PDMWUsers^ Users {  
    PDMWUsers^ get();  
}
```

Property Value

[IPDMWUsers](#) collection

Visual Basic for Applications (VBA) Syntax

See [PDMWConnection::Users](#).

See Also

[IPDMWConnection Interface](#)
[IPDMWConnection Members](#)

Availability

SOLIDWORKS Workgroup PDM 2004 FCS