

PDMWorks API (NET, legacy) — Reference (3/4): IPDMWGroup-IPDMWProperty

SOLIDWORKS API Documentation (converted from CHM)

IPDMWGroup (Type)

IPDMWGroup Interface

[See Also](#) [Members](#)



[PDMWorks.Interop.pdmworks Namespace](#) : IPDMWGroup Interface

Provides access to a group object. Typically, users assigned to the same projects are also assigned to the same group.

NOTE: Click the **Members** link, located near the top of the topic, to see this interface's methods and properties.

.NET Syntax

Visual Basic (Declaration)

```
Public Interface IPDMWGroup
```

Visual Basic (Usage)



```
Dim instance As IPDMWGroup
```

C#

```
public interface IPDMWGroup
```

C++/CLI

```
public interface class IPDMWGroup
```

Visual Basic for Applications (VBA) Syntax

See [PDMWGroup](#).

Accessors

[IPDMWConnection::CreateGroup](#)

[IPDMWGroups::Item](#)

See Also

- [IPDMWGroup Members](#)
- [PDMWorks.Interop.pdmworks Namespace](#)
- [IPDMWGroups Interface](#)
- [IPDMWUser Interface](#)
- [IPDMWUsers Interface](#)

IPDMWGroup Interface Members

[See Also](#) [Properties](#) [Methods](#)



[PDMWorks.Interop.pdmworks Namespace](#) : IPDMWGroup Interface

The following tables list the members exposed by [IPDMWGroup](#).

Public Properties

Name	Description
IsAdmin	Gets whether this group is a vault administrator.
Name	Gets or sets the name of this group.
Users	Gets the users in this group.

[Top](#)

Public Methods

Name	Description
 AddUser	Adds the specified user to this group.
 RemoveUser	Removes the specified user from a group.

[Top](#)

 See Also

[IPDMWGroup Interface](#)
[PDMWorks.Interop.pdmworks Namespace](#)
[IPDMWGroups Interface](#)
[IPDMWUser Interface](#)
[IPDMWUsers Interface](#)

SOLIDWORKS Workgroup PDM API Help

[Send comments on this topic.](#)

IPDMWGroup Interface Methods

[See Also](#)



[PDMWorks.Interop.pdmworks Namespace](#) : IPDMWGroup Interface

For a list of all members of this type, see [IPDMWGroup members](#).

 Public Methods

Name	Description
 AddUser	Adds the specified user to this group.
 RemoveUser	Removes the specified user from a group.

[Top](#)

 See Also

[IPDMWGroup Interface](#)
[PDMWorks.Interop.pdmworks Namespace](#)
[IPDMWGroups Interface](#)
[IPDMWUser Interface](#)
[IPDMWUsers Interface](#)

SOLIDWORKS Workgroup PDM API Help

[Send comments on this topic.](#)

IPDMWGroup Interface Properties

[See Also](#)



[PDMWorks.Interop.pdmworks Namespace](#) : IPDMWGroup Interface

For a list of all members of this type, see [IPDMWGroup members](#).

 Public Properties

Name	Description
 IsAdmin	Gets whether this group is a vault administrator.
 Name	Gets or sets the name of this group.
 Users	Gets the users in this group.

[Top](#)

 See Also

[IPDMWGroup Interface](#)
[PDMWorks.Interop.pdmworks Namespace](#)
[IPDMWGroups Interface](#)
[IPDMWUser Interface](#)
[IPDMWUsers Interface](#)

SOLIDWORKS Workgroup PDM API Help

[Send comments on this topic.](#)

AddUser Method (IPDMWGroup)

[See Also](#)

 

[PDMWorks.Interop.pdmworks Namespace](#) > [IPDMWGroup Interface](#) : AddUser Method (IPDMWGroup)

Adds the specified user to this group.

.NET Syntax

Visual Basic (Declaration)

```
Sub AddUser( _  
    ByVal userName As System.String _  
)
```

Visual Basic (Usage)



```
Dim instance As IPDMWGroup  
Dim userName As System.String  
  
instance.AddUser(userName)
```

C#

```
void AddUser(  
    System.string userName  
)
```

C++/CLI

```
void AddUser(  
& System.String^ userName  
)
```

Parameters

userName
Name of user to add to the group

Visual Basic for Applications (VBA) Syntax

See [PDMWGroup.AddUser](#).

Remarks

Only a vault administrator can use this method.

See Also

[IPDMWGroup Interface](#)
[IPDMWGroup Members](#)
[IPDMWConnection.CreateUser Method](#)
[IPDMWConnection.DeleteUser Method](#)
[IPDMWGroup.RemoveUser Method](#)
[IPDMWProject.SetUserPermissions Method](#)

Availability

SOLIDWORKS Workgroup PDM 2006 FCS

SOLIDWORKS Workgroup PDM API Help

[Send comments on this topic.](#)

IsAdmin Property (IPDMWGroup)

[See Also](#)



[PDMWorks.Interop.pdmworks Namespace](#) > [IPDMWGroup Interface](#) : IsAdmin Property (IPDMWGroup)

Gets whether this group is a vault administrator.

.NET Syntax

Visual Basic (Declaration)

```
ReadOnly Property IsAdmin As System.Boolean
```

Visual Basic (Usage)



```
Dim instance As IPDMWGroup
Dim value As System.Boolean

value = instance.IsAdmin
```

C#

```
System.bool IsAdmin {get;}
```

C++/CLI

```
property System.bool IsAdmin {
    System.bool get();
}
```

Property Value

True if this group is a vault administrator, false if not

Visual Basic for Applications (VBA) Syntax

See [PDMWGroup::IsAdmin](#).

See Also

[IPDMWGroup Interface](#)
[IPDMWGroup Members](#)

Availability

SOLIDWORKS Workgroup PDM 2007 SP2

SOLIDWORKS Workgroup PDM API Help

[Send comments](#) on this topic.

Name Property (IPDMWGroup)

[See Also](#)



[PDMWorks.Interop.pdmworks Namespace](#) > [IPDMWGroup Interface](#) : Name Property (IPDMWGroup)

Gets or sets the name of this group.

.NET Syntax

Visual Basic (Declaration)

```
Property Name As System.String
```

Visual Basic (Usage)



```
Dim instance As IPDMWGroup
Dim value As System.String

instance.Name = value

value = instance.Name
```

C#

```
System.string Name {get; set;}
```

C++/CLI

```
property System.String^ Name {
    System.String^ get();
    void set ( & System.String^ value);
}
```

Visual Basic for Applications (VBA) Syntax

See [PDMWGroup::Name](#).

Remarks

Only a vault administrator can set the name of this group.

See Also

[IPDMWGroup Interface](#)
[IPDMWGroup Members](#)

Availability

SOLIDWORKS Workgroup PDM 2006 FCS

SOLIDWORKS Workgroup PDM API Help

[Send comments](#) on this topic.

RemoveUser Method (IPDMWGroup)

[See Also](#)



[PDMWorks.Interop.pdmworks Namespace](#) > [IPDMWGroup Interface](#) : RemoveUser Method (IPDMWGroup)

Removes the specified user from a group.

.NET Syntax

Visual Basic (Declaration)

```
Sub RemoveUser( _  
    ByVal userName As System.String _  
)
```

Visual Basic (Usage)



```
Dim instance As IPDMWGroup  
Dim userName As System.String  
  
instance.RemoveUser(userName)
```

C#

```
void RemoveUser(  
    System.string userName  
)
```

C++/CLI

```
void RemoveUser(  
& System.String^ userName  
)
```

Parameters

userName
Name of user to remove from group

Visual Basic for Applications (VBA) Syntax

See [PDMWGroup::RemoveUser](#).

Remarks

Only a vault administrator can use this method.

See Also

[IPDMWGroup Interface](#)
[IPDMWGroup Members](#)
[IPDMWGroup::SetUserPermissions Method](#)
[IPDMWGroup::AddUser Method](#)

[IPDMWConnection::CreateUser Method](#)
[IPDMWConnection::DeleteUser Method](#)

Availability

SOLIDWORKS Workgroup PDM 2006 FCS

SOLIDWORKS Workgroup PDM API Help

[Send comments on this topic.](#)

Users Property (IPDMWGroup)

[See Also](#)



[PDMWorks.Interop.pdmworks Namespace](#) > [IPDMWGroup Interface](#) : Users Property (IPDMWGroup)

Gets the users in this group.

.NET Syntax

Visual Basic (Declaration)

ReadOnly Property Users As PDMWUsers

Visual Basic (Usage)



```
Dim instance As IPDMWGroup
Dim value As PDMWUsers

value = instance.Users
```

C#

```
PDMWUsers Users {get;}
```

C++/CLI

```
property PDMWUsers^ Users {
    PDMWUsers^ get();
}
```

Property Value

[IPDMWUsers](#) collection

Visual Basic for Applications (VBA) Syntax

See [PDMWGroup::Users](#).

See Also

[IPDMWGroup Interface](#)
[IPDMWGroup Members](#)

Availability

SOLIDWORKS Workgroup PDM 2004 FCS

IPDMWGroups (Type)

IPDMWGroups Interface

[See Also](#) [Members](#)



[PDMWorks.Interop.pdmworks Namespace](#) : IPDMWGroups Interface

Provides access to a collection of [IPDMWGroup](#) objects.

NOTE: Click the **Members** link, located near the top of the topic, to see this interface's methods and properties.

.NET Syntax

Visual Basic (Declaration)

Public Interface IPDMWGroups

Visual Basic (Usage)

Dim instance As [IPDMWGroups](#)

C#

public interface IPDMWGroups

C++/CLI

public interface class IPDMWGroups

Visual Basic for Applications (VBA) Syntax

See [PDMWGroups](#).

Accessors

[IPDMWConnection::Groups](#)

See Also

[IPDMWGroups Members](#)
[PDMWorks.Interop.pdmworks Namespace](#)
[IPDMWGroup Interface](#)
[IPDMWUser Interface](#)
[IPDMWUsers Interface](#)

IPDMWGroups Interface Members

[See Also](#) [Properties](#)



[PDMWorks.Interop.pdmworks Namespace](#) : IPDMWGroups Interface

The following tables list the members exposed by [IPDMWGroups](#).

Public Properties

Name	Description
Count	Gets the number of groups.
Item	Gets the specified group.

[Top](#)

See Also

[IPDMWGroups Interface](#)
[PDMWorks.Interop.pdmworks Namespace](#)
[IPDMWGroup Interface](#)
[IPDMWUser Interface](#)
[IPDMWUsers Interface](#)

IPDMWGroups Interface Properties

[See Also](#)

[PDMWorks.Interop.pdmworks Namespace](#) : IPDMWGroups Interface

For a list of all members of this type, see [IPDMWGroups members](#).

Public Properties

Name	Description
 Count	Gets the number of groups.
 Item	Gets the specified group.

[Top](#)

See Also

[IPDMWGroups Interface](#)
[PDMWorks.Interop.pdmworks Namespace](#)
[IPDMWGroup Interface](#)
[IPDMWUser Interface](#)
[IPDMWUsers Interface](#)

Count Property (IPDMWGroups)

[See Also](#)



[PDMWorks.Interop.pdmworks Namespace](#) > [IPDMWGroups Interface](#) : Count Property (IPDMWGroups)

Gets the number of groups.

.NET Syntax

Visual Basic (Declaration)

ReadOnly Property Count As System.Integer

Visual Basic (Usage)



```
Dim instance As IPDMWGroups  
Dim value As System.Integer  
  
value = instance.Count
```

C#

```
System.int Count {get;}
```

C++/CLI

```
property System.int Count {  
    System.int get();  
}
```

Property Value

Number of groups

Visual Basic for Applications (VBA) Syntax

See [PDMWGroups.Count](#).

See Also

[IPDMWGroups Interface](#)
[IPDMWGroups Members](#)
[IPDMWGroups.Item Property](#)

Availability

Item Property (IPDMWGroups)

[See Also](#)



[PDMWorks.Interop.pdmworks Namespace](#) > [IPDMWGroups Interface](#) : Item Property (IPDMWGroups)

Gets the specified group.

.NET Syntax

Visual Basic (Declaration)

```
ReadOnly Default Property Item( _  
    ByVal Index As System.Object _  
) As PDMWGroup
```

Visual Basic (Usage)



```
Dim instance As IPDMWGroups  
Dim Index As System.Object  
Dim value As PDMWGroup
```

```
value = instance.Item(Index)
```

C#

```
PDMWGroup this[  
    System.object Index  
]; {get;}
```

C++/CLI

```
property PDMWGroup^ default [System.Object^] {  
    PDMWGroup^ get(System.Object^ Index);  
}
```

Parameters

Index

Number indicating which group to get

Property Value

[IPDMWGroup](#)

Visual Basic for Applications (VBA) Syntax

See [PDMWGroups::Item](#).

See Also

[IPDMWGroups Interface](#)
[IPDMWGroups Members](#)
[IPDMWGroups::Count Property](#)

Availability

SOLIDWORKS Workgroup PDM 2004 FCS

IPDMLink (Type)

IPDMLink Interface

[See Also](#) [Members](#) [Example](#)



[PDMWorks.Interop.pdmworks Namespace](#) : IPDMLink Interface

Provides access to a link object. A link contains basic information about a referenced document.

NOTE: Click the **Members** link, located near the top of the topic, to see this interface's methods and properties.

.NET Syntax

Visual Basic (Declaration)

```
Public Interface IPDMLink
```

Visual Basic (Usage)



```
Dim instance As IPDMLink
```

C#

```
public interface IPDMLink
```

C++/CLI

```
public interface class IPDMLink
```

Visual Basic for Applications (VBA) Syntax

See [PDMLink](#).

Example

[List Assemblies Where Part Used \(VBA\)](#)

Accessors

[IPDMLinks.Item](#)

See Also

[IPDMLink Members](#)
[PDMWorks.Interop.pdmworks Namespace](#)
[IPDMLinks Interface](#)

IPDMLink Interface Members

[See Also](#) [Properties](#)



[PDMWorks.Interop.pdmworks Namespace](#) : IPDMLink Interface

The following tables list the members exposed by [IPDMLink](#).

Public Properties

Name	Description
 Config	Gets the name of the configuration for this link.
 Document	Gets the document for this link.
 Name	Gets the name of the document for this link.
 project	Gets the name of the project for the document for this link.
 Quantity	Gets the number of documents associated with this link.

 Revision	Gets the revision of the document associated with this link.
 Type	Gets the type of link.

[Top](#)

 See Also

[IPDMLink Interface](#)
[PDMWorks.Interop.pdmworks Namespace](#)
[IPDMLinks Interface](#)

SOLIDWORKS Workgroup PDM API Help

[Send comments on this topic.](#)

IPDMLink Interface Properties

[See Also](#)



[PDMWorks.Interop.pdmworks Namespace](#) : IPDMLink Interface

For a list of all members of this type, see [IPDMLink members](#).

 Public Properties

Name	Description
 Config	Gets the name of the configuration for this link.
 Document	Gets the document for this link.
 Name	Gets the name of the document for this link.
 Project	Gets the name of the project for the document for this link.
 Quantity	Gets the number of documents associated with this link.
 Revision	Gets the revision of the document associated with this link.
 Type	Gets the type of link.

[Top](#)

 See Also

[IPDMLink Interface](#)
[PDMWorks.Interop.pdmworks Namespace](#)
[IPDMLinks Interface](#)

SOLIDWORKS Workgroup PDM API Help

[Send comments on this topic.](#)

Config Property (IPDMLink)

[See Also](#)



[PDMWorks.Interop.pdmworks Namespace](#) > [IPDMLink Interface](#) : Config Property (IPDMLink)

Gets the name of the configuration for this link.

 .NET Syntax

Visual Basic (Declaration)

Property Config As System.String

Visual Basic (Usage)



```
Dim instance As IPDMLink  
Dim value As System.String
```

```
instance.Config = value
```

```
value = instance.Config
```

C#

```
System.string Config {get; set;}
```

C++/CLI

```
property System.String^ Config {
    System.String^ get();
    void set ( & System.String^ value);
}
```

Property Value

Name of the configuration for this link

Visual Basic for Applications (VBA) Syntax

See [PDMWLink::Config](#).

Remarks

If the source object is an [IPDMWDocument](#) object, then the name of the configuration is not available.

See Also

[IPDMWLink Interface](#)
[IPDMWLink Members](#)

Availability

SOLIDWORKS Workgroup PDM 2003 FCS

SOLIDWORKS Workgroup PDM API Help

[Send comments on this topic.](#)

Document Property (IPDMWLink)

[See Also](#)



[PDMWorks.Interop.pdmworks Namespace](#) > [IPDMWLink Interface](#) : Document Property (IPDMWLink)

Gets the document for this link.

.NET Syntax

Visual Basic (Declaration)

ReadOnly Property Document As PDMWDocument

Visual Basic (Usage)



```
Dim instance As IPDMWLink
Dim value As PDMWDocument

value = instance.Document
```

C#

```
PDMWDocument Document {get;}
```

C++/CLI

```
property PDMWDocument^ Document {
    PDMWDocument^ get();
}
```

Property Value

[IPDMWDocument](#) object for this link

Visual Basic for Applications (VBA) Syntax

See [PDMWLink::Document](#).

See Also

Availability

SOLIDWORKS Workgroup PDM 2003 FCS

SOLIDWORKS Workgroup PDM API Help

[Send comments on this topic.](#)

Name Property (IPDMLink)

[See Also](#)



[PDMWorks.Interop.pdmworks Namespace](#) > [IPDMLink Interface](#) : Name Property (IPDMLink)

Gets the name of the document for this link.

.NET Syntax

Visual Basic (Declaration)

Property Name As System.String

Visual Basic (Usage)



```
Dim instance As IPDMLink  
Dim value As System.String
```

```
instance.Name = value
```

```
value = instance.Name
```

C#

```
System.string Name {get; set;}
```

C++/CLI

```
property System.String^ Name {  
    System.String^ get();  
    void set ( & System.String^ value);  
}
```

Property Value

Name of the document for this link

Visual Basic for Applications (VBA) Syntax

See [PDMLink::Name](#).

See Also

[IPDMLink Interface](#)
[IPDMLink Members](#)

Availability

SOLIDWORKS Workgroup PDM 2003 FCS

SOLIDWORKS Workgroup PDM API Help

[Send comments on this topic.](#)

project Property (IPDMLink)

[See Also](#)



[PDMWorks.Interop.pdmworks Namespace](#) > [IPDMLink Interface](#) : project Property (IPDMLink)

Gets the name of the project for the document for this link.

.NET Syntax

Visual Basic (Declaration)

Property project As System.String

Visual Basic (Usage)



```
Dim instance As IPDMLink
Dim value As System.String

instance.project = value
value = instance.project
```

C#

```
System.string project {get; set;}
```

C++/CLI

```
property System.String^ project {
    System.String^ get();
    void set ( & System.String^ value);
}
```

Property Value

Name of project for this link

Visual Basic for Applications (VBA) Syntax

See [PDMWLink:project](#).

See Also

[IPDMLink Interface](#)
[IPDMLink Members](#)

Availability

SOLIDWORKS Workgroup PDM 2003 SP3

SOLIDWORKS Workgroup PDM API Help

[Send comments on this topic.](#)

Quantity Property (IPDMLink)

[See Also](#)



[PDMWorks.Interop.pdmworks Namespace](#) > [IPDMLink Interface](#) : Quantity Property (IPDMLink)

Gets the number of documents associated with this link.

.NET Syntax

Visual Basic (Declaration)

Property Quantity As System.Integer

Visual Basic (Usage)



```
Dim instance As IPDMLink
Dim value As System.Integer

instance.Quantity = value
value = instance.Quantity
```

C#

```
System.int Quantity {get; set;}
```

C++/CLI

```
property System.int Quantity {
    System.int get();
    void set ( & System.int value);
}
```

Property Value

Number of documents associated with this link

Visual Basic for Applications (VBA) Syntax

See [PDMWLink::Quantity](#).

See Also

[IPDMWLink Interface](#)
[IPDMWLink Members](#)

Availability

SOLIDWORKS Workgroup PDM 2003 FCS

SOLIDWORKS Workgroup PDM API Help

[Send comments](#) on this topic.

Revision Property (IPDMWLink)

[See Also](#)



[PDMWorks.Interop.pdmworks Namespace](#) > [IPDMWLink Interface](#) : Revision Property (IPDMWLink)

Gets the revision of the document associated with this link.

.NET Syntax

Visual Basic (Declaration)

Property Revision As System.String

Visual Basic (Usage)



```
Dim instance As IPDMWLink
Dim value As System.String

instance.Revision = value

value = instance.Revision
```

C#

```
System.string Revision {get; set;}
```

C++/CLI

```
property System.String^ Revision {
    System.String^ get();
    void set ( & System.String^ value);
}
```

Property Value

Revision of the document associated with this link

Visual Basic for Applications (VBA) Syntax

See [PDMWLink::Revision](#).

See Also

[IPDMWLink Interface](#)
[IPDMWLink Members](#)
[IPDMWConnection::BumpRevision Method](#)
[IPDMWConnection::Revision Property](#)
[IPDMWConnection::RevisionLabels Property](#)
[IPDMWConnection::Revisions Property](#)

Availability

SOLIDWORKS Workgroup PDM 2003 FCS

SOLIDWORKS Workgroup PDM API Help

[Send comments on this topic.](#)

Type Property (IPDMWLink)

[See Also](#)



[PDMWorks.Interop.pdmworks Namespace](#) > [IPDMWLink Interface](#) : Type Property (IPDMWLink)

Gets the type of link.

.NET Syntax

Visual Basic (Declaration)

Property Type As [PDMWLinkType](#)

Visual Basic (Usage)



```
Dim instance As IPDMWLink  
Dim value As PDMWLinkType
```

```
instance.Type = value
```

```
value = instance.Type
```

C#

```
PDMWLinkType Type {get; set;}
```

C++/CLI

```
property PDMWLinkType Type {  
    PDMWLinkType get();  
    void set ( & PDMWLinkType value);  
}
```

Property Value

Type of link as defined by [PDMWLinkType](#)

Visual Basic for Applications (VBA) Syntax

See [PDMWLink::Type](#).

See Also

[IPDMWLink Interface](#)
[IPDMWLink Members](#)

Availability

SOLIDWORKS Workgroup PDM 2003 FCS

IPDMLinks (Type)

IPDMLinks Interface

[See Also](#) [Members](#) [Example](#)



[PDMWorks.Interop.pdmworks Namespace](#) : IPDMLinks Interface

Contains [IPDMLink](#) objects.

NOTE: Click the **Members** link, located near the top of the topic, to see this interface's methods and properties.

.NET Syntax

Visual Basic (Declaration)

Public Interface IPDMLinks

Visual Basic (Usage)

Dim instance As [IPDMLinks](#)

C#

public interface IPDMLinks

C++/CLI

public interface class IPDMLinks

Visual Basic for Applications (VBA) Syntax

See [PDMWLinks](#).

Example

[List Assemblies Where Part Used \(VBA\)](#)

Accessors

[IPDMWConfiguration::ExtReferences](#)
[IPDMWConfiguration::ExtWhereUsed](#)
[IPDMWConfiguration::References](#)
[IPDMWConfiguration::WhereUsed](#)
[IPDMWDocument::ExtReferences](#)
[IPDMWDocument::ExtWhereUsed](#)
[IPDMWDocument::References](#)
[IPDMDoucment::WhereUsed](#)

See Also

[IPDMLinks Members](#)
[PDMWorks.Interop.pdmworks Namespace](#)
[IPDMLink Interface](#)

IPDMLinks Interface Members

[See Also](#) [Properties](#)



[PDMWorks.Interop.pdmworks Namespace](#) : IPDMLinks Interface

The following tables list the members exposed by [IPDMLinks](#).

Public Properties

Name	Description
 Count	Gets the number of links.
 Item	Gets the specified link.

[Top](#)

 See Also

[IPDMLinks Interface](#)
[PDMWorks.Interop.pdmworks Namespace](#)
[IPDMLink Interface](#)

SOLIDWORKS Workgroup PDM API Help

[Send comments on this topic.](#)

IPDMLinks Interface Properties

[See Also](#)



[PDMWorks.Interop.pdmworks Namespace](#) : IPDMLinks Interface

For a list of all members of this type, see [IPDMLinks members](#).

 Public Properties

Name	Description
 Count	Gets the number of links.
 Item	Gets the specified link.

[Top](#)

 See Also

[IPDMLinks Interface](#)
[PDMWorks.Interop.pdmworks Namespace](#)
[IPDMLink Interface](#)

SOLIDWORKS Workgroup PDM API Help

[Send comments on this topic.](#)

Count Property (IPDMLinks)

[See Also](#)



[PDMWorks.Interop.pdmworks Namespace](#) > [IPDMLinks Interface](#) : Count Property (IPDMLinks)

Gets the number of links.

 .NET Syntax

Visual Basic (Declaration)

ReadOnly Property Count As System.Integer

Visual Basic (Usage)



```
Dim instance As IPDMLinks  
Dim value As System.Integer  
  
value = instance.Count
```

C#

```
System.int Count {get;}
```

C++/CLI

```
property System.int Count {  
    System.int get();  
}
```

Property Value

Number of links

Visual Basic for Applications (VBA) Syntax

See [PDMWLinks.Count](#).

See Also

[IPDMWLinks Interface](#)
[IPDMWLinks Members](#)
[IPDMWLinks.Item Property](#)

Availability

SOLIDWORKS Workgroup PDM 2003 FCS

SOLIDWORKS Workgroup PDM API Help

[Send comments](#) on this topic.

Item Property (IPDMWLinks)

[See Also](#)



[PDMWorks.Interop.pdmworks Namespace](#) > [IPDMWLinks Interface](#) : Item Property (IPDMWLinks)

Gets the specified link.

.NET Syntax

Visual Basic (Declaration)

```
ReadOnly Default Property Item( _  
    ByVal Index As System.Integer _  
) As PDMWLink
```

Visual Basic (Usage)



```
Dim instance As IPDMWLinks  
Dim Index As System.Integer  
Dim value As PDMWLink
```

```
value = instance.Item(Index)
```

C#

```
PDMWLink this[  
    System.int Index  
]; {get;}
```

C++/CLI

```
property PDMWLink^ default [System.int] {  
    PDMWLink^ get(System.int Index);  
}
```

Parameters

Index

Number indicating which link to get

Property Value

[IPDMLink](#)

Visual Basic for Applications (VBA) Syntax

See [PDMWLinks.Item](#).

See Also

[IPDMWLinks Interface](#)
[IPDMWLinks Members](#)
[IPDMWLinks.Count Property](#)

IPDMWProject (Type)

IPDMWProject Interface

[See Also](#) [Members](#)



[PDMWorks.Interop.pdmworks Namespace](#) : IPDMWProject Interface

Provides access to the properties of vault projects.

NOTE: Click the **Members** link, located near the top of the topic, to see this interface's methods and properties.

.NET Syntax

Visual Basic (Declaration)

Public Interface IPDMWProject

Visual Basic (Usage)

Dim instance As [IPDMWProject](#)

C#

public interface IPDMWProject

C++/CLI

public interface class IPDMWProject

Visual Basic for Applications (VBA) Syntax

See [PDMWProject](#).

Accessors

[IPDMWConnection::CreateProject](#)
[IPDMWProject::CreateSubProject](#)
[IPDMWProject::Parent](#)
[IPDMWProjects::Item](#)

See Also

[IPDMWProject Members](#)
[PDMWorks.Interop.pdmworks Namespace](#)
[IPDMWProjects Interface](#)

IPDMWProject Interface Members

[See Also](#) [Properties](#) [Methods](#)



[PDMWorks.Interop.pdmworks Namespace](#) : IPDMWProject Interface

The following tables list the members exposed by [IPDMWProject](#).

Public Properties

Name	Description
AllowRead	Gets whether the user has read access to this project.
AllowWrite	Gets whether the user has write access to this project.
Description	Gets or sets the description for this project.
DocumentCount	Gets the number of documents in this project.
DocumentList	Gets a the list of document names for this project.

 Documents	Gets the documents for this project.
 Name	Gets or sets the name of this project.
 Parent	Gets or sets the parent project.
 SubProjects	Gets the child projects for this project.

[Top](#)

Public Methods

Name	Description
 CreateSubProject	Creates a child project to this project.
 SetUserPermissions	Sets the permission for the specified user or group's project.

[Top](#)

See Also

[IPDMWProject Interface](#)
[PDMWorks.Interop.pdmworks Namespace](#)
[IPDMWProjects Interface](#)

SOLIDWORKS Workgroup PDM API Help

[Send comments on this topic.](#)

IPDMWProject Interface Methods

[See Also](#)

 [PDMWorks.Interop.pdmworks Namespace](#) : IPDMWProject Interface

For a list of all members of this type, see [IPDMWProject members](#).

Public Methods

Name	Description
 CreateSubProject	Creates a child project to this project.
 SetUserPermissions	Sets the permission for the specified user or group's project.

[Top](#)

See Also

[IPDMWProject Interface](#)
[PDMWorks.Interop.pdmworks Namespace](#)
[IPDMWProjects Interface](#)

SOLIDWORKS Workgroup PDM API Help

[Send comments on this topic.](#)

IPDMWProject Interface Properties

[See Also](#)

 [PDMWorks.Interop.pdmworks Namespace](#) : IPDMWProject Interface

For a list of all members of this type, see [IPDMWProject members](#).

Public Properties

Name	Description
 AllowRead	Gets whether the user has read access to this project.
 AllowWrite	Gets whether the user has write access to this project.
 Description	Gets or sets the description for this project.
 DocumentCount	Gets the number of documents in this project.
 DocumentList	Gets a the list of document names for this project.
 Documents	Gets the documents for this project.
 Name	Gets or sets the name of this project.
 Parent	Gets or sets the parent project.
SubProjects	Gets the child projects for this project.



[Top](#)

See Also

[IPDMWProject Interface](#)
[PDMWorks.Interop.pdmworks Namespace](#)
[IPDMWProjects Interface](#)

SOLIDWORKS Workgroup PDM API Help

[Send comments on this topic.](#)

AllowRead Property (IPDMWProject)

[See Also](#)



[PDMWorks.Interop.pdmworks Namespace](#) > [IPDMWProject Interface](#) : AllowRead Property (IPDMWProject)

Gets whether the user has read access to this project.

.NET Syntax

Visual Basic (Declaration)

```
Property AllowRead As System.Integer
```

Visual Basic (Usage)



```
Dim instance As IPDMWProject  
Dim value As System.Integer  
  
instance.AllowRead = value  
value = instance.AllowRead
```

C#

```
System.int AllowRead {get; set;}
```

C++/CLI

```
property System.int AllowRead {  
    System.int get();  
    void set ( & System.int value);  
}
```

Property Value

0 if not allowed, 1 if allowed

Visual Basic for Applications (VBA) Syntax

See [PDMWProject::AllowRead](#).

See Also

[IPDMWProject Interface](#)
[IPDMWProject Members](#)
[IPDMWProject::AllowWrite Property](#)

Availability

SOLIDWORKS Workgroup PDM 2003 FCS

SOLIDWORKS Workgroup PDM API Help

[Send comments on this topic.](#)

AllowWrite Property (IPDMWProject)

[See Also](#)



[PDMWorks.Interop.pdmworks Namespace](#) > [IPDMWProject Interface](#) : AllowWrite Property (IPDMWProject)

Gets whether the user has write access to this project.

.NET Syntax

Visual Basic (Declaration)

```
Property AllowWrite As System.Integer
```

Visual Basic (Usage)



```
Dim instance As IPDMWProject  
Dim value As System.Integer  
  
instance.AllowWrite = value  
value = instance.AllowWrite
```

C#

```
System.int AllowWrite {get; set;}
```

C++/CLI

```
property System.int AllowWrite {  
    System.int get();  
    void set ( & System.int value);  
}
```

Property Value

0 if not allowed, 1 if allowed

Visual Basic for Applications (VBA) Syntax

See [PDMWProject::AllowWrite](#).

See Also

[IPDMWProject Interface](#)
[IPDMWProject Members](#)
[IPDMWProject::AllowRead Property](#)

Availability

SOLIDWORKS Workgroup PDM 2003 FCS

SOLIDWORKS Workgroup PDM API Help

[Send comments](#) on this topic.

CreateSubProject Method (IPDMWProject)

[See Also](#)



[PDMWorks.Interop.pdmworks Namespace](#) > [IPDMWProject Interface](#) : CreateSubProject Method (IPDMWProject)

Creates a child project to this project.

.NET Syntax

Visual Basic (Declaration)

```
Function CreateSubProject( _  
    ByVal Name As System.String, _  
    ByVal Description As System.String _  
) As PDMWProject
```

Visual Basic (Usage)



```
Dim instance As IPDMWProject  
Dim Name As System.String  
Dim Description As System.String  
Dim value As PDMWProject
```

```
value = instance.CreateSubProject(Name, Description)
```

C#

```
PDMWProject CreateSubProject(  
    System.string Name,  
    System.string Description  
)
```

C++/CLI

```
PDMWProject^ CreateSubProject(  
& System.String^ Name,  
& System.String^ Description  
)
```

Parameters

Name

New child project name

Description

Child project description

Return Value

Newly created [IPDMWProject](#) object

Visual Basic for Applications (VBA) Syntax

See [PDMWProject::CreateSubProject](#).

See Also

[IPDMWProject Interface](#)

[IPDMWProject Members](#)

[IPDMWProject::SubProjects Property](#)

Availability

SOLIDWORKS Workgroup PDM 2005 FCS

SOLIDWORKS Workgroup PDM API Help

[Send comments on this topic.](#)

Description Property (IPDMWProject)

[See Also](#)



[PDMWorks.Interop.pdmworks Namespace](#) > [IPDMWProject Interface](#) : Description Property (IPDMWProject)

Gets or sets the description for this project.

.NET Syntax

Visual Basic (Declaration)

```
Property Description As System.String
```

Visual Basic (Usage)



```
Dim instance As IPDMWProject  
Dim value As System.String
```

```
instance.Description = value
```

```
value = instance.Description
```

C#

```
System.string Description {get; set;}
```

C++/CLI

```
property System.String^ Description {
    System.String^ get();
    void set ( & System.String^ value);
}
```

Property Value

Description for this project

Visual Basic for Applications (VBA) Syntax

See [PDMWProject::Description](#).

Remarks

Only a vault administrator can set the description.

See Also

[IPDMWProject Interface](#)
[IPDMWProject Members](#)

Availability

SOLIDWORKS Workgroup PDM 2003 FCS

SOLIDWORKS Workgroup PDM API Help

[Send comments on this topic.](#)

DocumentCount Property (IPDMWProject)

[See Also](#)



[PDMWorks.Interop.pdmworks Namespace](#) > [IPDMWProject Interface](#) : DocumentCount Property (IPDMWProject)

Gets the number of documents in this project.

.NET Syntax

Visual Basic (Declaration)

```
ReadOnly Property DocumentCount As System.Integer
```

Visual Basic (Usage)



```
Dim instance As IPDMWProject
Dim value As System.Integer

value = instance.DocumentCount
```

C#

```
System.int DocumentCount {get;}
```

C++/CLI

```
property System.int DocumentCount {
    System.int get();
}
```

Property Value

Number of documents in this project

Visual Basic for Applications (VBA) Syntax

See [PDMWProject::DocumentCount](#).

See Also

[IPDMWProject Interface](#)
[IPDMWProject Members](#)
[IPDMWProject::DocumentList Property](#)
[IPDMWProject::Documents Property](#)

Availability

SOLIDWORKS Workgroup PDM 2007 FCS

SOLIDWORKS Workgroup PDM API Help

[Send comments on this topic.](#)

DocumentList Property (IPDMWProject)

[See Also](#)



[PDMWorks.Interop.pdmworks Namespace](#) > [IPDMWProject Interface](#) : DocumentList Property (IPDMWProject)

Gets a the list of document names for this project.

.NET Syntax

Visual Basic (Declaration)

ReadOnly Property DocumentList As System.Object

Visual Basic (Usage)



```
Dim instance As IPDMWProject  
Dim value As System.Object
```

```
value = instance.DocumentList
```

C#

```
System.object DocumentList {get;}
```

C++/CLI

```
property System.Object^ DocumentList {  
    System.Object^ get();  
}
```

Property Value

Array document names

Visual Basic for Applications (VBA) Syntax

See [PDMWProject::DocumentList](#).

See Also

[IPDMWProject Interface](#)
[IPDMWProject Members](#)
[IPDMWProject::DocumentCount Property](#)
[IPDMWProject::Documents Property](#)

Availability

SOLIDWORKS Workgroup PDM 2007 FCS

SOLIDWORKS Workgroup PDM API Help

[Send comments on this topic.](#)

Documents Property (IPDMWProject)

[See Also](#)



[PDMWorks.Interop.pdmworks Namespace](#) > [IPDMWProject Interface](#) : Documents Property (IPDMWProject)

Gets the documents for this project.

.NET Syntax

Visual Basic (Declaration)

ReadOnly Property Documents As PDMWDocuments

Visual Basic (Usage)



```
Dim instance As IPDMWProject  
Dim value As PDMWDocuments
```

```
value = instance.Documents
```

C#

```
PDMWDocuments Documents {get;}
```

C++/CLI

```
property PDMWDocuments^ Documents {  
    PDMWDocuments^ get();  
}
```

Property Value

Collection of [documents](#) for this project

Visual Basic for Applications (VBA) Syntax

See [PDMWProject::Documents](#).

See Also

[IPDMWProject Interface](#)
[IPDMWProject Members](#)
[IPDMWProject::DocumentCount Property](#)
[IPDMWProject::DocumentList Property](#)
[IPDMWConnection::Documents Property](#)

Availability

SOLIDWORKS Workgroup PDM 2003 FCS

SOLIDWORKS Workgroup PDM API Help

[Send comments on this topic.](#)

Name Property (IPDMWProject)

[See Also](#)



[PDMWorks.Interop.pdmworks Namespace](#) > [IPDMWProject Interface](#) : Name Property (IPDMWProject)

Gets or sets the name of this project.

.NET Syntax

Visual Basic (Declaration)

```
Property Name As System.String
```

Visual Basic (Usage)



```
Dim instance As IPDMWProject  
Dim value As System.String
```

```
instance.Name = value
```

```
value = instance.Name
```

C#

```
System.string Name {get; set;}
```

C++/CLI

```
property System.String^ Name {
    System.String^ get();
    void set ( & System.String^ value);
}
```

Property Value

Name of this project

Visual Basic for Applications (VBA) Syntax

See [PDMWProject::Name](#).

See Also

[IPDMWProject Interface](#)
[IPDMWProject Members](#)

Availability

SOLIDWORKS Workgroup PDM 2003 FCS

SOLIDWORKS Workgroup PDM API Help

[Send comments](#) on this topic.

Parent Property (IPDMWProject)

[See Also](#)



[PDMWorks.Interop.pdmworks Namespace](#) > [IPDMWProject Interface](#) : Parent Property (IPDMWProject)

Gets or sets the parent project.

.NET Syntax

Visual Basic (Declaration)

Property Parent As PDMWProject

Visual Basic (Usage)



```
Dim instance As IPDMWProject
Dim value As PDMWProject
```

```
instance.Parent = value
```

```
value = instance.Parent
```

C#

```
PDMWProject Parent {get; set;}
```

C++/CLI

```
property PDMWProject^ Parent {
    PDMWProject^ get();
    void set ( & PDMWProject^ value);
}
```

Property Value

[Parent project](#)

Visual Basic for Applications (VBA) Syntax

See [PDMWProject::Parent](#).

Remarks

Only a vault administrator can set the parent of a project.

See Also

[IPDMWProject Interface](#)
[IPDMWProject Members](#)

Availability

SOLIDWORKS Workgroup PDM 2006 FCS

SOLIDWORKS Workgroup PDM API Help

[Send comments](#) on this topic.

SetUserPermissions Method (IPDMWProject)

[See Also](#)



[PDMWorks.Interop.pdmworks Namespace](#) > [IPDMWProject Interface](#) : SetUserPermissions Method (IPDMWProject)

Sets the permission for the specified user or group's project.

Visual Basic Syntax

Visual Basic (Declaration)

```
Function SetUserPermissions( _  
    ByVal Name As System.String, _  
    ByVal permissions As PDMWPermission _  
) As System.Boolean
```

Visual Basic (Usage)



```
Dim instance As IPDMWProject  
Dim Name As System.String  
Dim permissions As PDMWPermission  
Dim value As System.Boolean  
  
value = instance.SetUserPermissions(Name, permissions)
```

C#

```
System.bool SetUserPermissions(  
    System.string Name,  
    PDMWPermission permissions  
)
```

C++/CLI

```
System.bool SetUserPermissions(  
& System.String^ Name,  
& PDMWPermission permissions  
)
```

Parameters

Name

Name of user or group's project for which to set permissions

permissions

Permissions to set as defined in [PDMWPermission](#)

Return Value

True if the permissions are set, false if not

Visual Basic for Applications (VBA) Syntax

See [PDMWProject::SetUserPermissions](#).

Remarks

Only a vault administrator can use this method.

See Also

[IPDMWProject Interface](#)
[IPDMWProject Members](#)
[IPDMWConnection::CreateProject Method](#)
[IPDMWConnection::CreateUser Method](#)
[IPDMWConnection::DeleteProject Method](#)
[IPDMWConnection::DeleteUser Method](#)
[IPDMWGroup::AddUser Method](#)
[IPDMWGroup::RemoveUser Method](#)

Availability

SOLIDWORKS Workgroup PDM 2006 FCS

SOLIDWORKS Workgroup PDM API Help

[Send comments on this topic.](#)

SubProjects Property (IPDMWProject)

[See Also](#)



[PDMWorks.Interop.pdmworks Namespace](#) > [IPDMWProject Interface](#) : SubProjects Property (IPDMWProject)

Gets the child projects for this project.

.NET Syntax

Visual Basic (Declaration)

```
ReadOnly Property SubProjects As PDMWProjects
```

Visual Basic (Usage)



```
Dim instance As IPDMWProject  
Dim value As PDMWProjects
```

```
value = instance.SubProjects
```

C#

```
PDMWProjects SubProjects {get;}
```

C++/CLI

```
property PDMWProjects^ SubProjects {  
    PDMWProjects^ get();  
}
```

Property Value

Collection of child [projects](#) for this project

Visual Basic for Applications (VBA) Syntax

See [PDMWProject::SubProjects](#).

See Also

[IPDMWProject Interface](#)
[IPDMWProject Members](#)
[IPDMWProject::CreateSubProject Method](#)

Availability

SOLIDWORKS Workgroup PDM 2005 SP1

IPDMWProjects (Type)

IPDMWProjects Interface

[See Also](#) [Members](#)



[PDMWorks.Interop.pdmworks Namespace](#) : IPDMWProjects Interface

Contains [IPDMWProject](#) objects.

NOTE: Click the **Members** link, located near the top of the topic, to see this interface's methods and properties.

.NET Syntax

Visual Basic (Declaration)

Public Interface IPDMWProjects

Visual Basic (Usage)

Dim instance As [IPDMWProjects](#)

C#

public interface IPDMWProjects

C++/CLI

public interface class IPDMWProjects

Visual Basic for Applications (VBA) Syntax

See [PDMWProjects](#).

Accessors

[IPDMWConnection::Projects](#)

See Also

[IPDMWProjects Members](#)
[PDMWorks.Interop.pdmworks Namespace](#)
[IPDMWProject Interface](#)

IPDMWProjects Interface Members

[See Also](#) [Properties](#)



[PDMWorks.Interop.pdmworks Namespace](#) : IPDMWProjects Interface

The following tables list the members exposed by [IPDMWProjects](#).

Public Properties

Name	Description
Count	Gets the number of projects.
Item	Gets the project by name.

[Top](#)

See Also

[IPDMWProjects Interface](#)
[PDMWorks.Interop.pdmworks Namespace](#)
[IPDMWProject Interface](#)

IPDMWProjects Interface Properties

[See Also](#)



[PDMWorks.Interop.pdmworks Namespace](#) : IPDMWProjects Interface

For a list of all members of this type, see [IPDMWProjects members](#).

Public Properties

Name	Description
 Count	Gets the number of projects.
 Item	Gets the project by name.

[Top](#)

See Also

[IPDMWProjects Interface](#)
[PDMWorks.Interop.pdmworks Namespace](#)
[IPDMWProject Interface](#)

SOLIDWORKS Workgroup PDM API Help

[Send comments on this topic.](#)

Count Property (IPDMWProjects)

[See Also](#)



[PDMWorks.Interop.pdmworks Namespace](#) > [IPDMWProjects Interface](#) : Count Property (IPDMWProjects)

Gets the number of projects.

.NET Syntax

Visual Basic (Declaration)

ReadOnly Property Count As System.Integer

Visual Basic (Usage)



Dim instance As [IPDMWProjects](#)
Dim value As System.Integer

value = instance.Count

C#

System.int Count {get;}

C++/CLI

```
property System.int Count {  
    System.int get();  
}
```

Property Value

Number of projects

Visual Basic for Applications (VBA) Syntax

See [PDMWProjects.Count](#).

See Also

[IPDMWProjects Interface](#)
[IPDMWProjects Members](#)
[IPDMWProjects.Item Property](#)

Availability

SOLIDWORKS Workgroup PDM 2003 FCS

Item Property (IPDMWProjects)

[See Also](#)



[PDMWorks.Interop.pdmworks Namespace](#) > [IPDMWProjects Interface](#) : Item Property (IPDMWProjects)

Gets the project by name.

.NET Syntax

Visual Basic (Declaration)

```
ReadOnly Default Property Item( _  
    ByVal Index As System.Object _  
) As System.Object
```

Visual Basic (Usage)



```
Dim instance As IPDMWProjects  
Dim Index As System.Object  
Dim value As System.Object  
  
value = instance.Item(Index)
```

C#

```
System.object this[  
    System.object Index  
]; {get;}
```

C++/CLI

```
property System.Object^ default [System.Object^] {  
    System.Object^ get(System.Object^ Index);  
}
```

Parameters

Index

Number or name indicating the project to get

Property Value

[IPDMWProject](#)

Visual Basic for Applications (VBA) Syntax

See [PDMWProjects::Item](#).

See Also

[IPDMWProjects Interface](#)
[IPDMWProjects Members](#)
[IPDMWProjects::Count Property](#)

Availability

SOLIDWORKS Workgroup PDM 2003 FCS

IPDMWProperties (Type)

IPDMWProperties Interface

[See Also](#) [Members](#)



[PDMWorks.Interop.pdmworks Namespace](#) : IPDMWProperties Interface

Contains [IPDMWProperty](#) objects.

NOTE: Click the **Members** link, located near the top of the topic, to see this interface's methods and properties.

.NET Syntax

Visual Basic (Declaration)

Public Interface IPDMWProperties

Visual Basic (Usage)

Dim instance As [IPDMWProperties](#)

C#

public interface IPDMWProperties

C++/CLI

public interface class IPDMWProperties

Visual Basic for Applications (VBA) Syntax

See [PDMWProperties](#).

Remarks

You can get collections of configuration, document, and vault administrator-defined custom properties. You can [add](#) new properties to configurations and documents; however, you cannot add new vault administrator-defined custom properties.

Accessors

[IPDMWConfiguration::Properties](#)

[IPDMWConnection::AdminDefinedProperties](#)

[IPDMWDocument::Properties](#)

See Also

[IPDMWProperties Members](#)

[PDMWorks.Interop.pdmworks Namespace](#)

[IPDMWProperty Interface](#)

IPDMWProperties Interface Members

[See Also](#) [Properties](#) [Methods](#)



[PDMWorks.Interop.pdmworks Namespace](#) : IPDMWProperties Interface

The following tables list the members exposed by [IPDMWProperties](#).

Public Properties

Name	Description
Count	Gets the number of properties.
Item	Gets a property.

Public Methods

Name	Description
 Add	Adds a new property if the name of the property is not already in the collection.
 Update	Updates SOLIDWORKS Workgroup PDM vault.

[Top](#)

See Also

[IPDMWProperties Interface](#)
[PDMWorks.Interop.pdmworks Namespace](#)
[IPDMWProperty Interface](#)

SOLIDWORKS Workgroup PDM API Help

[Send comments on this topic.](#)

IPDMWProperties Interface Methods

[See Also](#)



[PDMWorks.Interop.pdmworks Namespace](#) : IPDMWProperties Interface

For a list of all members of this type, see [IPDMWProperties members](#).

Public Methods

Name	Description
 Add	Adds a new property if the name of the property is not already in the collection.
 Update	Updates SOLIDWORKS Workgroup PDM vault.

[Top](#)

See Also

[IPDMWProperties Interface](#)
[PDMWorks.Interop.pdmworks Namespace](#)
[IPDMWProperty Interface](#)

SOLIDWORKS Workgroup PDM API Help

[Send comments on this topic.](#)

IPDMWProperties Interface Properties

[See Also](#)



[PDMWorks.Interop.pdmworks Namespace](#) : IPDMWProperties Interface

For a list of all members of this type, see [IPDMWProperties members](#).

Public Properties

Name	Description
 Count	Gets the number of properties.
 Item	Gets a property.

[Top](#)

See Also

[IPDMWProperties Interface](#)
[PDMWorks.Interop.pdmworks Namespace](#)
[IPDMWProperty Interface](#)

SOLIDWORKS Workgroup PDM API Help

[Send comments on this topic.](#)

Add Method (IPDMWProperties)

[See Also](#)



[PDMWorks.Interop.pdmworks Namespace](#) > [IPDMWProperties Interface](#) : Add Method (IPDMWProperties)

Adds a new property if the name of the property is not already in the collection.

.NET Syntax

Visual Basic (Declaration)

```
Function Add( _  
    ByVal Name As System.String _  
) As PDMWProperty
```

Visual Basic (Usage)



```
Dim instance As IPDMWProperties  
Dim Name As System.String  
Dim value As PDMWProperty  
  
value = instance.Add(Name)
```

C#

```
PDMWProperty Add(  
    System.string Name  
)
```

C++/CLI

```
PDMWProperty^ Add(  
& System.String^ Name  
)
```

Parameters

Name

Name of the property

Return Value

[IPDMWProperty](#).

Visual Basic for Applications (VBA) Syntax

See [PDMWProperties::Add](#).

Remarks

If using this property to add a PDMWProperty to a [IPDMWProperties](#) collection, assign a value to the property using [IPDMWProperty::Value](#) and then use [IPDMWProperties::Update](#) to update the SOLIDWORKS Workgroup PDM vault. Otherwise, the property is not added.

Use this method before using IPDMWProperties::Update.

You cannot add new properties to collections of vault administrator-assigned custom properties.

See Also

[IPDMWProperties Interface](#)
[IPDMWProperties Members](#)

Availability

SOLIDWORKS Workgroup PDM 2003 FCS

SOLIDWORKS Workgroup PDM API Help

[Send comments on this topic.](#)

Count Property (IPDMWProperties)

[See Also](#)



[PDMWorks.Interop.pdmworks Namespace](#) > [IPDMWProperties Interface](#) : Count Property (IPDMWProperties)

Gets the number of properties.

.NET Syntax

Visual Basic (Declaration)

```
ReadOnly Property Count As System.Integer
```

```
Dim instance As IPDMWProperties
Dim value As System.Integer

value = instance.Count
```

C#

```
System.int Count {get;}
```

C++/CLI

```
property System.int Count {
    System.int get();
}
```

Property Value

Number of properties

Visual Basic for Applications (VBA) Syntax

See [PDMWProperties::Count](#).

See Also

[IPDMWProperties Interface](#)
[IPDMWProperties Members](#)
[IPDMWProperties::Item Property](#)

Availability

SOLIDWORKS Workgroup PDM 2003 FCS

SOLIDWORKS Workgroup PDM API Help

[Send comments on this topic.](#)

Item Property (IPDMWProperties)

[See Also](#)



[PDMWorks.Interop.pdmworks Namespace](#) > [IPDMWProperties Interface](#) : Item Property (IPDMWProperties)

Gets a property.

.NET Syntax

Visual Basic (Declaration)

```
ReadOnly Default Property Item( _
    ByVal Index As System.Object _
) As System.Object
```

Visual Basic (Usage)

 Copy Code

```
Dim instance As IPDMWProperties
Dim Index As System.Object
Dim value As System.Object

value = instance.Item(Index)
```

C#

```
System.object this[
    System.object Index
]; {get;}
```

C++/CLI

```
property System.Object^ default [System.Object^] {
    System.Object^ get(System.Object^ Index);
}
```

```
}
```

Parameters

Index

Number or name indicating the property to get

Property Value

[IPDMWProperty](#)

Visual Basic for Applications (VBA) Syntax

See [PDMWProperties::Item](#).

Remarks

Before calling this method, call [IPDMWProperties::Count](#) to get the number of properties in the collection.

See Also

[IPDMWProperties Interface](#)
[IPDMWProperties Members](#)

Availability

SOLIDWORKS Workgroup PDM 2003 FCS

SOLIDWORKS Workgroup PDM API Help

[Send comments on this topic.](#)

Update Method (IPDMWProperties)

[See Also](#)



[PDMWorks.Interop.pdmworks Namespace](#) > [IPDMWProperties Interface](#) : Update Method (IPDMWProperties)

Updates SOLIDWORKS Workgroup PDM vault.

.NET Syntax

Visual Basic (Declaration)

```
Function Update() As System.Integer
```

Visual Basic (Usage)



```
Dim instance As IPDMWProperties  
Dim value As System.Integer
```

```
value = instance.Update()
```

C#

```
System.int Update()
```

C++/CLI

```
System.int Update();
```

Return Value

0 if successful, non-0 if not

Visual Basic for Applications (VBA) Syntax

See [PDMWProperties::Update](#).

Remarks

To update the SOLIDWORKS Workgroup PDM vault, use this method after using:

- [IPDMWProperties::Add](#) to add a new property.

- [IPDMWProperty::Value](#) to change an existing property.

If the **Allow change document properties** check box was not selected on the **Vault Settings** tab on the **SOLIDWORKS Workgroup PDM VaultAdmin** dialog box in the SOLIDWORKS Workgroup PDM VaultAdmin, then this method fails.

SOLIDWORKS Workgroup PDM 2004 FCS and later support changing configuration-specific properties using the SOLIDWORKS Workgroup PDM API.

See Also

[IPDMWProperties Interface](#)
[IPDMWProperties Members](#)

Availability

SOLIDWORKS Workgroup PDM 2003 FCS

IPDMWProperty (Type)

IPDMWProperty Interface

[See Also](#) [Members](#)



[PDMWorks.Interop.pdmworks Namespace](#) : IPDMWProperty Interface

Provides access to a configuration, document, or vault administrator-assigned custom property.

NOTE: Click the **Members** link, located near the top of the topic, to see this interface's methods and properties.

.NET Syntax

Visual Basic (Declaration)

Public Interface IPDMWProperty

Visual Basic (Usage)

Dim instance As [IPDMWProperty](#)

C#

public interface IPDMWProperty

C++/CLI

public interface class IPDMWProperty

Visual Basic for Applications (VBA) Syntax

See [PDMWProperty](#).

Accessors

[IPDMWProperties::Add](#)
[IPDMWProperties::Item](#)

See Also

[IPDMWProperty Members](#)
[PDMWorks.Interop.pdmworks Namespace](#)
[IPDMWProperties Interface](#)

IPDMWProperty Interface Members

[See Also](#) [Properties](#)



[PDMWorks.Interop.pdmworks Namespace](#) : IPDMWProperty Interface

The following tables list the members exposed by [IPDMWProperty](#).

Public Properties

Name	Description
Name	Gets the name of this property.
Value	Gets or sets the value of the property.

[Top](#)

See Also

[IPDMWProperty Interface](#)
[PDMWorks.Interop.pdmworks Namespace](#)
[IPDMWProperties Interface](#)

IPDMWProperty Interface Properties

[See Also](#)

[PDMWorks.Interop.pdmworks Namespace](#) : IPDMWProperty Interface

For a list of all members of this type, see [IPDMWProperty members](#).

Public Properties

Name	Description
 Name	Gets the name of this property.
 Value	Gets or sets the value of the property.

[Top](#)

See Also

[IPDMWProperty Interface](#)
[PDMWorks.Interop.pdmworks Namespace](#)
[IPDMWProperties Interface](#)

Name Property (IPDMWProperty)

[See Also](#)



[PDMWorks.Interop.pdmworks Namespace](#) > [IPDMWProperty Interface](#) : Name Property (IPDMWProperty)

Gets the name of this property.

.NET Syntax

Visual Basic (Declaration)

Property Name As System.String

Visual Basic (Usage)



```
Dim instance As IPDMWProperty  
Dim value As System.String
```

```
instance.Name = value
```

```
value = instance.Name
```

C#

```
System.string Name {get; set;}
```

C++/CLI

```
property System.String^ Name {  
    System.String^ get();  
    void set ( & System.String^ value);  
}
```

Property Value

Name of this property

Visual Basic for Applications (VBA) Syntax

See [PDMWProperty::Name](#).

See Also

[IPDMWProperty Interface](#)
[IPDMWProperty Members](#)

Availability

SOLIDWORKS Workgroup PDM 2003 FCS

SOLIDWORKS Workgroup PDM API Help

[Send comments on this topic.](#)

Value Property (IPDMWProperty)

[See Also](#)



[PDMWorks.Interop.pdmworks Namespace](#) > [IPDMWProperty Interface](#) : Value Property (IPDMWProperty)

Gets or sets the value of the property.

.NET Syntax

Visual Basic (Declaration)

Default Property Value As System.String

Visual Basic (Usage)



```
Dim instance As IPDMWProperty.  
Dim value As System.String
```

```
instance.Value = value
```

```
value = instance.Value
```

C#

```
System.string this {get; set;}
```

C++/CLI

```
property System.String^ default [] {  
    System.String^ get();  
    void set ( & System.String^ value);  
}
```

Property Value

Value of this property

Visual Basic for Applications (VBA) Syntax

See [PDMWProperty::Value](#).

Remarks

Use [IPDMWProperties::Update](#) to update the SOLIDWORKS Workgroup PDM vault after using this property to change the value of a property.

See Also

[IPDMWProperty Interface](#)
[IPDMWProperty Members](#)

Availability

SOLIDWORKS Workgroup PDM 2003 FCS