

SOLIDWORKS API (.NET VBA C#) — Reference

(36/337): ICalloutVariable

SOLIDWORKS API Documentation (converted from CHM)

ICalloutVariable (Type)

ICalloutVariable Interface

[See Also](#) [Members](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) : ICalloutVariable Interface

Allows access to a hole callout.

NOTE: Click the **Members** link, located near the top of the topic, to see this interface's methods and properties.

.NET Syntax

Visual Basic (Declaration)

```
Public Interface ICalloutVariable
```

Visual Basic (Usage)



```
Dim instance As ICalloutVariable
```

C#

```
public interface ICalloutVariable
```

C++/CLI

```
public interface class ICalloutVariable
```

Visual Basic for Applications (VBA) Syntax

See [CalloutVariable](#).

Example

[Get and Set Hole Callout Variables \(C#\)](#)
[Get and Set Hole Callout Variables \(VB.NET\)](#)
[Get and Set Hole Callout Variables \(VBA\)](#)

Remarks

These interfaces inherit from the ICalloutVariable interface:

- [ICalloutAngleVariable](#)
- [ICalloutLengthVariable](#)
- [ICalloutStringVariable](#)

Accessors

[IDisplayDimension::GetHoleCalloutVariables](#)

Access Diagram

[CalloutVariable](#)

See Also

[ICalloutVariable Members](#)
[SolidWorks.Interop.sldworks Namespace](#)
[IDisplayDimension::IsHoleCallout Method \(\)](#)
[IDrawingDoc::AddHoleCallout2 Method \(\)](#)
[IDrawingDoc::AddHoleCallout2 Method \(\)](#)

ICalloutVariable Interface Members

[See Also](#) [Properties](#)



[SolidWorks.Interop.sldworks Namespace](#) : ICalloutVariable Interface

The following tables list the members exposed by [ICalloutVariable](#).

Public Properties

Name	Description
 FitDisplayStyle	Gets or sets how fit tolerance is displayed in a hole callout.
 FitTextHeight	Gets or sets the height of the fit tolerance font in a hole callout.
 FitTextScale	Gets or sets the value with which to scale the fit tolerance font in a hole callout.
 FitType	Gets or sets the fit type for this hole callout.
 FitUseTextScale	Gets or sets whether to use the fit tolerance font scale value in a hole callout.
 HoleFit	Gets or sets the fit tolerance in a hole callout.
 ShaftFit	Gets or sets the shaft fit tolerance in a hole callout.
 ShowParenthesis	Gets or sets whether to show parentheses around linear tolerance dimensions in a hole callout.
 TextHeight	Gets or sets the height of the tolerance text in a hole callout.
 TextScale	Gets or sets the value with which to scale the tolerance font for a hole callout.
 ToleranceMax	Gets or sets the maximum tolerance for a hole callout.
 ToleranceMin	Gets or sets the minimum tolerance for a hole callout.
 ToleranceType	Gets or sets the type of tolerance for a hole callout.
 Type	Gets the type of general hole callout variable.
 UserReadableVariableName	Gets the name of the hole callout variable as it appears in the Dimension PropertyManager page in the Callout value drop-down list box.
 UseTextScale	Gets or sets whether to use the value with which to scale the tolerance text for a hole callout.
 VariableName	Gets the name of the hole callout variable as it appears in the Dimension PropertyManager page in the Dimension Text box.
 VariableType	Gets the type of specific hole callout variable.

[Top](#)

See Also

[ICalloutVariable Interface](#)
[SolidWorks.Interop.sldworks Namespace](#)
[IDisplayDimension::IsHoleCallout Method \(\)](#)
[IDrawingDoc::AddHoleCallout2 Method \(\)](#)
[IDrawingDoc::IAddHoleCallout2 Method \(\)](#)

ICalloutVariable Interface Properties

[See Also](#)

 [SolidWorks.Interop.sldworks Namespace](#) : ICalloutVariable Interface

For a list of all members of this type, see [ICalloutVariable members](#).

Public Properties		
Name	Description	
 FitDisplayStyle	Gets or sets how fit tolerance is displayed in a hole callout.	
 FitTextHeight	Gets or sets the height of the fit tolerance font in a hole callout.	
 FitTextScale	Gets or sets the value with which to scale the fit tolerance font in a hole callout.	
 FitType	Gets or sets the fit type for this hole callout.	
 FitUseTextScale	Gets or sets whether to use the fit tolerance font scale value in a hole callout.	
 HoleFit	Gets or sets the fit tolerance in a hole callout.	
 ShaftFit	Gets or sets the shaft fit tolerance in a hole callout.	
 ShowParenthesis	Gets or sets whether to show parentheses around linear tolerance dimensions in a hole callout.	
 TextHeight	Gets or sets the height of the tolerance text in a hole callout.	

 TextScale	Gets or sets the value with which to scale the tolerance font for a hole callout.
 ToleranceMax	Gets or sets the maximum tolerance for a hole callout.
 ToleranceMin	Gets or sets the minimum tolerance for a hole callout.
 ToleranceType	Gets or sets the type of tolerance for a hole callout.
 Type	Gets the type of general hole callout variable.
 UserReadableVariableName	Gets the name of the hole callout variable as it appears in the Dimension PropertyManager page in the Callout value drop-down list box.
 UseTextScale	Gets or sets whether to use the value with which to scale the tolerance text for a hole callout.
 VariableName	Gets the name of the hole callout variable as it appears in the Dimension PropertyManager page in the Dimension Text box.
 VariableType	Gets the type of specific hole callout variable.

[Top](#)

See Also

[ICalloutVariable Interface](#)
[SolidWorks.Interop.sldworks Namespace](#)
[IDisplayDimension::IsHoleCallout Method \(\)](#)
[IDrawingDoc::AddHoleCallout2 Method \(\)](#)
[IDrawingDoc::IAddHoleCallout2 Method \(\)](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

FitDisplayStyle Property (ICalloutVariable)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ICalloutVariable Interface](#) : FitDisplayStyle Property (ICalloutVariable)

Gets or sets how fit tolerance is displayed in a hole callout.

.NET Syntax

Visual Basic (Declaration)

```
Property FitDisplayStyle As System.Integer
```

Visual Basic (Usage)



```
Dim instance As ICalloutVariable  
Dim value As System.Integer
```

```
instance.FitDisplayStyle = value
```

```
value = instance.FitDisplayStyle
```

C#

```
System.int FitDisplayStyle {get; set;}
```

C++/CLI

```
property System.int FitDisplayStyle {  
    System.int get();  
    void set ( & System.int value);  
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

Fit tolerance display style as defined in [swFitToDisplay_e](#)

Visual Basic for Applications (VBA) Syntax

See [CalloutVariable::FitDisplayStyle](#).

Remarks

To see the effects of changing the fit tolerance display style, use [IModelView::GraphicsRedraw](#).

See Also

[ICalloutVariable Interface](#)
[ICalloutVariable Members](#)
[IDimensionTolerance::FitDisplayTolerance](#)
[ICalloutVariable::HoleFit Property \(\)](#)
[ICalloutVariable::ShaftFit Property \(\)](#)
[ICalloutVariable::FitTextHeight Property \(\)](#)

Availability

SOLIDWORKS 2016 FCS, Revision Number 24.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

FitTextHeight Property (ICalloutVariable)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ICalloutVariable Interface](#) : FitTextHeight Property (ICalloutVariable)

Gets or sets the height of the fit tolerance font in a hole callout.

.NET Syntax

Visual Basic (Declaration)

Property FitTextHeight As System.Double

Visual Basic (Usage)



```
Dim instance As ICalloutVariable  
Dim value As System.Double
```

```
instance.FitTextHeight = value
```

```
value = instance.FitTextHeight
```

C#

```
System.double FitTextHeight {get; set;}
```

C++/CLI

```
property System.double FitTextHeight {  
    System.double get();  
    void set ( & System.double value);  
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

Height of the fit tolerance font

Visual Basic for Applications (VBA) Syntax

See [CalloutVariable::FitTextHeight](#).

Remarks

This property supports fit and fit-with-tolerance types only.

See Also

[ICalloutVariable Interface](#)
[ICalloutVariable Members](#)
[ICalloutVariable::TextHeight Property \(\)](#)
[ICalloutVariable::HoleFit Property \(\)](#)
[ICalloutVariable::ShaftFit Property \(\)](#)

Availability

SOLIDWORKS 2016 FCS, Revision Number 24.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

FitTextScale Property (ICalloutVariable)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ICalloutVariable Interface](#) : FitTextScale Property (ICalloutVariable)

Gets or sets the value with which to scale the fit tolerance font in a hole callout.

.NET Syntax

Visual Basic (Declaration)

Property FitTextScale As System.Double

Visual Basic (Usage)



```
Dim instance As ICalloutVariable
Dim value As System.Double
```

```
instance.FitTextScale = value
```

```
value = instance.FitTextScale
```

C#

```
System.double FitTextScale {get; set;}
```

C++/CLI

```
property System.double FitTextScale {
    System.double get();
    void set ( & System.double value);
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

0.0 <= value with which to scale the fit tolerance font <= 10.0

Visual Basic for Applications (VBA) Syntax

See [CalloutVariable::FitTextScale](#).

Remarks

This property supports fit and fit-with-tolerance types only.

Set [ICalloutVariable::FitUseTextScale](#) to true to enable setting this property.

See Also

[ICalloutVariable Interface](#)
[ICalloutVariable Members](#)
[ICalloutVariable::TextScale Property \(\)](#)
[ICalloutVariable::UseTextScale Property \(\)](#)
[ICalloutVariable::HoleFit Property \(\)](#)
[ICalloutVariable::ShaftFit Property \(\)](#)

Availability

SOLIDWORKS 2016 FCS, Revision Number 24.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

FitType Property (ICalloutVariable)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ICalloutVariable Interface](#) : FitType Property (ICalloutVariable)

Gets or sets the fit type for this hole callout.

.NET Syntax

Visual Basic (Declaration)

```
Property FitType As System.Integer
```

Visual Basic (Usage)



```
Dim instance As ICalloutVariable  
Dim value As System.Integer
```

```
instance.FitType = value
```

```
value = instance.FitType
```

C#

```
System.int FitType {get; set;}
```

C++/CLI

```
property System.int FitType {  
    System.int get();  
    void set ( & System.int value);  
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

Fit type as defined in [swFitType_e](#)

Visual Basic for Applications (VBA) Syntax

See [CalloutVariable::FitType](#).

Remarks

This property is only available when the [type of tolerance](#) is [swTolType_e](#):

- swTolFIT,
- swTolFITTOLONLY, or
- swTolFITWITHTOL.

See Also

[ICalloutVariable Interface](#)
[ICalloutVariable Members](#)
[ICalloutVariable::HoleFit Property \(\)](#)
[ICalloutVariable::ShaftFit Property \(\)](#)

Availability

SOLIDWORKS 2016 FCS, Revision Number 24.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

FitUseTextScale Property (ICalloutVariable)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ICalloutVariable Interface](#) : FitUseTextScale Property (ICalloutVariable)

Gets or sets whether to use the fit tolerance font scale value in a hole callout.

.NET Syntax

Visual Basic (Declaration)

Property FitUseTextScale As System.Boolean

Visual Basic (Usage)



```
Dim instance As ICalloutVariable  
Dim value As System.Boolean  
  
instance.FitUseTextScale = value  
  
value = instance.FitUseTextScale
```

C#

```
System.bool FitUseTextScale {get; set;}
```

C++/CLI

```
property System.bool FitUseTextScale {  
    System.bool get();  
    void set ( & System.bool value);  
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

True to use the fit tolerance font scale value, false to not

Visual Basic for Applications (VBA) Syntax

See [CalloutVariable::FitUseTextScale](#).

Remarks

Use [ICalloutVariable::FitTextScale](#) to get or set the fit tolerance font scale value in a hole callout.

See Also

[ICalloutVariable Interface](#)
[ICalloutVariable Members](#)
[ICalloutVariable::TextScale Property \(\)](#)
[ICalloutVariable::UseTextScale Property \(\)](#)
[ICalloutVariable::HoleFit Property \(\)](#)
[ICalloutVariable::ShaftFit Property \(\)](#)

Availability

SOLIDWORKS 2016 FCS, Revision Number 24.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

HoleFit Property (ICalloutVariable)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ICalloutVariable Interface](#) : HoleFit Property (ICalloutVariable)

Gets or sets the fit tolerance in a hole callout.

.NET Syntax

Visual Basic (Declaration)

Property HoleFit As System.String

Visual Basic (Usage)



```
Dim instance As ICalloutVariable  
Dim value As System.String  
  
instance.HoleFit = value
```

```
value = instance.HoleFit
```

C#

```
System.string HoleFit {get; set;}
```

C++/CLI

```
property System.String^ HoleFit {  
    System.String^ get();  
    void set ( & System.String^ value);  
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

Fit tolerance

Visual Basic for Applications (VBA) Syntax

See [CalloutVariable::HoleFit](#).

Remarks

Depending on the [tolerance type](#), tolerance fit might not be visible. You cannot set tolerance fit if the tolerance type is [swTolType_e.swTolNONE](#).

To see the effects of setting tolerance fit, use [IModelView::GraphicsRedraw](#).

See Also

[ICalloutVariable Interface](#)
[ICalloutVariable Members](#)
[ICalloutVariable::FitDisplayStyle Property \(\)](#)
[ICalloutVariable::FitTextHeight Property \(\)](#)
[ICalloutVariable::FitTextScale Property \(\)](#)
[ICalloutVariable::FitType Property \(\)](#)
[ICalloutVariable::FitUseTextScale Property \(\)](#)
[ICalloutVariable::ShaftFit Property \(\)](#)
[IDimensionTolerance::GetHoleFitValue Method \(\)](#)
[IDimensionTolerance::SetFitValues Method \(\)](#)

Availability

SOLIDWORKS 2016 FCS, Revision Number 24.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

ShaftFit Property (ICalloutVariable)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ICalloutVariable Interface](#) : ShaftFit Property (ICalloutVariable)

Gets or sets the shaft fit tolerance in a hole callout.

.NET Syntax

Visual Basic (Declaration)

```
Property ShaftFit As System.String
```

Visual Basic (Usage)



```
Dim instance As ICalloutVariable  
Dim value As System.String
```

```
instance.ShaftFit = value
```

```
value = instance.ShaftFit
```

C#

```
System.string ShaftFit {get; set;}
```

C++/CLI

```
property System.String^ ShaftFit {  
    System.String^ get();  
    void set ( & System.String^ value);  
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

Shaft fit tolerance

Visual Basic for Applications (VBA) Syntax

See [CalloutVariable::ShaftFit](#).

Remarks

Depending on the [tolerance type](#), tolerance shaft fit might not be visible. You cannot set tolerance shaft fit if the tolerance type is [swTolType_e.swToINONE](#).

To see the effects of setting the tolerance shaft fit, use [IModelView::GraphicsRedraw](#).

See Also

[ICalloutVariable Interface](#)
[ICalloutVariable Members](#)
[ICalloutVariable::FitDisplayStyle Property \(\)](#)
[ICalloutVariable::FitTextHeight Property \(\)](#)
[ICalloutVariable::FitTextScale Property \(\)](#)
[ICalloutVariable::FitType Property \(\)](#)
[ICalloutVariable::FitUseTextScale Property \(\)](#)
[ICalloutVariable::HoleFit Property \(\)](#)
[IDimensionTolerance::GetShaftFitValue Method \(\)](#)
[IDimensionTolerance::SetFitValues Method \(\)](#)

Availability

SOLIDWORKS 2016 FCS, Revision Number 24.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

ShowParenthesis Property (ICalloutVariable)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ICalloutVariable Interface](#) : ShowParenthesis Property (ICalloutVariable)

Gets or sets whether to show parentheses around linear tolerance dimensions in a hole callout.

.NET Syntax

Visual Basic (Declaration)

```
Property ShowParenthesis As System.Boolean
```

Visual Basic (Usage)



```
Dim instance As ICalloutVariable  
Dim value As System.Boolean
```

```
instance.ShowParenthesis = value
```

```
value = instance.ShowParenthesis
```

C#

```
System.bool ShowParenthesis {get; set;}
```

C++/CLI

```
property System.bool ShowParenthesis {
    System.bool get();
    void set ( & System.bool value);
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

True to show parentheses around linear tolerance dimensions, false to not

Visual Basic for Applications (VBA) Syntax

See [CalloutVariable::ShowParenthesis](#).

Remarks

This property supports bilateral, symmetric, or fit-with-tolerance types only.

In SOLIDWORKS 2016 and later, use this property to set whether to show parentheses around linear tolerance dimensions in a hole callout. Calling [IDimensionTolerance::ShowParenthesis](#) to set whether to show parentheses around linear tolerance dimensions in a hole callout does not override this property's setting.

See Also

[ICalloutVariable Interface](#)
[ICalloutVariable Members](#)

Availability

SOLIDWORKS 2016 FCS, Revision Number 24.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

TextHeight Property (ICalloutVariable)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ICalloutVariable Interface](#) : TextHeight Property (ICalloutVariable)

Gets or sets the height of the tolerance text in a hole callout.

.NET Syntax

Visual Basic (Declaration)

```
Property TextHeight As System.Double
```

Visual Basic (Usage)



```
Dim instance As ICalloutVariable
Dim value As System.Double
```

```
instance.TextHeight = value
```

```
value = instance.TextHeight
```

C#

```
System.double TextHeight {get; set;}
```

C++/CLI

```
property System.double TextHeight {
    System.double get();
    void set ( & System.double value);
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

Height of the tolerance text

Visual Basic for Applications (VBA) Syntax

See [ICalloutVariable::TextHeight](#).

See Also

[ICalloutVariable Interface](#)
[ICalloutVariable Members](#)
[ICalloutVariable::FitTextHeight Property \(\)](#)

Availability

SOLIDWORKS 2016 FCS, Revision Number 24.0

SOLIDWORKS API Help

[Send comments](#) on this topic.

TextScale Property (ICalloutVariable)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ICalloutVariable Interface](#) : TextScale Property (ICalloutVariable)

Gets or sets the value with which to scale the tolerance font for a hole callout.

.NET Syntax

Visual Basic (Declaration)

```
Property TextScale As System.Double
```

Visual Basic (Usage)



```
Dim instance As ICalloutVariable  
Dim value As System.Double
```

```
instance.TextScale = value
```

```
value = instance.TextScale
```

C#

```
System.double TextScale {get; set;}
```

C++/CLI

```
property System.double TextScale {  
    System.double get();  
    void set ( & System.double value);  
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

0.0 <= value with which to scale the tolerance font <= 10.0

Visual Basic for Applications (VBA) Syntax

See [CalloutVariable::TextScale](#).

Remarks

Set [ICalloutVariable::UseTextScale](#) to true to enable setting this property.

See Also

[ICalloutVariable Interface](#)
[ICalloutVariable Members](#)
[ICalloutVariable::FitTextScale Property \(\)](#)
[ICalloutVariable::FitUseTextScale Property \(\)](#)

Availability

SOLIDWORKS 2016 FCS, Revision Number 24.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

ToleranceMax Property (ICalloutVariable)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ICalloutVariable Interface](#) : ToleranceMax Property (ICalloutVariable)

Gets or sets the maximum tolerance for a hole callout.

.NET Syntax

Visual Basic (Declaration)

Property ToleranceMax As System.Double

Visual Basic (Usage)



```
Dim instance As ICalloutVariable
Dim value As System.Double
```

```
instance.ToleranceMax = value
```

```
value = instance.ToleranceMax
```

C#

```
System.double ToleranceMax {get; set;}
```

C++/CLI

```
property System.double ToleranceMax {
    System.double get();
    void set ( & System.double value);
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

Maximum tolerance

Visual Basic for Applications (VBA) Syntax

See [CalloutVariable::ToleranceMax](#).

See Also

[ICalloutVariable Interface](#)
[ICalloutVariable Members](#)
[ICalloutVariable::ToleranceMin Property \(\)](#)

Availability

SOLIDWORKS 2016 FCS, Revision Number 24.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

ToleranceMin Property (ICalloutVariable)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ICalloutVariable Interface](#) : ToleranceMin Property (ICalloutVariable)

Gets or sets the minimum tolerance for a hole callout.

.NET Syntax

Visual Basic (Declaration)

Property ToleranceMin As System.Double

Visual Basic (Usage)



```
Dim instance As ICalloutVariable
Dim value As System.Double

instance.ToleranceMin = value

value = instance.ToleranceMin
```

C#

```
System.double ToleranceMin {get; set;}
```

C++/CLI

```
property System.double ToleranceMin {
    System.double get();
    void set ( & System.double value);
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

Minimum tolerance

Visual Basic for Applications (VBA) Syntax

See [CalloutVariable::ToleranceMin](#).

See Also

[ICalloutVariable Interface](#)
[ICalloutVariable Members](#)
[ICalloutVariable::ToleranceMax Property\(\)](#)

Availability

SOLIDWORKS 2016 FCS, Revision Number 24.0

SOLIDWORKS API Help

[Send comments](#) on this topic.

ToleranceType Property (ICalloutVariable)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ICalloutVariable Interface](#) : ToleranceType Property (ICalloutVariable)

Gets or sets the type of tolerance for a hole callout.

.NET Syntax

Visual Basic (Declaration)

```
Property ToleranceType As System.Integer
```

Visual Basic (Usage)



```
Dim instance As ICalloutVariable
Dim value As System.Integer

instance.ToleranceType = value

value = instance.ToleranceType
```

C#

```
System.int ToleranceType {get; set;}
```

C++/CLI

```
property System.int ToleranceType {
    System.int get();
    void set ( & System.int value);
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

Type of tolerance as defined in [swTolType_e](#) (see **Remarks**)

Visual Basic for Applications (VBA) Syntax

See [CalloutVariable::ToleranceType](#).

Example

[Get and Set Hole Callout Variables \(C#\)](#)
[Get and Set Hole Callout Variables \(VB.NET\)](#)
[Get and Set Hole Callout Variables \(VBA\)](#)

Remarks

In SOLIDWORKS 2016 and later, use this property to set the type of tolerance for a hole callout. Calling [IDimensionTolerance::Type](#) to set the type of tolerance for a hole callout does not override this property's setting.

To see the effects of changing the tolerance type, use [IModelView::GraphicsRedraw](#).

See Also

[ICalloutVariable Interface](#)
[ICalloutVariable Members](#)

Availability

SOLIDWORKS 2016 FCS, Revision Number 24.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

Type Property (ICalloutVariable)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ICalloutVariable Interface](#) : Type Property (ICalloutVariable)

Gets the type of general hole callout variable.

.NET Syntax

Visual Basic (Declaration)

```
ReadOnly Property Type As System.Integer
```

Visual Basic (Usage)



```
Dim instance As ICalloutVariable
Dim value As System.Integer

value = instance.Type
```

C#

```
System.int Type {get;}
```

C++/CLI

```
property System.int Type {
    System.int get();
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

Type of general hole callout variable as defined in [swCalloutVariableType_e](#)

Visual Basic for Applications (VBA) Syntax

See [CalloutVariable::Type](#).

Example

[Get and Set Hole Callout Variables \(C#\)](#)
[Get and Set Hole Callout Variables \(VB.NET\)](#)
[Get and Set Hole Callout Variables \(VBA\)](#)

Remarks

Use [ICalloutVariable::VariableType](#) to get the type of specific callout variable.

See Also

[ICalloutVariable Interface](#)
[ICalloutVariable Members](#)
[ICalloutAngleVariable Interface](#)
[ICalloutLengthVariable Interface](#)
[ICalloutStringVariable Interface](#)

Availability

SOLIDWORKS 2016 FCS, Revision Number 24.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

UserReadableVariableName Property (ICalloutVariable)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ICalloutVariable Interface](#) : UserReadableVariableName Property (ICalloutVariable)

Gets the name of the hole callout variable as it appears in the Dimension PropertyManager page in the **Callout value** drop-down list box.

.NET Syntax

Visual Basic (Declaration)

```
ReadOnly Property UserReadableVariableName As System.String
```

Visual Basic (Usage)



```
Dim instance As ICalloutVariable  
Dim value As System.String  
  
value = instance.UserReadableVariableName
```

C#

```
System.string UserReadableVariableName {get;}
```

C++/CLI

```
property System.String^ UserReadableVariableName {  
    System.String^ get();  
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

Name of the hole callout variable as it appears in the Dimension PropertyManager page in **Callout value** drop-down list box

Visual Basic for Applications (VBA) Syntax

See [CalloutVariable::UserReadableVariableName](#).

Example

[Get and Set Hole Callout Variables \(C#\)](#)
[Get and Set Hole Callout Variables \(VB.NET\)](#)
[Get and Set Hole Callout Variables \(VBA\)](#)

Remarks

Call [ICalloutVariable::VariableName](#) to get the name of the hole callout variable as it appears in the Dimension PropertyManager page in the **Dimension Text** box.

See Also

[ICalloutVariable Interface](#)
[ICalloutVariable Members](#)

Availability

SOLIDWORKS 2016 FCS, Revision Number 24.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

UseTextScale Property (ICalloutVariable)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ICalloutVariable Interface](#) : UseTextScale Property (ICalloutVariable)

Gets or sets whether to use the value with which to scale the tolerance text for a hole callout.

.NET Syntax

Visual Basic (Declaration)

Property UseTextScale As System.Boolean

Visual Basic (Usage)



```
Dim instance As ICalloutVariable
Dim value As System.Boolean
```

```
instance.UseTextScale = value
```

```
value = instance.UseTextScale
```

C#

```
System.bool UseTextScale {get; set;}
```

C++/CLI

```
property System.bool UseTextScale {
    System.bool get();
    void set ( & System.bool value);
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

True to use the value with which to scale the tolerance text, false to not

Visual Basic for Applications (VBA) Syntax

See [CalloutVariable::UseTextScale](#).

Remarks

Call [ICalloutVariable::TextScale](#) to get or set the value with which to scale the tolerance text.

See Also

Availability

SOLIDWORKS 2016 FCS, Revision Number 24.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

VariableName Property (ICalloutVariable)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ICalloutVariable Interface](#) : VariableName Property (ICalloutVariable)

Gets the name of the hole callout variable as it appears in the Dimension PropertyManager page in the **Dimension Text** box.

.NET Syntax

Visual Basic (Declaration)

```
ReadOnly Property VariableName As System.String
```

Visual Basic (Usage)



```
Dim instance As ICalloutVariable  
Dim value As System.String
```

```
value = instance.VariableName
```

C#

```
System.string VariableName {get;}
```

C++/CLI

```
property System.String^ VariableName {  
    System.String^ get();  
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

Name of the hole callout variable as it appears in the Dimension PropertyManager page in the **Dimension Text** box

Visual Basic for Applications (VBA) Syntax

See [CalloutVariable::VariableName](#).

Example

[Get and Set Hole Callout Variables \(C#\)](#)
[Get and Set Hole Callout Variables \(VB.NET\)](#)
[Get and Set Hole Callout Variables \(VBA\)](#)

Remarks

Call [ICalloutVariable::UserReadableVariableName](#) to get the name of the hole callout variable as it appears in the Dimension PropertyManager page in the **Callout value** drop-down list box.

See Also

[ICalloutVariable Interface](#)
[ICalloutVariable Members](#)

Availability

SOLIDWORKS 2016 FCS, Revision Number 24.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

VariableType Property (ICalloutVariable)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ICalloutVariable Interface](#) : VariableType Property (ICalloutVariable)

Gets the type of specific hole callout variable.

.NET Syntax

Visual Basic (Declaration)

```
ReadOnly Property VariableType As System.Integer
```

Visual Basic (Usage)



```
Dim instance As ICalloutVariable  
Dim value As System.Integer
```

```
value = instance.VariableType
```

C#

```
System.int VariableType {get;}
```

C++/CLI

```
property System.int VariableType {  
    System.int get();  
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

Type of specific hole callout variable as defined in [swCalloutVariable_e](#)

Visual Basic for Applications (VBA) Syntax

See [CalloutVariable::VariableType](#).

Remarks

Call [ICalloutVariable::Type](#) to get the type of general hole callout variable.

See Also

[ICalloutVariable Interface](#)
[ICalloutVariable Members](#)

Availability

SOLIDWORKS 2016 FCS, Revision Number 24.0