

SOLIDWORKS API (.NET VBA C#) — Reference

(52/337): ICompositeCurveFeatureData- IConcentricMateFeatureData

SOLIDWORKS API Documentation (converted from CHM)

ICompositeCurveFeatureData (Type)

ICompositeCurveFeatureData Interface

[See Also](#) [Members](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) : ICompositeCurveFeatureData Interface

Allows access to a composite curve feature.
NOTE: Click the **Members** link, located near the top of the topic, to see this interface's methods and properties.

.NET Syntax

Visual Basic (Declaration)

```
Public Interface ICompositeCurveFeatureData
```

Visual Basic (Usage)



```
Dim instance As ICompositeCurveFeatureData
```

C#

```
public interface ICompositeCurveFeatureData
```

C++/CLI

```
public interface class ICompositeCurveFeatureData
```

Visual Basic for Applications (VBA) Syntax

See [CompositeCurveFeatureData](#).

Example

[Insert a Composite Curve \(C#\)](#)
[Insert a Composite Curve \(VB.NET\)](#)
[Insert a Composite Curve \(VBA\)](#)

Accessors

[IFeature::GetDefinition](#) and [IFeature::IGetDefinition](#)

Access Diagram

[CompositeCurveFeatureData](#)

See Also

[ICompositeCurveFeatureData Members](#)
[SolidWorks.Interop.sldworks Namespace](#)
[IModelDoc2::InsertCompositeCurve Method](#)

ICompositeCurveFeatureData Interface Methods

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) : ICompositeCurveFeatureData Interface

For a list of all members of this type, see [ICompositeCurveFeatureData members](#).

Public Methods

Name	Description
 AccessSelections	Gains access to the selections that define this composite curve.
 GetEntitiesToJoin	Gets the entities to join to create this composite curve feature.

 GetEntitiesToJoinCount	Gets the number of entities that are joined to create a composite curve.
 IGetEntitiesToJoin	Gets the entities to join to create this composite curve.
 ISetEntitiesToJoin	Sets the entities to join to create this composite curve.
 ReleaseSelectionAccess	Releases access to the selections that define this composite curve.
 SetEntitiesToJoin	Sets the entities to join to create this composite curve.

[Top](#)

 See Also

[ICompositeCurveFeatureData Interface](#)
[SolidWorks.Interop.sldworks Namespace](#)
[IModelDoc2::InsertCompositeCurve Method](#)

SOLIDWORKS API Help [Send comments on this topic.](#)

ICompositeCurveFeatureData Interface Members

[See Also](#) [Methods](#)

 [SolidWorks.Interop.sldworks Namespace](#) : ICompositeCurveFeatureData Interface

The following tables list the members exposed by [ICompositeCurveFeatureData](#).

 Public Methods

Name	Description
 AccessSelections	Gains access to the selections that define this composite curve.
 GetEntitiesToJoin	Gets the entities to join to create this composite curve feature.
 GetEntitiesToJoinCount	Gets the number of entities that are joined to create a composite curve.
 IGetEntitiesToJoin	Gets the entities to join to create this composite curve.
 ISetEntitiesToJoin	Sets the entities to join to create this composite curve.
 ReleaseSelectionAccess	Releases access to the selections that define this composite curve.
 SetEntitiesToJoin	Sets the entities to join to create this composite curve.

[Top](#)

 See Also

[ICompositeCurveFeatureData Interface](#)
[SolidWorks.Interop.sldworks Namespace](#)
[IModelDoc2::InsertCompositeCurve Method](#)

SOLIDWORKS API Help [Send comments on this topic.](#)

AccessSelections Method (ICompossiteCurveFeatureData)

[See Also](#)

  [SolidWorks.Interop.sldworks Namespace](#) > [ICompositeCurveFeatureData Interface](#) : AccessSelections Method (ICompositeCurveFeatureData)
Gains access to the selections that define this composite curve.

 .NET Syntax

Visual Basic (Declaration)

```
Function AccessSelections(  
    ByVal TopDoc As ModelDoc2, _  
    ByVal Component As Component2 _  
) As System.Boolean
```

Visual Basic (Usage)

```
Dim instance As ICompositeCurveFeatureData  
Dim TopDoc As ModelDoc2  
Dim Component As Component2  
Dim value As System.Boolean
```



```
value = instance.AccessSelections(TopDoc, Component)
```

C#

```
System.bool AccessSelections(  
    ModelDoc2 TopDoc,  
    Component2 Component  
)
```

C++/CLI

```
System.bool AccessSelections(  
& ModelDoc2^ TopDoc,  
& Component2^ Component  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

TopDoc

Top-level document

Component

Component in which the feature is to be modified

Return Value

True if the selections are successfully accessed, false if not

Visual Basic for Applications (VBA) Syntax

See [CompositeCurveFeatureData::AccessSelections](#).

Remarks

To modify a feature in a...	Then...
Part	- TopDoc argument is the IModelDoc2 for the part - Component argument is NULL
Assembly	- TopDoc is the IModelDoc2 object for the assembly - Component argument is the IComponent2 object in which the feature is to be modified

This method puts the model into a rollback state to allow access to the selections that define this feature. You must use either of the following methods to restore the rollback state:

- [IFeature::ModifyDefinition](#) and [IFeature::IModifyDefinition2](#) if you modified the feature
- [ICompositeCurveFeatureData::ReleaseSelectionAccess](#) if you did not

See Also

[ICompositeCurveFeatureData Interface](#)
[ICompositeCurveFeatureData Members](#)

Availability

SOLIDWORKS 2003 FCS, Revision Number 11.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

GetEntitiesToJoin Method (ICompositeCurveFeatureData)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ICompositeCurveFeatureData Interface](#) : GetEntitiesToJoin Method (ICompositeCurveFeatureData)

Gets the entities to join to create this composite curve feature.

.NET Syntax

Visual Basic (Declaration)

```
Function GetEntitiesToJoin( _  
    ByRef Type As System.Object _  
) As System.Object
```

Visual Basic (Usage)

```
Dim instance As ICompositeCurveFeatureData  
Dim Type As System.Object  
Dim value As System.Object  
  
value = instance.GetEntitiesToJoin(Type)
```

C#

```
System.object GetEntitiesToJoin(  
    out System.object Type  
)
```

C++/CLI

```
System.Object^ GetEntitiesToJoin(  
    & [Out] System.Object^ Type  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Type
Type of entity as defined in [swSelectType_e](#)

Return Value

Array of entities (see **Remarks**)

Visual Basic for Applications (VBA) Syntax

See [CompositeCurveFeatureData::GetEntitiesToJoin](#).

Remarks

The entities can be edges, reference curves other than composite curves, projection curves, and sketch entities.

See [Accessing Selections that Define Features](#) for additional details on using this method.

See Also

[ICompositeCurveFeatureData Interface](#)
[ICompositeCurveFeatureData Members](#)
[ICompositeCurveFeatureData::IGetEntitiesToJoin Method](#)
[ICompositeCurveFeatureData::GetEntitiesToJoinCount Method](#)

Availability

SOLIDWORKS 2003 FCS, Revision Number 11.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

GetEntitiesToJoinCount Method (ICompositeCurveFeatureData)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ICompositeCurveFeatureData Interface](#) : GetEntitiesToJoinCount Method (ICompositeCurveFeatureData)

Gets the number of entities that are joined to create a composite curve.

.NET Syntax

Visual Basic (Declaration)

```
Function GetEntitiesToJoinCount() As System.Integer
```

Visual Basic (Usage)

```
Dim instance As ICompositeCurveFeatureData  
Dim value As System.Integer
```

```
value = instance.GetEntitiesToJoinCount()
```

C#

```
System.int GetEntitiesToJoinCount()
```

C++/CLI

```
System.int GetEntitiesToJoinCount();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Return Value

Number of entities

Visual Basic for Applications (VBA) Syntax

See [CompositeCurveFeatureData::GetEntitiesToJoinCount](#).

Example

[Insert a Composite Curve \(C#\)](#)
[Insert a Composite Curve \(VB.NET\)](#)
[Insert a Composite Curve \(VBA\)](#)

Remarks

Call this method before calling [ICompositeCurveFeatureData::IGetEntitiesToJoin](#).

See Also

[ICompositeCurveFeatureData Interface](#)
[ICompositeCurveFeatureData Members](#)
[ICompositeCurveFeatureData::GetEntitiesToJoin Method](#)

Availability

SOLIDWORKS 2003 FCS, Revision Number 11.0

SOLIDWORKS API Help

[Send comments](#) on this topic.

IGetEntitiesToJoin Method (ICompositeCurveFeatureData)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ICompositeCurveFeatureData Interface](#) : IGetEntitiesToJoin Method (ICompositeCurveFeatureData)

Gets the entities to join to create this composite curve.

.NET Syntax

Visual Basic (Declaration)

```
Function IGetEntitiesToJoin( _  
    ByVal Count As System.Integer, _  
    ByRef Type As System.Integer _  
) As System.Object
```

Visual Basic (Usage)



```
Dim instance As ICompositeCurveFeatureData  
Dim Count As System.Integer  
Dim Type As System.Integer  
Dim value As System.Object  
  
value = instance.IGetEntitiesToJoin(Count, Type)
```

C#

```
System.object IGetEntitiesToJoin(  
    System.int Count,  
    out System.int Type  
)
```

C++/CLI

```
System.Object^ IGetEntitiesToJoin(  
& System.int Count,  
& [Out] System.int Type  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Count

Number of entities

Type

Type of entity as defined in [swSelectType_e](#)

Return Value

- in-process, unmanaged C++: Pointer to an array of entities (see **Remarks**)
- VBA, VB.NET, C#, and C++/CLI: Not supported
- See [In-process Methods](#) for details about this type of method.

Remarks

The entities can be edges, reference curves other than composite curves, projection curves, and sketch entities. Call [ICompositeCurveFeatureData::GetEntitiesToJoinCount](#) before calling this method.

See [Accessing Selections that Define Features](#) for additional details on using this method.

See Also

[ICompositeCurveFeatureData Interface](#)

[ICompositeCurveFeatureData Members](#)

[ICompositeCurveFeatureData::GetEntitiesToJoin Method](#)

Availability

SolidWorks 2003 FCS, Revision Number 11.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

ISetEntitiesToJoin Method (ICompositeCurveFeatureData)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ICompositeCurveFeatureData Interface](#) : ISetEntitiesToJoin Method (ICompositeCurveFeatureData)

Sets the entities to join to create this composite curve.

.NET Syntax

Visual Basic (Declaration)

```
Sub ISetEntitiesToJoin( _  
    ByVal Count As System.Integer, _  
    ByRef Ents As System.Object _  
)
```

Visual Basic (Usage)



```
Dim instance As ICompositeCurveFeatureData  
Dim Count As System.Integer  
Dim Ents As System.Object  
  
instance.ISetEntitiesToJoin(Count, Ents)
```

C#

```
void ISetEntitiesToJoin(  
    System.int Count,  
    ref System.object Ents  
)
```

C++/CLI

```
void ISetEntitiesToJoin(  
& System.int Count,  
& System.Object^% Ents  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Count

Number of entities

Ents

in-process, unmanaged C++: Pointer to an array of entities (see **Remarks**)

- VBA, VB.NET, C#, and C++/CLI: Not supported
See [in-process Methods](#) for details about this type of method.

Remarks

The entities can be edges, reference curves other than composite curves, projection curves, and sketch entities.

See [Accessing Selections that Define Features](#) for additional details on using this method.

See Also

[ICompositeCurveFeatureData Interface](#)
[ICompositeCurveFeatureData Members](#)
[ICompositeCurveFeatureData::SetEntitiesToJoin Method](#)

Availability

SOLIDWORKS 2003 FCS, Revision Number 11.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

ReleaseSelectionAccess Method (ICompositeCurveFeatureData)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ICompositeCurveFeatureData Interface](#) : ReleaseSelectionAccess Method (ICompositeCurveFeatureData)

Releases access to the selections that define this composite curve.

.NET Syntax

Visual Basic (Declaration)

```
Sub ReleaseSelectionAccess()
```

Visual Basic (Usage)



```
Dim instance As ICompositeCurveFeatureData  
instance.ReleaseSelectionAccess()
```

C#

```
void ReleaseSelectionAccess()
```

C++/CLI

```
void ReleaseSelectionAccess();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Visual Basic for Applications (VBA) Syntax

See [CompositeCurveFeatureData::ReleaseSelectionAccess](#).

Remarks

[ICompositeCurveFeatureData::AccessSelections](#) puts the model into a rollback state to allow access to the selections that define this feature. Use this method to restore the rollback state if you did not modify the feature or use [IFeature::ModifyDefinition](#) or [IFeature::IModifyDefinition2](#) if you did.

See Also

[ICompositeCurveFeatureData Interface](#)
[ICompositeCurveFeatureData Members](#)

Availability

SOLIDWORKS 2003 FCS, Revision Number 11.0

SOLIDWORKS API Help

[Send comments](#) on this topic.

SetEntitiesToJoin Method (ICompositeCurveFeatureData)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ICompositeCurveFeatureData Interface](#) : SetEntitiesToJoin Method (ICompositeCurveFeatureData)

Sets the entities to join to create this composite curve.

.NET Syntax

Visual Basic (Declaration)

```
Sub SetEntitiesToJoin( _  
    ByVal EntVar As System.Object _  
)
```

Visual Basic (Usage)



```
Dim instance As ICompositeCurveFeatureData  
Dim EntVar As System.Object  
  
instance.SetEntitiesToJoin(EntVar)
```

C#

```
void SetEntitiesToJoin(  
    System.object EntVar  
)
```

C++/CLI

```
void SetEntitiesToJoin(  
    & System.Object^ EntVar  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

EntVar

Array of entities (see **Remarks**)

Visual Basic for Applications (VBA) Syntax

See [CompositeCurveFeatureData::SetEntitiesToJoin](#).

Remarks

The entities can be edges, reference curves other than composite curves, projection curves, and sketch entities.

See [Accessing Selections that Define Features](#) for additional details on using this method.

See Also

[ICompositeCurveFeatureData Interface](#)
[ICompositeCurveFeatureData Members](#)
[ICompositeCurveFeatureData::ISetEntitiesToJoin Method](#)

Availability

SOLIDWORKS 2003 FCS, Revision Number 11.0

IConcentricMateFeatureData (Type)

SOLIDWORKS API Help

[Send comments](#) on this topic.

IConcentricMateFeatureData Interface

[See Also](#) [Members](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) : IConcentricMateFeatureData Interface

Allows access to a concentric mate feature.

NOTE: Click the **Members** link, located near the top of the topic, to see this interface's methods and properties.

.NET Syntax

Visual Basic (Declaration)

```
Public Interface IConcentricMateFeatureData
```

Visual Basic (Usage)



```
Dim instance As IConcentricMateFeatureData
```

C#

```
public interface IConcentricMateFeatureData
```

C++/CLI

```
public interface class IConcentricMateFeatureData
```

Visual Basic for Applications (VBA) Syntax

See [ConcentricMateFeatureData](#).

Example

[Create Standard Mates \(VBA\)](#)
[Create Standard Mates \(C#\)](#)

Remarks

A concentric mate:

- Places selections so that they share the same axis.
- Can be configured to prevent rotation.

[IMateFeatureData](#) is the parent of this mate interface.

To create a concentric mate:

1. Follow general instructions in the [IAssemblyDoc::CreateMate](#) Remarks.
2. Specify [IConcentricMateFeatureData::EntitiesToMate](#) or use [IModelDocExtension::SelectByID2](#) to pre-select the entities to mate using Mark = 1.
3. Specify other properties of the ConcentricMateFeatureData object.

To edit a concentric mate:

1. Access its feature and call [IFeature::GetDefinition](#) to get the MateFeatureData object.
2. Cast the MateFeatureData object to a ConcentricMateFeatureData object.
3. Modify the ConcentricMateFeatureData object.
4. Call [IFeature::ModifyDefinition](#).

To delete this concentric mate, use [IModelDocExtension::DeleteSelection2](#).

Access Diagram

[ConcentricMateFeatureData](#)

See Also

[IConcentricMateFeatureData Members](#)
[SolidWorks.Interop.sldworks Namespace](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

IConcentricMateFeatureData Interface Members

[See Also](#) [Properties](#)



[SolidWorks.Interop.sldworks Namespace](#) : IConcentricMateFeatureData Interface

The following tables list the members exposed by [IConcentricMateFeatureData](#).

Public Properties

Name	Description
EntitiesToMate	Gets or sets the entities to mate in this concentric mate.
LockRotation	Gets or sets whether to lock the rotation of the entities in this concentric mate.
MateAlignment	Gets or sets the mate alignment of this concentric mate.
PickPoints	Gets or sets the pick points for the entities to mate in this concentric mate.

[Top](#)

See Also

[IConcentricMateFeatureData Interface](#)
[SolidWorks.Interop.sldworks Namespace](#)

SOLIDWORKS API Help

[Send comments on this topic.](#)

IConcentricMateFeatureData Interface Properties

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) : IConcentricMateFeatureData Interface

For a list of all members of this type, see [IConcentricMateFeatureData members](#).

Public Properties

Name	Description
EntitiesToMate	Gets or sets the entities to mate in this concentric mate.
LockRotation	Gets or sets whether to lock the rotation of the entities in this concentric mate.
MateAlignment	Gets or sets the mate alignment of this concentric mate.
PickPoints	Gets or sets the pick points for the entities to mate in this concentric mate.

[Top](#)

See Also

[IConcentricMateFeatureData Interface](#)
[SolidWorks.Interop.sldworks Namespace](#)

SOLIDWORKS API Help

[Send comments on this topic.](#)

EntitiesToMate Property (IConcentricMateFeatureData)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IConcentricMateFeatureData Interface](#) : EntitiesToMate Property (IConcentricMateFeatureData)

Gets or sets the entities to mate in this concentric mate.

.NET Syntax

Visual Basic (Declaration)

Property EntitiesToMate As System.Object

Visual Basic (Usage)



```
Dim instance As IConcentricMateFeatureData
Dim value As System.Object

instance.EntitiesToMate = value

value = instance.EntitiesToMate
```

C#

System.Object EntitiesToMate {get; set;}

C++/CLI

```
property System.Object^ EntitiesToMate {
    System.Object^ get();
    void set ( & System.Object^ value);
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

Entities to mate (see **Remarks**)

 Visual Basic for Applications (VBA) Syntax

See [ConcentricMateFeatureData::EntitiesToMate](#).

 Example

See the [IConcentricMateFeatureData](#) example.

 Remarks

You can create concentric mates with the following mate entity combinations:

Mate entity/Mate entity	IEdge (arc, circular edge)	IRefAxis , (cone)	IRefAxis, (cylinder)	IEdge, IRefAxis, ICenterLine , ISketchLine (line)	IRefPoint , IVertex , ISketchPoint	IRefAxis, ISketchPoint IRefPoint, IVertex (sphere)
IEdge (arc, circular edge)	•	•	•	•		
IRefAxis (cone)	•	•	•	•	•	
IRefAxis (cylinder)	•	•	•	•	•	•
IEdge, IRefAxis, ICenterLine, ISketchLine (line)	•	•	•			•
IRefPoint, IVertex, ISketchPoint		•	•			•
IRefAxis, IRefPoint, ISketchPoint, IVertex (sphere)			•	•	•	•

Instead of specifying this property, you can use [IModelDocExtension::SelectByID2](#) to pre-select the entities to mate using Mark = 1. You can pre select mate entities during mate creation, but not during mate editing.

 See Also

[IConcentricMateFeatureData Interface](#)
[IConcentricMateFeatureData Members](#)

 Availability

SOLIDWORKS 2019 FCS, Revision Number 27.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

LockRotation Property (IConcentricMateFeatureData)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IConcentricMateFeatureData Interface](#) : LockRotation Property (IConcentricMateFeatureData)

Gets or sets whether to lock the rotation of the entities in this concentric mate.

 .NET Syntax

Visual Basic (Declaration)

Property LockRotation As System.Boolean

Visual Basic (Usage)

```
Dim instance As IConcentricMateFeatureData
Dim value As System.Boolean

instance.LockRotation = value

value = instance.LockRotation
```

C#

```
System.bool LockRotation {get; set;}
```

C++/CLI

```
property System.bool LockRotation {
    System.bool get();
    void set ( & System.bool value);
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

True to lock rotation, false to not

Visual Basic for Applications (VBA) Syntax

See [ConcentricMateFeatureData::LockRotation](#).

Example

See the [IConcentricMateFeatureData](#) example.

See Also

[IConcentricMateFeatureData Interface](#)
[IConcentricMateFeatureData Members](#)

Availability

SOLIDWORKS 2019 FCS, Revision Number 27.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

MateAlignment Property (IConcentricMateFeatureData)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IConcentricMateFeatureData Interface](#) : MateAlignment Property (IConcentricMateFeatureData)

Gets or sets the mate alignment of this concentric mate.

.NET Syntax

Visual Basic (Declaration)

```
Property MateAlignment As System.Integer
```

Visual Basic (Usage)

```
Dim instance As IConcentricMateFeatureData
Dim value As System.Integer

instance.MateAlignment = value

value = instance.MateAlignment
```

C#

```
System.int MateAlignment {get; set;}
```

C++/CLI

```
property System.int MateAlignment {  
    System.int get();  
    void set ( & System.int value);  
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

Mate alignment as defined in [swMateAlign_e](#)

Visual Basic for Applications (VBA) Syntax

See [ConcentricMateFeatureData::MateAlignment](#).

Example

See the [IConcentricMateFeatureData](#) example.

See Also

[IConcentricMateFeatureData Interface](#)
[IConcentricMateFeatureData Members](#)

Availability

SOLIDWORKS 2019 FCS, Revision Number 27.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

PickPoints Property (IConcentricMateFeatureData)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IConcentricMateFeatureData Interface](#) : PickPoints Property (IConcentricMateFeatureData)

Gets or sets the pick points for the entities to mate in this concentric mate.

.NET Syntax

Visual Basic (Declaration)

Property PickPoints As System.Object

Visual Basic (Usage)



```
Dim instance As IConcentricMateFeatureData  
Dim value As System.Object
```

```
instance.PickPoints = value
```

```
value = instance.PickPoints
```

C#

```
System.object PickPoints {get; set;}
```

C++/CLI

```
property System.Object^ PickPoints {  
    System.Object^ get();  
    void set ( & System.Object^ value);  
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

Array of x, y, z-coordinates, one set for each mate entity

Visual Basic for Applications (VBA) Syntax

See [ConcentricMateFeatureData::PickPoints](#).

Remarks

After you set the pick points for a given selection of [IConcentricMateFeatureData::EntitiesToMate](#), you cannot modify the pick points. If you want to use new pick points, then you must create an entirely new concentric mate.

See Also

[IConcentricMateFeatureData Interface](#)
[IConcentricMateFeatureData Members](#)

Availability

SOLIDWORKS 2019 FCS, Revision Number 27.0