

SOLIDWORKS API (.NET VBA C#) — Reference (96/337): IEnumCoEdges-IEnumFaces

SOLIDWORKS API Documentation (converted from CHM)

IEnumCoEdges (Type)

IEnumCoEdges Interface

[See Also](#) [Members](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) : IEnumCoEdges Interface

Allows access to a [coedges](#) enumeration.

NOTE: Click the **Members** link, located near the top of the topic, to see this interface's methods and properties.

.NET Syntax

Visual Basic (Declaration)

```
Public Interface IEnumCoEdges
```

Visual Basic (Usage)



```
Dim instance As IEnumCoEdges
```

C#

```
public interface IEnumCoEdges
```

C++/CLI

```
public interface class IEnumCoEdges
```

Visual Basic for Applications (VBA) Syntax

See [EnumCoEdges](#).

Example

[Enumerate Bodies \(C++\)](#)

Remarks

For use in in-process DLLs only.

Accessors

[IEdge::EnumCoEdges](#)

[IEnumCoEdges::Clone](#)

[ILoop2::EnumCoEdges](#)

Access Diagram

[EnumCoEdges](#)

See Also

[IEnumCoEdges Members](#)

[SolidWorks.Interop.sldworks Namespace](#)

IEnumCoEdges Interface Members

[See Also](#) [Methods](#)



[SolidWorks.Interop.sldworks Namespace](#) : IEnumCoEdges Interface

The following tables list the members exposed by [IEnumCoEdges](#).

Public Methods

Name	Description
 Clone	Clones the a coedges enumeration.
 Next	Gets the next coedge in the coedges enumeration.
 Reset	Resets the sequence to the beginning of the coedges enumeration.
 Skip	Skips the specified number of coedges in the coedges enumeration.

[Top](#)

See Also

[IEnumCoEdges Interface](#)
[SolidWorks.Interop.sldworks Namespace](#)

SOLIDWORKS API Help

[Send comments on this topic.](#)

IEnumCoEdges Interface Methods

[See Also](#)

 [SolidWorks.Interop.sldworks Namespace](#) : IEnumCoEdges Interface

For a list of all members of this type, see [IEnumCoEdges members](#).

Public Methods

Name	Description
 Clone	Clones the a coedges enumeration.
 Next	Gets the next coedge in the coedges enumeration.
 Reset	Resets the sequence to the beginning of the coedges enumeration.
 Skip	Skips the specified number of coedges in the coedges enumeration.

[Top](#)

See Also

[IEnumCoEdges Interface](#)
[SolidWorks.Interop.sldworks Namespace](#)

SOLIDWORKS API Help

[Send comments on this topic.](#)

Clone Method (IEnumCoEdges)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IEnumCoEdges Interface](#) : Clone Method (IEnumCoEdges)

Clones the a coedges enumeration.

.NET Syntax

Visual Basic (Declaration)

```
Sub Clone( _  
    ByRef Ppenum As EnumCoEdges _  
)
```

Visual Basic (Usage)



```
Dim instance As IEnumCoEdges  
Dim Ppenum As EnumCoEdges  
  
instance.Clone(Ppenum)
```

C#

```
void Clone(  
    out EnumCoEdges Ppenum  
)
```

C++/CLI

```
void Clone(  
&    [Out] EnumCoEdges^ Ppenum  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Ppenum

Pointer to the cloned [coedges enumeration](#)

Visual Basic for Applications (VBA) Syntax

See [EnumCoEdges.Clone](#).

Remarks

For use in in-process DLLs only.

See Also

[IEnumCoEdges Interface](#)

[IEnumCoEdges Members](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

Next Method (IEnumCoEdges)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IEnumCoEdges Interface](#) : Next Method (IEnumCoEdges)

Gets the next coedge in the coedges enumeration.

.NET Syntax

Visual Basic (Declaration)

```
Sub Next(  
    ByVal Celt As System.Integer, _  
    ByRef Rgelt As CoEdge, _  
    ByRef PceltFetched As System.Integer _  
)
```

Visual Basic (Usage)

```
Dim instance As IEnumCoEdges  
Dim Celt As System.Integer  
Dim Rgelt As CoEdge  
Dim PceltFetched As System.Integer  
  
instance.Next(Celt, Rgelt, PceltFetched)
```

C#

```
void Next(  
    System.int Celt,  
    out CoEdge Rgelt,  
    out System.int PceltFetched  
)
```

C++/CLI

```
void Next(  
&    System.int Celt,
```



```
& [Out] CoEdge^ Rgelt,  
& [Out] System.int PceltFetched  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Celt

Number of coedges for the coedges enumeration

Rgelt

Pointer to an array of [coedges](#) of size Celt

PceltFetched

Number of coedges returned from the list; this value can be less than Celt if you asked for more coedges than exist, or it can be NULL if no more coedges exist

Visual Basic for Applications (VBA) Syntax

See [EnumCoEdges::Next](#).

Example

[Enumerate Bodies \(C++\)](#)

Remarks

For use in in-process DLLs only.

See Also

[IEnumCoEdges Interface](#)
[IEnumCoEdges Members](#)
[ICoEdge::GetNext Method](#)
[ICoEdge::IGetNext Method](#)
[ILoop2::GetFirstCoEdge Method](#)
[ILoop2::IGetFirstCoEdge Method](#)

SOLIDWORKS API Help

[Send comments on this topic.](#)

Reset Method (IEnumCoEdges)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IEnumCoEdges Interface](#) : Reset Method (IEnumCoEdges)

Resets the sequence to the beginning of the coedges enumeration.

.NET Syntax

Visual Basic (Declaration)

```
Sub Reset()
```

Visual Basic (Usage)

```
Dim instance As IEnumCoEdges  
instance.Reset()
```

C#

```
void Reset()
```

C++/CLI

```
void Reset();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Visual Basic for Applications (VBA) Syntax

See [EnumCoEdges::Reset](#).

Remarks

For use in in-process DLLs only.

See Also

[IEnumCoEdges Interface](#)
[IEnumCoEdges Members](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

Skip Method (IEnumCoEdges)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IEnumCoEdges Interface](#) : Skip Method (IEnumCoEdges)

Skips the specified number of coedges in the coedges enumeration.

.NET Syntax

Visual Basic (Declaration)

```
Sub Skip(  
    ByVal Celt As System.Integer _  
)
```

Visual Basic (Usage)



```
Dim instance As IEnumCoEdges  
Dim Celt As System.Integer
```

```
instance.Skip(Celt)
```

C#

```
void Skip(  
    System.int Celt  
)
```

C++/CLI

```
void Skip(  
& System.int Celt  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Celt

Number of coedges to skip

Visual Basic for Applications (VBA) Syntax

See [EnumCoEdges::Skip](#).

Remarks

For use in in-process DLLs only.

See Also

[IEnumCoEdges Interface](#)
[IEnumCoEdges Members](#)

IEnumComponents (Type)

IEnumComponents Interface

[See Also](#) [Members](#)



[SolidWorks.Interop.sldworks Namespace](#) : IEnumComponents Interface

Obsolete. Superseded by [IEnumComponents2](#).

NOTE: Click the **Members** link, located near the top of the topic, to see this interface's methods and properties.

.NET Syntax

Visual Basic (Declaration)

```
Public Interface IEnumComponents
```

Visual Basic (Usage)



```
Dim instance As IEnumComponents
```

C#

```
public interface IEnumComponents
```

C++/CLI

```
public interface class IEnumComponents
```

Visual Basic for Applications (VBA) Syntax

See [EnumComponents](#).

See Also

[IEnumComponents Members](#)
[SolidWorks.Interop.sldworks Namespace](#)

IEnumComponents Interface Methods

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) : IEnumComponents Interface

For a list of all members of this type, see [IEnumComponents members](#).

Public Methods

Name	Description
Clone	Obsolete. Superseded by IEnumComponents2.Clone .
Next	Obsolete. Superseded by IEnumComponents2.Next .
Reset	Obsolete. Superseded by IEnumComponents2.Reset .
Skip	Obsolete. Superseded by IEnumComponents2.Skip .

[Top](#)

See Also

[IEnumComponents Interface](#)
[SolidWorks.Interop.sldworks Namespace](#)

IEnumComponents Interface Members

[See Also](#) [Methods](#)



[SolidWorks.Interop.sldworks Namespace](#) : IEnumComponents Interface

The following tables list the members exposed by [IEnumComponents](#).

Public Methods

Name	Description
Clone	Obsolete. Superseded by IEnumComponents2.Clone .
Next	Obsolete. Superseded by IEnumComponents2.Next .
Reset	Obsolete. Superseded by IEnumComponents2.Reset .
Skip	Obsolete. Superseded by IEnumComponents2.Skip .

[Top](#)

See Also

[IEnumComponents Interface](#)
[SolidWorks.Interop.sldworks Namespace](#)

Clone Method (IEnumComponents)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IEnumComponents Interface](#) : Clone Method (IEnumComponents)

Obsolete. Superseded by [IEnumComponents2.Clone](#).

.NET Syntax

Visual Basic (Declaration)

```
Sub Clone( _  
    ByRef Ppenum As EnumComponents _  
)
```

Visual Basic (Usage)

Copy Code

```
Dim instance As IEnumComponents  
Dim Ppenum As EnumComponents  
  
instance.Clone(Ppenum)
```

C#

```
void Clone(  
    out EnumComponents Ppenum  
)
```

C++/CLI

```
void Clone(  
& [Out] EnumComponents^ Ppenum  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Ppenum

Visual Basic for Applications (VBA) Syntax

See [EnumComponents.Clone](#).

See Also

[IEnumComponents Interface](#)
[IEnumComponents Members](#)

Next Method (IEnumComponents)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IEnumComponents Interface](#) : Next Method (IEnumComponents)

Obsolete. Superseded by [IEnumComponents2::Next](#).

.NET Syntax

Visual Basic (Declaration)

```
Sub Next( _  
    ByVal Celt As System.Integer, _  
    ByRef Rgelt As Component, _  
    ByRef PceltFetched As System.Integer _  
)
```

Visual Basic (Usage)



```
Dim instance As IEnumComponents  
Dim Celt As System.Integer  
Dim Rgelt As Component  
Dim PceltFetched As System.Integer  
  
instance.Next(Celt, Rgelt, PceltFetched)
```

C#

```
void Next(  
    System.int Celt,  
    out Component Rgelt,  
    out System.int PceltFetched  
)
```

C++/CLI

```
void Next(  
&    System.int Celt,  
&    [Out] Component^ Rgelt,  
&    [Out] System.int PceltFetched  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Celt

Rgelt

PceltFetched

Visual Basic for Applications (VBA) Syntax

See [EnumComponents::Next](#).

See Also

[IEnumComponents Interface](#)
[IEnumComponents Members](#)

Reset Method (IEnumComponents)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IEnumComponents Interface](#) : Reset Method (IEnumComponents)

Obsolete. Superseded by [IEnumComponents2::Reset](#).

.NET Syntax

Visual Basic (Declaration)

```
Sub Reset()
```

Visual Basic (Usage)



```
Dim instance As IEnumComponents  
  
instance.Reset()
```

C#

```
void Reset()
```

C++/CLI

```
void Reset();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Visual Basic for Applications (VBA) Syntax

See [EnumComponents::Reset](#).

See Also

[IEnumComponents Interface](#)
[IEnumComponents Members](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

Skip Method (IEnumComponents)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IEnumComponents Interface](#) : Skip Method (IEnumComponents)

Obsolete. Superseded by [IEnumComponents2::Skip](#).

.NET Syntax

Visual Basic (Declaration)

```
Sub Skip(  
    ByVal Celt As System.Integer  
)
```

Visual Basic (Usage)



```
Dim instance As IEnumComponents  
Dim Celt As System.Integer  
  
instance.Skip(Celt)
```

C#

```
void Skip(  
    System.int Celt  
)
```

C++/CLI

```
void Skip(  
& System.int Celt  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Visual Basic for Applications (VBA) Syntax

See [EnumComponents::Skip](#).

See Also

[IEnumComponents Interface](#)
[IEnumComponents Members](#)

IEnumComponents2 (Type)

IEnumComponents2 Interface

[See Also](#) [Members](#)



[SolidWorks.Interop.sldworks Namespace](#) : IEnumComponents2 Interface

Allows access to a [components](#) enumeration.

NOTE: Click the **Members** link, located near the top of the topic, to see this interface's methods and properties.

.NET Syntax

Visual Basic (Declaration)

```
Public Interface IEnumComponents2
```

Visual Basic (Usage)

```
Dim instance As IEnumComponents2
```

C#

```
public interface IEnumComponents2
```

C++/CLI

```
public interface class IEnumComponents2
```

Visual Basic for Applications (VBA) Syntax

See [EnumComponents2](#).

Remarks

For use in in-process DLLs only.

Accessors

[IDrSection::EnumExcludedComponents2](#)

[IEnumComponents2::Clone](#)

[IView::EnumHiddenComponents2](#)

Access Diagram

[EnumComponents2](#)

See Also

[IEnumComponents2 Members](#)
[SolidWorks.Interop.sldworks Namespace](#)

IEnumComponents2 Interface Members

[See Also](#) [Methods](#)



[SolidWorks.Interop.sldworks Namespace](#) : IEnumComponents2 Interface

The following tables list the members exposed by [IEnumComponents2](#).

Public Methods

Name	Description
Clone	Clones the components enumeration.

 Next	Gets the next component in the components enumeration.
 Reset	Resets the sequence to the beginning of the components enumeration.
 Skip	Skips the specified number of components in the components enumeration.

[Top](#)

 See Also

[IEnumComponents2 Interface](#)
[SolidWorks.Interop.sldworks Namespace](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

IEnumComponents2 Interface Methods

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) : IEnumComponents2 Interface

For a list of all members of this type, see [IEnumComponents2 members](#).

 Public Methods

Name	Description
 Clone	Clones the components enumeration.
 Next	Gets the next component in the components enumeration.
 Reset	Resets the sequence to the beginning of the components enumeration.
 Skip	Skips the specified number of components in the components enumeration.

[Top](#)

 See Also

[IEnumComponents2 Interface](#)
[SolidWorks.Interop.sldworks Namespace](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

Clone Method (IEnumComponents2)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IEnumComponents2 Interface](#) : Clone Method (IEnumComponents2)

Clones the components enumeration.

 .NET Syntax

Visual Basic (Declaration)

```
Sub Clone( _  
    ByRef Ppenum As EnumComponents2 _  
)
```

Visual Basic (Usage)



```
Dim instance As IEnumComponents2  
Dim Ppenum As EnumComponents2  
  
instance.Clone(Ppenum)
```

C#

```
void Clone(  
    out EnumComponents2 Ppenum  
)
```

C++/CLI

```
void Clone(  
& [Out] EnumComponents2^ Ppenum
```

)

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Ppenum

Pointer to the cloned [components enumeration](#)

Visual Basic for Applications (VBA) Syntax

See [EnumComponents2.Clone](#).

Remarks

For use in in-process DLLs only.

See Also

[IEnumComponents2 Interface](#)

[IEnumComponents2 Members](#)

Availability

SOLIDWORKS 2001Plus FCS, Revision Number 10.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

Next Method (IEnumComponents2)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IEnumComponents2 Interface](#) : Next Method (IEnumComponents2)

Gets the next component in the components enumeration.

.NET Syntax

Visual Basic (Declaration)

```
Sub Next( _  
    ByVal Celt As System.Integer, _  
    ByRef Rgelt As Component2, _  
    ByRef PceltFetched As System.Integer _  
)
```

Visual Basic (Usage)



```
Dim instance As IEnumComponents2  
Dim Celt As System.Integer  
Dim Rgelt As Component2  
Dim PceltFetched As System.Integer  
  
instance.Next(Celt, Rgelt, PceltFetched)
```

C#

```
void Next(  
    System.int Celt,  
    out Component2 Rgelt,  
    out System.int PceltFetched  
)
```

C++/CLI

```
void Next(  
& System.int Celt,  
& [Out] Component2^ Rgelt,  
& [Out] System.int PceltFetched  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Celt

Number of components for the components enumeration

Rgelt

Pointer to an array [components](#) of size Celt

PceltFetched

Pointer to the number of components returned from the list.; this value can be less than Celt if you ask for more components than exist, or it can be NULL if no more components exist

Visual Basic for Applications (VBA) Syntax

See [EnumComponents2::Next](#).

Remarks

For use in in-process DLLs only.

See Also

[IEnumComponents2 Interface](#)
[IEnumComponents2 Members](#)

Availability

SOLIDWORKS 2001Plus FCS, Revision Number 10.0

SOLIDWORKS API Help

[Send comments](#) on this topic.

Reset Method (IEnumComponents2)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IEnumComponents2 Interface](#) : Reset Method (IEnumComponents2)

Resets the sequence to the beginning of the components enumeration.

.NET Syntax

Visual Basic (Declaration)

```
Sub Reset()
```

Visual Basic (Usage)



```
Dim instance As IEnumComponents2  
instance.Reset()
```

C#

```
void Reset()
```

C++/CLI

```
void Reset();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Visual Basic for Applications (VBA) Syntax

See [EnumComponents2::Reset](#).

Remarks

For use in in-process DLLs only.

See Also

[IEnumComponents2 Interface](#)
[IEnumComponents2 Members](#)

Availability

SOLIDWORKS 2001Plus FCS, Revision Number 10.0

SOLIDWORKS API Help

[Send comments](#) on this topic.

Skip Method (IEnumComponents2)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IEnumComponents2 Interface](#) : Skip Method (IEnumComponents2)

Skips the specified number of components in the components enumeration.

.NET Syntax

Visual Basic (Declaration)

```
Sub Skip( _  
    ByVal Celt As System.Integer _  
)
```

Visual Basic (Usage)



```
Dim instance As IEnumComponents2  
Dim Celt As System.Integer  
  
instance.Skip(Celt)
```

C#

```
void Skip(  
    System.int Celt  
)
```

C++/CLI

```
void Skip(  
& System.int Celt  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Celt

Number of components to skip

Visual Basic for Applications (VBA) Syntax

See [EnumComponents2::Skip](#).

Remarks

For use in in-process DLLs only.

See Also

[IEnumComponents2 Interface](#)
[IEnumComponents2 Members](#)

IEnumDisplayDimensions (Type)

IEnumDisplayDimensions Interface

[See Also](#) [Members](#)



[SolidWorks.Interop.sldworks Namespace](#) : IEnumDisplayDimensions Interface

Allows access to a [display dimensions](#) enumeration.

NOTE: Click the **Members** link, located near the top of the topic, to see this interface's methods and properties.

.NET Syntax

Visual Basic (Declaration)

```
Public Interface IEnumDisplayDimensions
```

Visual Basic (Usage)

```
Dim instance As IEnumDisplayDimensions
```

C#

```
public interface IEnumDisplayDimensions
```

C++/CLI

```
public interface class IEnumDisplayDimensions
```

Visual Basic for Applications (VBA) Syntax

See [EnumDisplayDimensions](#).

Remarks

For use in in-process DLLs only.

Accessors

[IEnumDisplayDimensions::Clone](#)
[IFeature::EnumDisplayDimensions](#)

Access Diagram

[EnumDisplayDimensions](#)

See Also

[IEnumDisplayDimensions Members](#)
[SolidWorks.Interop.sldworks Namespace](#)

IEnumDisplayDimensions Interface Methods

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) : IEnumDisplayDimensions Interface

For a list of all members of this type, see [IEnumDisplayDimensions members](#).

Public Methods

Name	Description
Clone	Clones the display dimensions enumeration.
Next	Gets the next display dimension in the display dimensions enumeration.

 Reset	Resets the sequence to the beginning of the display dimensions enumeration.
 Skip	Skips the specified number of display dimensions in the display dimensions enumeration.

[Top](#)

 See Also

[IEnumDisplayDimensions Interface](#)
[SolidWorks.Interop.sldworks Namespace](#)

SOLIDWORKS API Help

[Send comments on this topic.](#)

IEnumDisplayDimensions Interface Members

[See Also](#) [Methods](#)

	SolidWorks.Interop.sldworks Namespace : IEnumDisplayDimensions Interface
---	--

The following tables list the members exposed by [IEnumDisplayDimensions](#).

 Public Methods

Name	Description
 Clone	Clones the display dimensions enumeration.
 Next	Gets the next display dimension in the display dimensions enumeration.
 Reset	Resets the sequence to the beginning of the display dimensions enumeration.
 Skip	Skips the specified number of display dimensions in the display dimensions enumeration.

[Top](#)

 See Also

[IEnumDisplayDimensions Interface](#)
[SolidWorks.Interop.sldworks Namespace](#)

SOLIDWORKS API Help

[Send comments on this topic.](#)

Clone Method (IEnumDisplayDimensions)

[See Also](#)

	
SolidWorks.Interop.sldworks Namespace > IEnumDisplayDimensions Interface : Clone Method (IEnumDisplayDimensions)	
Clones the display dimensions enumeration.	

 I.NET Syntax

Visual Basic (Declaration)

```
Sub Clone( _  
    ByRef Ppenum As EnumDisplayDimensions _  
)
```

Visual Basic (Usage)

```
Dim instance As IEnumDisplayDimensions  
Dim Ppenum As EnumDisplayDimensions  
  
instance.Clone(Ppenum)
```

C#

```
void Clone(  
    out EnumDisplayDimensions Ppenum  
)
```

C++/CLI

```
void Clone(  
& [Out] EnumDisplayDimensions^ Ppenum  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Ppenum

Pointer to the cloned [display dimensions enumeration](#)

Visual Basic for Applications (VBA) Syntax

See [EnumDisplayDimensions::Clone](#).

Remarks

For use in in-process DLLs only.

See Also

[IEnumDisplayDimensions Interface](#)

[IEnumDisplayDimensions Members](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

Next Method (IEnumDisplayDimensions)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IEnumDisplayDimensions Interface](#) : Next Method (IEnumDisplayDimensions)

Gets the next display dimension in the display dimensions enumeration.

.NET Syntax

Visual Basic (Declaration)

```
Sub Next( _  
    ByVal Celt As System.Integer, _  
    ByRef Rgelt As DisplayDimension, _  
    ByRef PceltFetched As System.Integer _  
)
```

Visual Basic (Usage)



```
Dim instance As IEnumDisplayDimensions  
Dim Celt As System.Integer  
Dim Rgelt As DisplayDimension  
Dim PceltFetched As System.Integer  
  
instance.Next(Celt, Rgelt, PceltFetched)
```

C#

```
void Next(  
    System.int Celt,  
    out DisplayDimension Rgelt,  
    out System.int PceltFetched  
)
```

C++/CLI

```
void Next(  
& System.int Celt,  
& [Out] DisplayDimension^ Rgelt,  
& [Out] System.int PceltFetched  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Celt

Number of display dimensions for the display dimension enumeration

Rgelt

Pointer to an array of [display dimensions](#) in of size Celt

PceltFetched

Pointer to the number of display dimensions from the list; this value can be less than Celt if you ask for more display dimensions than exist, or it can be NULL if no more display dimensions exist

Visual Basic for Applications (VBA) Syntax

See [EnumDisplayDimensions::Next](#).

Remarks

For use in in-process DLLs only.

See Also

[IEnumDisplayDimensions Interface](#)
[IEnumDisplayDimensions Members](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

Reset Method (IEnumDisplayDimensions)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IEnumDisplayDimensions Interface](#) : Reset Method (IEnumDisplayDimensions)

Resets the sequence to the beginning of the display dimensions enumeration.

.NET Syntax

Visual Basic (Declaration)

```
Sub Reset()
```

Visual Basic (Usage)



```
Dim instance As IEnumDisplayDimensions
```

```
instance.Reset()
```

C#

```
void Reset()
```

C++/CLI

```
void Reset();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Visual Basic for Applications (VBA) Syntax

See [EnumDisplayDimensions::Reset](#).

Remarks

For use in in-process DLLs only.

See Also

[IEnumDisplayDimensions Interface](#)
[IEnumDisplayDimensions Members](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

Skip Method (IEnumDisplayDimensions)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IEnumDisplayDimensions Interface](#) : Skip Method (IEnumDisplayDimensions)

Skips the specified number of display dimensions in the display dimensions enumeration.

.NET Syntax

Visual Basic (Declaration)

```
Sub Skip( _  
    ByVal Celt As System.Integer _  
)
```

Visual Basic (Usage)



```
Dim instance As IEnumDisplayDimensions  
Dim Celt As System.Integer  
  
instance.Skip(Celt)
```

C#

```
void Skip(  
    System.int Celt  
)
```

C++/CLI

```
void Skip(  
& System.int Celt  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Celt
Number of display dimensions to skip

Visual Basic for Applications (VBA) Syntax

See [EnumDisplayDimensions::Skip](#).

Remarks

For use in in-process DLLs only.

See Also

[IEnumDisplayDimensions Interface](#)
[IEnumDisplayDimensions Members](#)

IEnumDocuments (Type)

IEnumDocuments Interface

[See Also](#) [Members](#)



[SolidWorks.Interop.sldworks Namespace](#) : IEnumDocuments Interface

Obsolete. Superseded by [IEnumDocuments2](#).

NOTE: Click the **Members** link, located near the top of the topic, to see this interface's methods and properties.

.NET Syntax

Visual Basic (Declaration)

Public Interface IEnumDocuments

Visual Basic (Usage)

Dim instance As [IEnumDocuments](#)

C#

public interface IEnumDocuments

C++/CLI

public interface class IEnumDocuments

Visual Basic for Applications (VBA) Syntax

See [EnumDocuments](#).

See Also

[IEnumDocuments Members](#)
[SolidWorks.Interop.sldworks Namespace](#)

IEnumDocuments Interface Methods

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) : IEnumDocuments Interface

For a list of all members of this type, see [IEnumDocuments members](#).

Public Methods

Name	Description
Clone	Obsolete. Superseded by IEnumDocuments2.Clone .
Next	Obsolete. Superseded by IEnumDocuments2.Next .
Reset	Obsolete. Superseded by IEnumDocuments2.Reset .
Skip	Obsolete. Superseded by IEnumDocument2.Skip .

[Top](#)

See Also

[IEnumDocuments Interface](#)
[SolidWorks.Interop.sldworks Namespace](#)

IEnumDocuments Interface Members

[See Also](#) [Methods](#)



[SolidWorks.Interop.sldworks Namespace](#) : IEnumDocuments Interface

The following tables list the members exposed by [IEnumDocuments](#).

Public Methods

Name	Description
Clone	Obsolete. Superseded by IEnumDocuments2.Clone .
Next	Obsolete. Superseded by IEnumDocuments2.Next .
Reset	Obsolete. Superseded by IEnumDocuments2.Reset .
Skip	Obsolete. Superseded by IEnumDocument2.Skip .

[Top](#)

See Also

[IEnumDocuments Interface](#)
[SolidWorks.Interop.sldworks Namespace](#)

Clone Method (IEnumDocuments)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IEnumDocuments Interface](#) : Clone Method (IEnumDocuments)

Obsolete. Superseded by [IEnumDocuments2.Clone](#).

.NET Syntax

Visual Basic (Declaration)

```
Sub Clone( _  
    ByRef Ppenum As EnumDocuments _  
)
```

Visual Basic (Usage)

Copy Code

```
Dim instance As IEnumDocuments  
Dim Ppenum As EnumDocuments  
  
instance.Clone(Ppenum)
```

C#

```
void Clone(  
    out EnumDocuments Ppenum  
)
```

C++/CLI

```
void Clone(  
& [Out] EnumDocuments^ Ppenum  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Ppenum

Visual Basic for Applications (VBA) Syntax

See [EnumDocuments::Clone](#).

See Also

[IEnumDocuments Interface](#)
[IEnumDocuments Members](#)

Next Method (IEnumDocuments)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IEnumDocuments Interface](#) : Next Method (IEnumDocuments)

Obsolete. Superseded by [IEnumDocuments2::Next](#).

.NET Syntax

Visual Basic (Declaration)

```
Sub Next( _  
    ByVal Celt As System.Integer, _  
    ByRef Rgelt As ModelDoc, _  
    ByRef PceltFetched As System.Integer _  
)
```

Visual Basic (Usage)



```
Dim instance As IEnumDocuments  
Dim Celt As System.Integer  
Dim Rgelt As ModelDoc  
Dim PceltFetched As System.Integer  
  
instance.Next(Celt, Rgelt, PceltFetched)
```

C#

```
void Next(  
    System.int Celt,  
    out ModelDoc Rgelt,  
    out System.int PceltFetched  
)
```

C++/CLI

```
void Next(  
&    System.int Celt,  
&    [Out] ModelDoc^ Rgelt,  
&    [Out] System.int PceltFetched  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Celt

Rgelt

PceltFetched

Visual Basic for Applications (VBA) Syntax

See [EnumDocuments::Next](#).

See Also

[IEnumDocuments Interface](#)
[IEnumDocuments Members](#)

Reset Method (IEnumDocuments)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IEnumDocuments Interface](#) : Reset Method (IEnumDocuments)

Obsolete. Superseded by [IEnumDocuments2::Reset](#).

.NET Syntax

Visual Basic (Declaration)

```
Sub Reset()
```

Visual Basic (Usage)



```
Dim instance As IEnumDocuments  
  
instance.Reset()
```

C#

```
void Reset()
```

C++/CLI

```
void Reset();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Visual Basic for Applications (VBA) Syntax

See [EnumDocuments::Reset](#).

See Also

[IEnumDocuments Interface](#)
[IEnumDocuments Members](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

Skip Method (IEnumDocuments)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IEnumDocuments Interface](#) : Skip Method (IEnumDocuments)

Obsolete. Superseded by [IEnumDocument2::Skip](#).

.NET Syntax

Visual Basic (Declaration)

```
Sub Skip(  
    ByVal Celt As System.Integer  
)
```

Visual Basic (Usage)



```
Dim instance As IEnumDocuments  
Dim Celt As System.Integer  
  
instance.Skip(Celt)
```

C#

```
void Skip(  
    System.int Celt  
)
```

C++/CLI

```
void Skip(  
& System.int Celt  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Visual Basic for Applications (VBA) Syntax

See [EnumDocuments::Skip](#).

See Also

[IEnumDocuments Interface](#)
[IEnumDocuments Members](#)

IEnumDocuments2 (Type)

IEnumDocuments2 Interface

[See Also](#) [Members](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) : IEnumDocuments2 Interface

Allows access to a [documents](#) enumeration.

NOTE: Click the **Members** link, located near the top of the topic, to see this interface's methods and properties.

.NET Syntax

Visual Basic (Declaration)

```
Public Interface IEnumDocuments2
```

Visual Basic (Usage)

```
Dim instance As IEnumDocuments2
```

C#

```
public interface IEnumDocuments2
```

C++/CLI

```
public interface class IEnumDocuments2
```

Visual Basic for Applications (VBA) Syntax

See [EnumDocuments2](#).

Example

[Get List of Open Documents \(C++\)](#)
[Traverse All Open Documents \(C++\)](#)

Remarks

For use in in-process DLLs only.

The list of [IModelDoc2](#) objects in the IEnumDocuments2 object contains all open IModelDoc2 pointers, including IModelDoc2 objects opened as file references (for example, from an assembly or drawing). You can use [IModelDoc2::Visible](#) to determine if a particular document has its own window and is visible to the user.

Accessors

[IEnumDocuments2::Clone](#)
[ISldWorks::EnumDocuments2](#)

Access Diagram

[EnumDocuments2](#)

See Also

[IEnumDocuments2 Members](#)
[SolidWorks.Interop.sldworks Namespace](#)

IEnumDocuments2 Interface Methods

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) : IEnumDocuments2 Interface

For a list of all members of this type, see [IEnumDocuments2 members](#).

Public Methods

Name	Description
 Clone	Clones the documents enumeration.
 Next	Gets the next document in the documents enumeration.
 Reset	Resets the sequence to the beginning of the documents enumeration.
 Skip	Skips the specified number of documents in the documents enumeration.

[Top](#)

See Also

[IEnumDocuments2 Interface](#)
[SolidWorks.Interop.sldworks Namespace](#)

SOLIDWORKS API Help

[Send comments on this topic.](#)

IEnumDocuments2 Interface Members

[See Also](#) [Methods](#)



[SolidWorks.Interop.sldworks Namespace](#) : IEnumDocuments2 Interface

The following tables list the members exposed by [IEnumDocuments2](#).

Public Methods

Name	Description
 Clone	Clones the documents enumeration.
 Next	Gets the next document in the documents enumeration.
 Reset	Resets the sequence to the beginning of the documents enumeration.
 Skip	Skips the specified number of documents in the documents enumeration.

[Top](#)

See Also

[IEnumDocuments2 Interface](#)
[SolidWorks.Interop.sldworks Namespace](#)

SOLIDWORKS API Help

[Send comments on this topic.](#)

Clone Method (IEnumDocuments2)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IEnumDocuments2 Interface](#) : Clone Method (IEnumDocuments2)

Clones the documents enumeration.

.NET Syntax

Visual Basic (Declaration)

```
Sub Clone( _  
    ByRef Ppenum As EnumDocuments2 _  
)
```

Visual Basic (Usage)



```
Dim instance As IEnumDocuments2  
Dim Ppenum As EnumDocuments2  
  
instance.Clone(Ppenum)
```

C#

```
void Clone(  
    out EnumDocuments2 Ppenum  
)
```

C++/CLI

```
void Clone(  
& [Out] EnumDocuments2^ Ppenum  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Ppenum

Pointer to the cloned [documents enumeration](#)

Visual Basic for Applications (VBA) Syntax

See [EnumDocuments2::Clone](#).

Remarks

For use in in-process DLLs only.

See Also

[IEnumDocuments2 Interface](#)
[IEnumDocuments2 Members](#)

Availability

SOLIDWORKS 2001Plus FCS, Revision Number 10.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

Next Method (IEnumDocuments2)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IEnumDocuments2 Interface](#) : Next Method (IEnumDocuments2)

Gets the next document in the documents enumeration.

.NET Syntax

Visual Basic (Declaration)

```
Sub Next( _  
    ByVal Celt As System.Integer, _  
    ByRef Rgelt As ModelDoc2, _  
    ByRef PceltFetched As System.Integer _  
)
```

Visual Basic (Usage)



```
Dim instance As IEnumDocuments2  
Dim Celt As System.Integer  
Dim Rgelt As ModelDoc2  
Dim PceltFetched As System.Integer  
  
instance.Next(Celt, Rgelt, PceltFetched)
```

C#

```
void Next(
    System.int Celt,
    out ModelDoc2 Rgelt,
    out System.int PceltFetched
)
```

C++/CLI

```
void Next(
    & System.int Celt,
    & [Out] ModelDoc2^ Rgelt,
    & [Out] System.int PceltFetched
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Celt

Number of documents for the documents enumeration

Rgelt

Pointer to an array of [documents](#) of size Celt

PceltFetched

Pointer to the number of documents returned from the list; this value can be less than Celt if you ask for more documents than exist, or it can be NULL if no more documents exist.

Visual Basic for Applications (VBA) Syntax

See [EnumDocuments2::Next](#).

Example

[Get List of Open Documents \(C++\)](#)
[Traverse All Open Documents \(C++\)](#)

Remarks

For use in in-process DLLs only.

See Also

[IEnumDocuments2 Interface](#)
[IEnumDocuments2 Members](#)

Availability

SOLIDWORKS 2001Plus FCS, Revision Number 10.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

Reset Method (IEnumDocuments2)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IEnumDocuments2 Interface](#) : Reset Method (IEnumDocuments2)

Resets the sequence to the beginning of the documents enumeration.

.NET Syntax

Visual Basic (Declaration)

```
Sub Reset()
```

Visual Basic (Usage)



```
Dim instance As IEnumDocuments2
```

```
instance.Reset()
```

C#

```
void Reset()
```

C++/CLI

```
void Reset();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Visual Basic for Applications (VBA) Syntax

See [EnumDocuments2::Reset](#).

Example

[Get List of Open Documents \(C++\)](#)

Remarks

For use in in-process DLLs only.

See Also

[IEnumDocuments2 Interface](#)
[IEnumDocuments2 Members](#)

Availability

SOLIDWORKS 2001Plus FCS, Revision 10.0

SOLIDWORKS API Help

[Send comments](#) on this topic.

Skip Method (IEnumDocuments2)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IEnumDocuments2 Interface](#) : Skip Method (IEnumDocuments2)

Skips the specified number of documents in the documents enumeration.

.NET Syntax

Visual Basic (Declaration)

```
Sub Skip(  
    ByVal Celt As System.Integer _  
)
```

Visual Basic (Usage)



```
Dim instance As IEnumDocuments2  
Dim Celt As System.Integer  
  
instance.Skip(Celt)
```

C#

```
void Skip(  
    System.int Celt  
)
```

C++/CLI

```
void Skip(  
& System.int Celt  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Celt
Number of documents to skip

Visual Basic for Applications (VBA) Syntax

See [EnumDocuments2::Skip](#).

Remarks

For use in in-process DLLs only.

See Also

[IEnumDocuments2 Interface](#)
[IEnumDocuments2 Members](#)

Availability

SOLIDWORKS 2001Plus FCS, Revision Number 10.0

IEnumDrSections (Type)

IEnumDrSections Interface

[See Also](#) [Members](#)



[SolidWorks.Interop.sldworks Namespace](#) : IEnumDrSections Interface

Allows access to a [section views](#) enumeration.

NOTE: Click the **Members** link, located near the top of the topic, to see this interface's methods and properties.

.NET Syntax

Visual Basic (Declaration)

```
Public Interface IEnumDrSections
```

Visual Basic (Usage)

```
Dim instance As IEnumDrSections
```

C#

```
public interface IEnumDrSections
```

C++/CLI

```
public interface class IEnumDrSections
```

Visual Basic for Applications (VBA) Syntax

See [EnumDrSections](#).

Remarks

For use in in-process DLLs only.

Accessors

[IEnumDrSections::Clone](#)

[IView::EnumSectionLines](#)

Access Diagram

[EnumDrSections](#)

See Also

[IEnumDrSections Members](#)

[SolidWorks.Interop.sldworks Namespace](#)

IEnumDrSections Interface Members

[See Also](#) [Methods](#)



[SolidWorks.Interop.sldworks Namespace](#) : IEnumDrSections Interface

The following tables list the members exposed by [IEnumDrSections](#).

Public Methods

Name	Description
Clone	Clones the section views enumeration.
Next	Gets the next section view in the section views enumeration.

 Reset	Resets the sequence to the beginning of the section views enumeration.
 Skip	Skips the specified number of section views in the section views enumeration.

[Top](#)

 See Also

[IEnumDrSections Interface](#)
[SolidWorks.Interop.sldworks Namespace](#)

SOLIDWORKS API Help

[Send comments on this topic.](#)

IEnumDrSections Interface Methods

[See Also](#)

 [SolidWorks.Interop.sldworks Namespace](#) : IEnumDrSections Interface

For a list of all members of this type, see [IEnumDrSections members](#).

 Public Methods

Name	Description
 Clone	Clones the section views enumeration.
 Next	Gets the next section view in the section views enumeration.
 Reset	Resets the sequence to the beginning of the section views enumeration.
 Skip	Skips the specified number of section views in the section views enumeration.

[Top](#)

 See Also

[IEnumDrSections Interface](#)
[SolidWorks.Interop.sldworks Namespace](#)

SOLIDWORKS API Help

[Send comments on this topic.](#)

Clone Method (IEnumDrSections)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IEnumDrSections Interface](#) : Clone Method (IEnumDrSections)

Clones the section views enumeration.

 I.NET Syntax

Visual Basic (Declaration)

```
Sub Clone( _  
    ByRef Ppenum As EnumDrSections _  
)
```

Visual Basic (Usage)

```
Dim instance As IEnumDrSections  
Dim Ppenum As EnumDrSections  
  
instance.Clone(Ppenum)
```

C#

```
void Clone(  
    out EnumDrSections Ppenum  
)
```

C++/CLI

```
void Clone(  
& [Out] EnumDrSections^ Ppenum  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Ppenum

Pointer to the cloned [section views enumeration](#)

Visual Basic for Applications (VBA) Syntax

See [EnumDrSections::Clone](#).

Remarks

For use in in-process DLLs only.

See Also

[IEnumDrSections Interface](#)

[IEnumDrSections Members](#)

Availability

SOLIDWORKS 2000 FCS, Revision Number 8.0

SOLIDWORKS API Help

[Send comments on this topic](#).

Next Method (IEnumDrSections)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IEnumDrSections Interface](#) : Next Method (IEnumDrSections)

Gets the next section view in the section views enumeration.

.NET Syntax

Visual Basic (Declaration)

```
Sub Next( _  
    ByVal Celt As System.Integer, _  
    ByRef Rgelt As DrSection, _  
    ByRef PceltFetched As System.Integer _  
)
```

Visual Basic (Usage)



```
Dim instance As IEnumDrSections  
Dim Celt As System.Integer  
Dim Rgelt As DrSection  
Dim PceltFetched As System.Integer  
  
instance.Next(Celt, Rgelt, PceltFetched)
```

C#

```
void Next(  
    System.int Celt,  
    out DrSection Rgelt,  
    out System.int PceltFetched  
)
```

C++/CLI

```
void Next(  
& System.int Celt,  
& [Out] DrSection^ Rgelt,  
& [Out] System.int PceltFetched  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Celt

Number of section views for the section views enumeration

Rgelt

Pointer to an array of [section views](#) of size Celt

PceltFetched

Pointer to the number of drawing sections returned from the list; this value can be less than Celt if you ask for more drawing sections than exist, or it can be NULL if no more drawing sections exist

Visual Basic for Applications (VBA) Syntax

See [EnumDrSections::Next](#).

Remarks

For use in in-process DLLs only.

See Also

[IEnumDrSections Interface](#)
[IEnumDrSections Members](#)

SOLIDWORKS API Help

[Send comments on this topic.](#)

Reset Method (IEnumDrSections)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IEnumDrSections Interface](#) : Reset Method (IEnumDrSections)

Resets the sequence to the beginning of the section views enumeration.

.NET Syntax

Visual Basic (Declaration)

Sub Reset()

Visual Basic (Usage)



```
Dim instance As IEnumDrSections  
instance.Reset()
```

C#

```
void Reset()
```

C++/CLI

```
void Reset();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Visual Basic for Applications (VBA) Syntax

See [EnumDrSections::Reset](#).

Remarks

For use in in-process DLLs only.

See Also

[IEnumDrSections Interface](#)
[IEnumDrSections Members](#)

SOLIDWORKS API Help

[Send comments on this topic.](#)

Skip Method (IEnumDrSections)

[See Also](#)



Skips the specified number of section views in the section views enumeration.

.NET Syntax

Visual Basic (Declaration)

```
Sub Skip( _  
    ByVal Celt As System.Integer _  
)
```

Visual Basic (Usage)



```
Dim instance As IEnumDrSections  
Dim Celt As System.Integer  
  
instance.Skip(Celt)
```

C#

```
void Skip(  
    System.int Celt  
)
```

C++/CLI

```
void Skip(  
& System.int Celt  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Celt

Number of section views to skip

Visual Basic for Applications (VBA) Syntax

See [EnumDrSections::Skip](#).

Remarks

For use in in-process DLLs only.

See Also

[IEnumDrSections Interface](#)
[IEnumDrSections Members](#)

IEnumEdges (Type)

IEnumEdges Interface

[See Also](#) [Members](#)



[SolidWorks.Interop.sldworks Namespace](#) : IEnumEdges Interface

Allows access to an [edges](#) enumeration.

NOTE: Click the **Members** link, located near the top of the topic, to see this interface's methods and properties.

.NET Syntax

Visual Basic (Declaration)

```
Public Interface IEnumEdges
```

Visual Basic (Usage)

```
Dim instance As IEnumEdges
```

C#

```
public interface IEnumEdges
```

C++/CLI

```
public interface class IEnumEdges
```

Visual Basic for Applications (VBA) Syntax

See [EnumEdges](#).

Remarks

For use in in-process DLLs only.

Accessors

- [IEnumEdges::Clone](#)
- [IFace2::EnumEdges](#)
- [ILoop2::EnumEdges](#)
- [ISketchText::EnumEdges](#)
- [IVertex::EnumEdges](#)
- [IVertex::EnumEdgesOriented](#)

Access Diagram

[EnumEdges](#)

See Also

- [IEnumEdges Members](#)
- [SolidWorks.Interop.sldworks Namespace](#)

IEnumEdges Interface Members

[See Also](#) [Methods](#)



[SolidWorks.Interop.sldworks Namespace](#) : IEnumEdges Interface

The following tables list the members exposed by [IEnumEdges](#).

Public Methods

Name	Description
 Clone	Clones the edges enumeration.
 Next	Gets the next edge in the edges enumeration.
 Reset	Resets the sequence to the beginning of the edges enumeration.
 Skip	Skips the specified number edges in the edges enumeration.

[Top](#)

 See Also

[IEnumEdges Interface](#)
[SolidWorks.Interop.sldworks Namespace](#)

SOLIDWORKS API Help

[Send comments on this topic.](#)

IEnumEdges Interface Methods

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) : IEnumEdges Interface

For a list of all members of this type, see [IEnumEdges members](#).

 Public Methods

Name	Description
 Clone	Clones the edges enumeration.
 Next	Gets the next edge in the edges enumeration.
 Reset	Resets the sequence to the beginning of the edges enumeration.
 Skip	Skips the specified number edges in the edges enumeration.

[Top](#)

 See Also

[IEnumEdges Interface](#)
[SolidWorks.Interop.sldworks Namespace](#)

SOLIDWORKS API Help

[Send comments on this topic.](#)

Clone Method (IEnumEdges)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IEnumEdges Interface](#) : Clone Method (IEnumEdges)

Clones the edges enumeration.

 .NET Syntax

Visual Basic (Declaration)

```
Sub Clone( _  
    ByRef Ppenum As EnumEdges _  
)
```

Visual Basic (Usage)



```
Dim instance As IEnumEdges  
Dim Ppenum As EnumEdges  
  
instance.Clone(Ppenum)
```

C#

```
void Clone(  
    out EnumEdges Ppenum  
)
```

C++/CLI

```
void Clone(  
& [Out] EnumEdges^ Ppenum  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Ppenum
Pointer to the clones [edges enumeration](#)

Visual Basic for Applications (VBA) Syntax

See [EnumEdges::Clone](#).

Remarks

For use in in-process DLLs only.

See Also

[IEnumEdges Interface](#)
[IEnumEdges Members](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

Next Method (IEnumEdges)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IEnumEdges Interface](#) : Next Method (IEnumEdges)

Gets the next edge in the edges enumeration.

.NET Syntax

Visual Basic (Declaration)

```
Sub Next( _  
    ByVal Celt As System.Integer, _  
    ByRef Rgelt As Edge, _  
    ByRef PceltFetched As System.Integer _  
)
```

Visual Basic (Usage)



```
Dim instance As IEnumEdges  
Dim Celt As System.Integer  
Dim Rgelt As Edge  
Dim PceltFetched As System.Integer  
  
instance.Next(Celt, Rgelt, PceltFetched)
```

C#

```
void Next(  
    System.int Celt,  
    out Edge Rgelt,  
    out System.int PceltFetched  
)
```

C++/CLI

```
void Next(  
& System.int Celt,  
& [Out] Edge^ Rgelt,  
& [Out] System.int PceltFetched  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Celt
Number edges for the edges enumeration
Rgelt
Pointer to an array of edges of size Celt
PceltFetched
Pointer to the number of edges returned from the list; this value can be less than Celt if you ask for more edges than exist, or it can be NULL if no more edges exist.

 Visual Basic for Applications (VBA) Syntax

See [EnumEdges::Next](#).

 Remarks

For use in in-process DLLs only.

 See Also

[IEnumEdges Interface](#)
[IEnumEdges Members](#)

SOLIDWORKS API Help

[Send comments on this topic.](#)

Reset Method (IEnumEdges)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IEnumEdges Interface](#) : Reset Method (IEnumEdges)

Resets the sequence to the beginning of the edges enumeration.

 .NET Syntax

Visual Basic (Declaration)

Sub Reset()

Visual Basic (Usage)



```
Dim instance As IEnumEdges  
  
instance.Reset()
```

C#

```
void Reset()
```

C++/CLI

```
void Reset();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

 Visual Basic for Applications (VBA) Syntax

See [EnumEdges::Reset](#).

 Remarks

For use in in-process DLLs only.

 See Also

[IEnumEdges Interface](#)
[IEnumEdges Members](#)

SOLIDWORKS API Help

[Send comments on this topic.](#)

Skip Method (IEnumEdges)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IEnumEdges Interface](#) : Skip Method (IEnumEdges)

Skips the specified number edges in the edges enumeration.

.NET Syntax

Visual Basic (Declaration)

```
Sub Skip( _  
    ByVal Celt As System.Integer _  
)
```

Visual Basic (Usage)



```
Dim instance As IEnumEdges  
Dim Celt As System.Integer  
  
instance.Skip(Celt)
```

C#

```
void Skip(  
    System.int Celt  
)
```

C++/CLI

```
void Skip(  
&    System.int Celt  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Celt
Number of edges to skip

Visual Basic for Applications (VBA) Syntax

See [EnumEdges::Skip](#).

Remarks

For use in in-process DLLs only.

See Also

[IEnumEdges Interface](#)
[IEnumEdges Members](#)

IEnumFaces (Type)

IEnumFaces Interface

[See Also](#) [Members](#)



[SolidWorks.Interop.sldworks Namespace](#) : IEnumFaces Interface

Obsolete. Superseded by [IEnumFaces2](#).

NOTE: Click the **Members** link, located near the top of the topic, to see this interface's methods and properties.

.NET Syntax

Visual Basic (Declaration)

```
Public Interface IEnumFaces
```

Visual Basic (Usage)



```
Dim instance As IEnumFaces
```

C#

```
public interface IEnumFaces
```

C++/CLI

```
public interface class IEnumFaces
```

Visual Basic for Applications (VBA) Syntax

See [EnumFaces](#).

See Also

[IEnumFaces Members](#)
[SolidWorks.Interop.sldworks Namespace](#)

IEnumFaces Interface Members

[See Also](#) [Methods](#)



[SolidWorks.Interop.sldworks Namespace](#) : IEnumFaces Interface

The following tables list the members exposed by [IEnumFaces](#).

Public Methods

Name	Description
 Clone	Obsolete. Superseded by IEnumFaces2.Clone .
 Next	Obsolete. Superseded by IEnumFaces2.Next .
 Reset	Obsolete. Superseded by IEnumFaces2.Reset .
 Skip	Obsolete. Superseded by IEnumFaces2.Skip .

[Top](#)

See Also

[IEnumFaces Interface](#)
[SolidWorks.Interop.sldworks Namespace](#)

IEnumFaces Interface Methods

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) : IEnumFaces Interface

For a list of all members of this type, see [IEnumFaces members](#).

Public Methods	
Name	Description
 Clone	Obsolete. Superseded by IEnumFaces2.Clone .
 Next	Obsolete. Superseded by IEnumFaces2.Next .
 Reset	Obsolete. Superseded by IEnumFaces2.Reset .
 Skip	Obsolete. Superseded by IEnumFaces2.Skip .

[Top](#)

See Also

[IEnumFaces Interface](#)
[SolidWorks.Interop.sldworks Namespace](#)

Clone Method (IEnumFaces)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IEnumFaces Interface](#) : Clone Method (IEnumFaces)

Obsolete. Superseded by [IEnumFaces2.Clone](#).

.NET Syntax

Visual Basic (Declaration)

```
Sub Clone( _  
    ByRef Ppenum As EnumFaces _  
)
```

Visual Basic (Usage)



```
Dim instance As IEnumFaces  
Dim Ppenum As EnumFaces  
  
instance.Clone(Ppenum)
```

C#

```
void Clone(  
    out EnumFaces Ppenum  
)
```

C++/CLI

```
void Clone(  
& [Out] EnumFaces^ Ppenum  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Ppenum

Visual Basic for Applications (VBA) Syntax

See [EnumFaces.Clone](#).

See Also

[IEnumFaces Interface](#)
[IEnumFaces Members](#)

Next Method (IEnumFaces)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IEnumFaces Interface](#) : Next Method (IEnumFaces)

Obsolete. Superseded by [IEnumFaces2::Next](#).

.NET Syntax

Visual Basic (Declaration)

```
Sub Next( _  
    ByVal Celt As System.Integer, _  
    ByRef Rgelt As Face, _  
    ByRef PceltFetched As System.Integer _  
)
```

Visual Basic (Usage)



```
Dim instance As IEnumFaces  
Dim Celt As System.Integer  
Dim Rgelt As Face  
Dim PceltFetched As System.Integer  
  
instance.Next(Celt, Rgelt, PceltFetched)
```

C#

```
void Next(  
    System.int Celt,  
    out Face Rgelt,  
    out System.int PceltFetched  
)
```

C++/CLI

```
void Next(  
&    System.int Celt,  
&    [Out] Face^ Rgelt,  
&    [Out] System.int PceltFetched  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Celt

Rgelt

PceltFetched

Visual Basic for Applications (VBA) Syntax

See [EnumFaces::Next](#).

See Also

[IEnumFaces Interface](#)
[IEnumFaces Members](#)

Reset Method (IEnumFaces)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IEnumFaces Interface](#) : Reset Method (IEnumFaces)

Obsolete. Superseded by [IEnumFaces2::Reset](#).

.NET Syntax

Visual Basic (Declaration)

```
Sub Reset()
```

Visual Basic (Usage)



```
Dim instance As IEnumFaces  
  
instance.Reset()
```

C#

```
void Reset()
```

C++/CLI

```
void Reset();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Visual Basic for Applications (VBA) Syntax

See [EnumFaces::Reset](#).

See Also

[IEnumFaces Interface](#)
[IEnumFaces Members](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

Skip Method (IEnumFaces)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IEnumFaces Interface](#) : Skip Method (IEnumFaces)

Obsolete. Superseded by [IEnumFaces2::Skip](#).

.NET Syntax

Visual Basic (Declaration)

```
Sub Skip(  
    ByVal Celt As System.Integer  
)
```

Visual Basic (Usage)



```
Dim instance As IEnumFaces  
Dim Celt As System.Integer  
  
instance.Skip(Celt)
```

C#

```
void Skip(  
    System.int Celt  
)
```

C++/CLI

```
void Skip(  
& System.int Celt  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Visual Basic for Applications (VBA) Syntax

See [EnumFaces::Skip](#).

See Also

[IEnumFaces Interface](#)
[IEnumFaces Members](#)