

SOLIDWORKS API (.NET VBA C#) — Reference (97/337): IEnumFaces2-IEnumSketchSegments

SOLIDWORKS API Documentation (converted from CHM)

IEnumFaces2 (Type)

IEnumFaces2 Interface

[See Also](#) [Members](#)



[SolidWorks.Interop.sldworks Namespace](#) : IEnumFaces2 Interface

Allows access to a [faces](#) enumeration.

NOTE: Click the **Members** link, located near the top of the topic, to see this interface's methods and properties.

.NET Syntax

Visual Basic (Declaration)

```
Public Interface IEnumFaces2
```

Visual Basic (Usage)

```
Dim instance As IEnumFaces2
```

C#

```
public interface IEnumFaces2
```

C++/CLI

```
public interface class IEnumFaces2
```

Visual Basic for Applications (VBA) Syntax

See [EnumFaces2](#).

Remarks

For use in in-process DLLs only.

Accessors

[IBody2::EnumFaces](#)

[IEnumFaces2::Clone](#)

Access Diagram

[EnumFaces2](#)

See Also

[IEnumFaces2 Members](#)
[SolidWorks.Interop.sldworks Namespace](#)

IEnumFaces2 Interface Members

[See Also](#) [Methods](#)



[SolidWorks.Interop.sldworks Namespace](#) : IEnumFaces2 Interface

The following tables list the members exposed by [IEnumFaces2](#).

Public Methods

Name	Description
Clone	Clones the faces enumeration.
Next	Gets the next face in the faces enumeration.

 Reset	Resets the sequence to the beginning of the faces enumeration.
 Skip	Skips the specified number of faces in the faces enumeration.

[Top](#)

 See Also

[IEnumFaces2 Interface](#)
[SolidWorks.Interop.sldworks Namespace](#)

SOLIDWORKS API Help

[Send comments on this topic.](#)

IEnumFaces2 Interface Methods

[See Also](#)


SolidWorks.Interop.sldworks Namespace : IEnumFaces2 Interface

For a list of all members of this type, see [IEnumFaces2 members](#).

 Public Methods

Name	Description
 Clone	Clones the faces enumeration.
 Next	Gets the next face in the faces enumeration.
 Reset	Resets the sequence to the beginning of the faces enumeration.
 Skip	Skips the specified number of faces in the faces enumeration.

[Top](#)

 See Also

[IEnumFaces2 Interface](#)
[SolidWorks.Interop.sldworks Namespace](#)

SOLIDWORKS API Help

[Send comments on this topic.](#)

Clone Method (IEnumFaces2)

[See Also](#)

 
SolidWorks.Interop.sldworks Namespace > IEnumFaces2 Interface : Clone Method (IEnumFaces2)

Clones the faces enumeration.

 I.NET Syntax

Visual Basic (Declaration)

```
Sub Clone( _  
    ByRef Ppenum As EnumFaces2 _  
)
```

Visual Basic (Usage)



```
Dim instance As IEnumFaces2  
Dim Ppenum As EnumFaces2  
  
instance.Clone(Ppenum)
```

C#

```
void Clone(  
    out EnumFaces2 Ppenum  
)
```

C++/CLI

```
void Clone(  
& [Out] EnumFaces2^ Ppenum  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Ppenum

Pointer to the cloned [faces enumeration](#)

Visual Basic for Applications (VBA) Syntax

See [EnumFaces2::Clone](#).

Remarks

For use in in-process DLLs only.

See Also

[IEnumFaces2 Interface](#)
[IEnumFaces2 Members](#)

Availability

SOLIDWORKS 2001Plus FCS, Revision Number 10.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

Next Method (IEnumFaces2)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IEnumFaces2 Interface](#) : Next Method (IEnumFaces2)

Gets the next face in the faces enumeration.

.NET Syntax

Visual Basic (Declaration)

```
Sub Next( _  
    ByVal Celt As System.Integer, _  
    ByRef Rgelt As Face2, _  
    ByRef PceltFetched As System.Integer _  
)
```

Visual Basic (Usage)



```
Dim instance As IEnumFaces2  
Dim Celt As System.Integer  
Dim Rgelt As Face2  
Dim PceltFetched As System.Integer  
  
instance.Next(Celt, Rgelt, PceltFetched)
```

C#

```
void Next(  
    System.int Celt,  
    out Face2 Rgelt,  
    out System.int PceltFetched  
)
```

C++/CLI

```
void Next(  
& System.int Celt,  
& [Out] Face2^ Rgelt,  
& [Out] System.int PceltFetched  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Celt
Number of faces for the faces enumeration
Rgelt
Pointer to an array of [faces](#) of size Celt
PceltFetched
Pointer to the number of faces returned from the list; this value can be less than Celt if you asked for more faces than exist, or it can be NULL if no more faces exist

Visual Basic for Applications (VBA) Syntax

See [EnumFaces2::Next](#).

Remarks

For use in in-process DLLs only.

See Also

[IEnumFaces2 Interface](#)
[IEnumFaces2 Members](#)

Availability

SOLIDWORKS 2001Plus FCS, Revision Number 10.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

Reset Method (IEnumFaces2)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IEnumFaces2 Interface](#) : Reset Method (IEnumFaces2)

Resets the sequence to the beginning of the faces enumeration.

.NET Syntax

Visual Basic (Declaration)

```
Sub Reset()
```

Visual Basic (Usage)



```
Dim instance As IEnumFaces2  
  
instance.Reset()
```

C#

```
void Reset()
```

C++/CLI

```
void Reset();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Visual Basic for Applications (VBA) Syntax

See [EnumFaces2::Reset](#).

Remarks

For use in in-process DLLs only.

See Also

[IEnumFaces2 Interface](#)
[IEnumFaces2 Members](#)

Availability

SOLIDWORKS 2001Plus FCS, Revision Number 10.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

Skip Method (IEnumFaces2)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IEnumFaces2 Interface](#) : Skip Method (IEnumFaces2)

Skips the specified number of faces in the faces enumeration.

.NET Syntax

Visual Basic (Declaration)

```
Sub Skip( _  
    ByVal Celt As System.Integer _  
)
```

Visual Basic (Usage)



```
Dim instance As IEnumFaces2  
Dim Celt As System.Integer  
  
instance.Skip(Celt)
```

C#

```
void Skip(  
    System.int Celt  
)
```

C++/CLI

```
void Skip(  
& System.int Celt  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Celt
Number of faces to skip

Visual Basic for Applications (VBA) Syntax

See [EnumFaces2::Skip](#).

Remarks

For use in in-process DLLs only.

See Also

[IEnumFaces2 Interface](#)
[IEnumFaces2 Members](#)

Availability

SOLIDWORKS 2001Plus FCS, Revision Number 10.0

IEnumLoops (Type)

IEnumLoops Interface

[See Also](#) [Members](#)



[SolidWorks.Interop.sldworks Namespace](#) : IEnumLoops Interface

Obsolete. Superseded by [IEnumLoops2](#).

NOTE: Click the **Members** link, located near the top of the topic, to see this interface's methods and properties.

.NET Syntax

Visual Basic (Declaration)

```
Public Interface IEnumLoops
```

Visual Basic (Usage)



```
Dim instance As IEnumLoops
```

C#

```
public interface IEnumLoops
```

C++/CLI

```
public interface class IEnumLoops
```

Visual Basic for Applications (VBA) Syntax

See [EnumLoops](#).

See Also

[IEnumLoops Members](#)
[SolidWorks.Interop.sldworks Namespace](#)

IEnumLoops Interface Methods

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) : IEnumLoops Interface

For a list of all members of this type, see [IEnumLoops members](#).

Public Methods

Name	Description
 Clone	Obsolete. Superseded by IEnumLoops2.Clone .
 Next	Obsolete. Superseded by IEnumLoops2.Next .
 Reset	Obsolete. Superseded by IEnumLoops2.Reset .
 Skip	Obsolete. Superseded by IEnumLoops2.Skip .

[Top](#)

See Also

[IEnumLoops Interface](#)
[SolidWorks.Interop.sldworks Namespace](#)

IEnumLoops Interface Members

[See Also](#) [Methods](#)



[SolidWorks.Interop.sldworks Namespace](#) : IEnumLoops Interface

The following tables list the members exposed by [IEnumLoops](#).

Public Methods

Name	Description
 Clone	Obsolete. Superseded by IEnumLoops2.Clone .
 Next	Obsolete. Superseded by IEnumLoops2.Next .
 Reset	Obsolete. Superseded by IEnumLoops2.Reset .
 Skip	Obsolete. Superseded by IEnumLoops2.Skip .

[Top](#)

See Also

[IEnumLoops Interface](#)
[SolidWorks.Interop.sldworks Namespace](#)

Clone Method (IEnumLoops)

[See Also](#)

 

[SolidWorks.Interop.sldworks Namespace](#) > [IEnumLoops Interface](#) : Clone Method (IEnumLoops)

Obsolete. Superseded by [IEnumLoops2.Clone](#).

.NET Syntax

Visual Basic (Declaration)

Sub Clone(_
 ByRef [Ppenum](#) As EnumLoops _
)

Visual Basic (Usage)

Dim instance As [IEnumLoops](#)
Dim Ppenum As EnumLoops

instance.Clone(Ppenum)

C#

void Clone(
 out EnumLoops [Ppenum](#)
)

C++/CLI

void Clone(
& [Out] EnumLoops^ [Ppenum](#)
)

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Ppenum

Visual Basic for Applications (VBA) Syntax

See [EnumLoops.Clone](#).

See Also

[IEnumLoops Interface](#)
[IEnumLoops Members](#)

Next Method (IEnumLoops)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IEnumLoops Interface](#) : Next Method (IEnumLoops)

Obsolete. Superseded by [IEnumLoops2::Next](#).

.NET Syntax

Visual Basic (Declaration)

```
Sub Next( _  
    ByVal Celt As System.Integer, _  
    ByRef Rgelt As Loop, _  
    ByRef PceltFetched As System.Integer _  
)
```

Visual Basic (Usage)



```
Dim instance As IEnumLoops  
Dim Celt As System.Integer  
Dim Rgelt As Loop  
Dim PceltFetched As System.Integer  
  
instance.Next(Celt, Rgelt, PceltFetched)
```

C#

```
void Next(  
    System.int Celt,  
    out Loop Rgelt,  
    out System.int PceltFetched  
)
```

C++/CLI

```
void Next(  
& System.int Celt,  
& [Out] Loop^ Rgelt,  
& [Out] System.int PceltFetched  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Celt

Rgelt

PceltFetched

Visual Basic for Applications (VBA) Syntax

See [EnumLoops::Next](#).

See Also

[IEnumLoops Interface](#)
[IEnumLoops Members](#)

Reset Method (IEnumLoops)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IEnumLoops Interface](#) : Reset Method (IEnumLoops)

Obsolete. Superseded by [IEnumLoops2::Reset](#).

.NET Syntax

Visual Basic (Declaration)

```
Sub Reset()
```

Visual Basic (Usage)



```
Dim instance As IEnumLoops  
  
instance.Reset()
```

C#

```
void Reset()
```

C++/CLI

```
void Reset();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Visual Basic for Applications (VBA) Syntax

See [EnumLoops::Reset](#).

See Also

[IEnumLoops Interface](#)
[IEnumLoops Members](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

Skip Method (IEnumLoops)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IEnumLoops Interface](#) : Skip Method (IEnumLoops)

Obsolete. Superseded by [IEnumLoops2::Skip](#).

.NET Syntax

Visual Basic (Declaration)

```
Sub Skip(  
    ByVal Celt As System.Integer  
)
```

Visual Basic (Usage)



```
Dim instance As IEnumLoops  
Dim Celt As System.Integer  
  
instance.Skip(Celt)
```

C#

```
void Skip(  
    System.int Celt  
)
```

C++/CLI

```
void Skip(  
& System.int Celt  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Visual Basic for Applications (VBA) Syntax

See [EnumLoops::Skip](#).

See Also

[IEnumLoops Interface](#)
[IEnumLoops Members](#)

IEnumLoops2 (Type)

IEnumLoops2 Interface

[See Also](#) [Members](#)



[SolidWorks.Interop.sldworks Namespace](#) : IEnumLoops2 Interface

Allows access to a [loops](#) enumeration.
NOTE: Click the **Members** link, located near the top of the topic, to see this interface's methods and properties.

.NET Syntax

Visual Basic (Declaration)

```
Public Interface IEnumLoops2
```

Visual Basic (Usage)



```
Dim instance As IEnumLoops2
```

C#

```
public interface IEnumLoops2
```

C++/CLI

```
public interface class IEnumLoops2
```

Visual Basic for Applications (VBA) Syntax

See [EnumLoops2](#).

Remarks

For use in in-process DLLs only.

Accessors

[IEnumLoops2::Clone](#)

[IFace2::EnumLoops](#)

Access Diagram

[EnumLoops2](#)

See Also

[IEnumLoops2 Members](#)
[SolidWorks.Interop.sldworks Namespace](#)

IEnumLoops2 Interface Members

[See Also](#) [Methods](#)



[SolidWorks.Interop.sldworks Namespace](#) : IEnumLoops2 Interface

The following tables list the members exposed by [IEnumLoops2](#).

Public Methods

Name	Description
 Clone	Clones the loops enumeration.
 Next	Gets the next loop in the loops enumeration.

 Reset	Resets the sequence to the beginning of the loops enumeration.
 Skip	Skips the specified number of loops in the loops enumeration.

[Top](#)

 See Also

[IEnumerator2 Interface](#)
[SolidWorks.Interop.sldworks Namespace](#)

SOLIDWORKS API Help

[Send comments on this topic.](#)

IEnumerator2 Interface Methods

[See Also](#)


SolidWorks.Interop.sldworks Namespace : IEnumerator2 Interface

For a list of all members of this type, see [IEnumerator2 members](#).

 Public Methods

Name	Description
 Clone	Clones the loops enumeration.
 Next	Gets the next loop in the loops enumeration.
 Reset	Resets the sequence to the beginning of the loops enumeration.
 Skip	Skips the specified number of loops in the loops enumeration.

[Top](#)

 See Also

[IEnumerator2 Interface](#)
[SolidWorks.Interop.sldworks Namespace](#)

SOLIDWORKS API Help

[Send comments on this topic.](#)

Clone Method (IEnumerator2)

[See Also](#)



SolidWorks.Interop.sldworks Namespace > IEnumerator2 Interface : Clone Method (IEnumerator2)
Clones the loops enumeration.

 Visual Basic Syntax

Visual Basic (Declaration)

```
Sub Clone( _  
    ByRef Ppenum As EnumLoops2 _  
)
```

Visual Basic (Usage)

```
Dim instance As IEnumerator2  
Dim Ppenum As EnumLoops2  
  
instance.Clone(Ppenum)
```

C#

```
void Clone(  
    out EnumLoops2 Ppenum  
)
```

C++/CLI

```
void Clone(  
& [Out] EnumLoops2^ Ppenum  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Ppenum

Pointer to the clones [loops enumeration](#)

Visual Basic for Applications (VBA) Syntax

See [EnumLoops2::Clone](#).

Remarks

For use in in-process DLLs only.

See Also

[IEnumLoops2 Interface](#)

[IEnumLoops2 Members](#)

Availability

SOLIDWORKS 2001Plus FCS, Revision Number 10.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

Next Method (IEnumLoops2)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IEnumLoops2 Interface](#) : Next Method (IEnumLoops2)

Gets the next loop in the loops enumeration.

.NET Syntax

Visual Basic (Declaration)

```
Sub Next( _  
    ByVal Celt As System.Integer, _  
    ByRef Rgelt As Loop2, _  
    ByRef PceltFetched As System.Integer _  
)
```

Visual Basic (Usage)



```
Dim instance As IEnumLoops2  
Dim Celt As System.Integer  
Dim Rgelt As Loop2  
Dim PceltFetched As System.Integer  
  
instance.Next(Celt, Rgelt, PceltFetched)
```

C#

```
void Next(  
    System.int Celt,  
    out Loop2 Rgelt,  
    out System.int PceltFetched  
)
```

C++/CLI

```
void Next(  
& System.int Celt,  
& [Out] Loop2^ Rgelt,  
& [Out] System.int PceltFetched  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Celt
Number of loops for the loops enumeration
Rgelt
Pointer to an array of [loops](#) of size Celt
PceltFetched
Pointer to the number of loops returned from the list; this value can be less than celt if you ask for more loops than exist, or it can be NULL if no more loops exist

Visual Basic for Applications (VBA) Syntax

See [EnumLoops2::Next](#).

Remarks

For use in in-process DLLs only.

See Also

[IEnumLoops2 Interface](#)
[IEnumLoops2 Members](#)

Availability

SOLIDWORKS 2001Plus FCS, Revision Number 10.0

SOLIDWORKS API Help

[Send comments](#) on this topic.

Reset Method (IEnumLoops2)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IEnumLoops2 Interface](#) : Reset Method (IEnumLoops2)

Resets the sequence to the beginning of the loops enumeration.

.NET Syntax

Visual Basic (Declaration)

```
Sub Reset()
```

Visual Basic (Usage)



```
Dim instance As IEnumLoops2  
instance.Reset()
```

C#

```
void Reset()
```

C++/CLI

```
void Reset();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Visual Basic for Applications (VBA) Syntax

See [EnumLoops2::Reset](#).

Remarks

For use in in-process DLLs only.

See Also

[IEnumLoops2 Interface](#)
[IEnumLoops2 Members](#)

Availability

SOLIDWORKS 2001Plus FCS, Revision Number 10.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

Skip Method (IEnumLoops2)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IEnumLoops2 Interface](#) : Skip Method (IEnumLoops2)

Skips the specified number of loops in the loops enumeration.

.NET Syntax

Visual Basic (Declaration)

```
Sub Skip( _  
    ByVal Celt As System.Integer _  
)
```

Visual Basic (Usage)



```
Dim instance As IEnumLoops2  
Dim Celt As System.Integer  
  
instance.Skip(Celt)
```

C#

```
void Skip(  
    System.int Celt  
)
```

C++/CLI

```
void Skip(  
& System.int Celt  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Celt
Number of loops

Visual Basic for Applications (VBA) Syntax

See [EnumLoops2::Skip](#).

Remarks

For use in in-process DLLs only.

See Also

[IEnumLoops2 Interface](#)
[IEnumLoops2 Members](#)

Availability

SOLIDWORKS 2001Plus FCS, Revision Number 10.0

IEnumModelViews (Type)

IEnumModelViews Interface

[See Also](#) [Members](#)



[SolidWorks.Interop.sldworks Namespace](#) : IEnumModelViews Interface

Allows access to a [model views](#) enumeration.

NOTE: Click the **Members** link, located near the top of the topic, to see this interface's methods and properties.

.NET Syntax

Visual Basic (Declaration)

Public Interface IEnumModelViews

Visual Basic (Usage)

Dim instance As [IEnumModelViews](#)

C#

public interface IEnumModelViews

C++/CLI

public interface class IEnumModelViews

Visual Basic for Applications (VBA) Syntax

See [EnumModelViews](#).

Remarks

For use in in-process DLLs only.

Accessors

- [IEnumModelViews::Clone](#)
- [IModelDoc2::EnumModelViews](#)

Access Diagram

[EnumModelViews](#)

See Also

- [IEnumModelViews Members](#)
- [SolidWorks.Interop.sldworks Namespace](#)

IEnumModelViews Interface Members

[See Also](#) [Methods](#)



[SolidWorks.Interop.sldworks Namespace](#) : IEnumModelViews Interface

The following tables list the members exposed by [IEnumModelViews](#).

Public Methods

Name	Description
Clone	Clones the model views enumeration.
Next	Gets the next model view in the model views enumeration.

 Reset	Resets the sequence to the beginning of the model views enumeration.
 Skip	Skips the specified number of model views in the model views enumeration.

[Top](#)

 See Also

[IEnumModelViews Interface](#)
[SolidWorks.Interop.sldworks Namespace](#)

SOLIDWORKS API Help

[Send comments on this topic.](#)

IEnumModelViews Interface Methods

[See Also](#)

 [SolidWorks.Interop.sldworks Namespace](#) : IEnumModelViews Interface

For a list of all members of this type, see [IEnumModelViews members](#).

 Public Methods

Name	Description
 Clone	Clones the model views enumeration.
 Next	Gets the next model view in the model views enumeration.
 Reset	Resets the sequence to the beginning of the model views enumeration.
 Skip	Skips the specified number of model views in the model views enumeration.

[Top](#)

 See Also

[IEnumModelViews Interface](#)
[SolidWorks.Interop.sldworks Namespace](#)

SOLIDWORKS API Help

[Send comments on this topic.](#)

Clone Method (IEnumModelViews)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IEnumModelViews Interface](#) : Clone Method (IEnumModelViews)

Clones the model views enumeration.

 I.NET Syntax

Visual Basic (Declaration)

```
Sub Clone( _  
    ByRef Ppenum As EnumModelViews _  
)
```

Visual Basic (Usage)



```
Dim instance As IEnumModelViews  
Dim Ppenum As EnumModelViews  
  
instance.Clone(Ppenum)
```

C#

```
void Clone(  
    out EnumModelViews Ppenum  
)
```

C++/CLI

```
void Clone(  
& [Out] EnumModelViews^ Ppenum  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Ppenum

Pointer to the model views enumeration

Visual Basic for Applications (VBA) Syntax

See [EnumModelViews::Clone](#).

Remarks

For use in in-process DLLs only.

See Also

[IEnumModelViews Interface](#)

[IEnumModelViews Members](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

Next Method (IEnumModelViews)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IEnumModelViews Interface](#) : Next Method (IEnumModelViews)

Gets the next model view in the model views enumeration.

.NET Syntax

Visual Basic (Declaration)

```
Sub Next( _  
    ByVal Celt As System.Integer, _  
    ByRef Rgelt As ModelView, _  
    ByRef PceltFetched As System.Integer _  
)
```

Visual Basic (Usage)



```
Dim instance As IEnumModelViews  
Dim Celt As System.Integer  
Dim Rgelt As ModelView  
Dim PceltFetched As System.Integer  
  
instance.Next(Celt, Rgelt, PceltFetched)
```

C#

```
void Next(  
    System.int Celt,  
    out ModelView Rgelt,  
    out System.int PceltFetched  
)
```

C++/CLI

```
void Next(  
& System.int Celt,  
& [Out] ModelView^ Rgelt,  
& [Out] System.int PceltFetched  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Celt

Number of model views for the model views enumeration

Rgelt

Pointer to an array of [model views](#) of size Celt

PceltFetched

Pointer to the number of model views returned from the list; this value can be less than celt if you ask for more model views than exist, or it can be NULL if no more model views exist

Visual Basic for Applications (VBA) Syntax

See [EnumModelViews::Next](#).

Remarks

For use in in-process DLLs only.

See Also

[IEnumModelViews Interface](#)
[IEnumModelViews Members](#)

SOLIDWORKS API Help

[Send comments on this topic.](#)

Reset Method (IEnumModelViews)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IEnumModelViews Interface](#) : Reset Method (IEnumModelViews)

Resets the sequence to the beginning of the model views enumeration.

.NET Syntax

Visual Basic (Declaration)

```
Sub Reset()
```

Visual Basic (Usage)



```
Dim instance As IEnumModelViews  
instance.Reset()
```

C#

```
void Reset()
```

C++/CLI

```
void Reset();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Visual Basic for Applications (VBA) Syntax

See [EnumModelViews::Reset](#).

Remarks

For use in in-process DLLs only.

See Also

[IEnumModelViews Interface](#)
[IEnumModelViews Members](#)

SOLIDWORKS API Help

[Send comments on this topic.](#)

Skip Method (IEnumModelViews)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IEnumModelViews Interface](#) : Skip Method (IEnumModelViews)

Skips the specified number of model views in the model views enumeration.

.NET Syntax

Visual Basic (Declaration)

```
Sub Skip( _  
    ByVal Celt As System.Integer _  
)
```

Visual Basic (Usage)



```
Dim instance As IEnumerableModelViews  
Dim Celt As System.Integer  
  
instance.Skip(Celt)
```

C#

```
void Skip(  
    System.int Celt  
)
```

C++/CLI

```
void Skip(  
&    System.int Celt  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Celt
Number of model views to skip

Visual Basic for Applications (VBA) Syntax

See [EnumModelViews::Skip](#).

Remarks

For use in in-process DLLs only.

See Also

[IEnumerableModelViews Interface](#)
[IEnumerableModelViews Members](#)

IEnumSketchHatches (Type)

IEnumSketchHatches Interface

[See Also](#) [Members](#)



[SolidWorks.Interop.sldworks Namespace](#) : IEnumSketchHatches Interface

Allows access to a [sketch hatches](#) enumeration.

NOTE: Click the **Members** link, located near the top of the topic, to see this interface's methods and properties.

.NET Syntax

Visual Basic (Declaration)

Public Interface IEnumSketchHatches

Visual Basic (Usage)

Dim instance As [IEnumSketchHatches](#)

C#

public interface IEnumSketchHatches

C++/CLI

public interface class IEnumSketchHatches

Visual Basic for Applications (VBA) Syntax

See [EnumSketchHatches](#).

Remarks

For use in in-process DLLs only.

Accessors

[IEnumSketchHatches::Clone](#)

[ISketch::IEnumSketchHatches](#)

Access Diagram

[EnumSketchHatches](#)

See Also

[IEnumSketchHatches Members](#)
[SolidWorks.Interop.sldworks Namespace](#)

IEnumSketchHatches Interface Methods

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) : IEnumSketchHatches Interface

For a list of all members of this type, see [IEnumSketchHatches members](#).

Public Methods

Name	Description
Clone	Clones the sketch hatches enumeration.
Next	Gets the next sketch hatch in the sketch hatch enumeration.

 Reset	Resets the sequence to the beginning of the sketch hatches enumeration.
 Skip	Skips the specified number of sketch hatches in the sketch hatches enumeration.

[Top](#)

 See Also

[IEnumSketchHatches Interface](#)
[SolidWorks.Interop.sldworks Namespace](#)

SOLIDWORKS API Help

[Send comments on this topic.](#)

IEnumSketchHatches Interface Members

[See Also](#) [Methods](#)

	SolidWorks.Interop.sldworks Namespace : IEnumSketchHatches Interface
---	--

The following tables list the members exposed by [IEnumSketchHatches](#).

 Public Methods

Name	Description
 Clone	Clones the sketch hatches enumeration.
 Next	Gets the next sketch hatch in the sketch hatch enumeration.
 Reset	Resets the sequence to the beginning of the sketch hatches enumeration.
 Skip	Skips the specified number of sketch hatches in the sketch hatches enumeration.

[Top](#)

 See Also

[IEnumSketchHatches Interface](#)
[SolidWorks.Interop.sldworks Namespace](#)

SOLIDWORKS API Help

[Send comments on this topic.](#)

Clone Method (IEnumSketchHatches)

[See Also](#)

	
SolidWorks.Interop.sldworks Namespace > IEnumSketchHatches Interface : Clone Method (IEnumSketchHatches)	
Clones the sketch hatches enumeration.	

 I.NET Syntax

Visual Basic (Declaration)

```
Sub Clone( _  
    ByRef Ppenum As EnumSketchHatches _  
)
```

Visual Basic (Usage)



```
Dim instance As IEnumSketchHatches  
Dim Ppenum As EnumSketchHatches  
  
instance.Clone(Ppenum)
```

C#

```
void Clone(  
    out EnumSketchHatches Ppenum  
)
```

C++/CLI

```
void Clone(  
& [Out] EnumSketchHatches^ Ppenum  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Ppenum

Pointer to the cloned sketch hatches enumeration

Visual Basic for Applications (VBA) Syntax

See [EnumSketchHatches::Clone](#).

Remarks

For use in in-process DLLs only.

See Also

[IEnumSketchHatches Interface](#)
[IEnumSketchHatches Members](#)

Availability

SOLIDWORKS 2000 FCS, Revision Number 8.0

SOLIDWORKS API Help

[Send comments on this topic](#).

Next Method (IEnumSketchHatches)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IEnumSketchHatches Interface](#) : Next Method (IEnumSketchHatches)

Gets the next sketch hatch in the sketch hatch enumeration.

.NET Syntax

Visual Basic (Declaration)

```
Sub Next( _  
    ByVal Celt As System.Integer, _  
    ByRef Rgelt As SketchHatch, _  
    ByRef PceltFetched As System.Integer _  
)
```

Visual Basic (Usage)



```
Dim instance As IEnumSketchHatches  
Dim Celt As System.Integer  
Dim Rgelt As SketchHatch  
Dim PceltFetched As System.Integer  
  
instance.Next(Celt, Rgelt, PceltFetched)
```

C#

```
void Next(  
    System.int Celt,  
    out SketchHatch Rgelt,  
    out System.int PceltFetched  
)
```

C++/CLI

```
void Next(  
& System.int Celt,  
& [Out] SketchHatch^ Rgelt,  
& [Out] System.int PceltFetched  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Celt

Number of sketch hatches for this sketch hatch enumeration

Rgelt

Pointer to an array of [sketch hatches](#) of size *Celt*

PceltFetched

Pointer to the number of sketch hatches returned from the list; this value can be less than *celt* if you ask for more SketchHatch objects than exist or it can be NULL if no more SketchHatch objects exist

Visual Basic for Applications (VBA) Syntax

See [EnumSketchHatches::Next](#).

Remarks

For use in in-process DLLs only.

See Also

[IEnumSketchHatches Interface](#)

[IEnumSketchHatches Members](#)

Availability

SOLIDWORKS 2000 FCS, Revision Number 8.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

Reset Method (IEnumSketchHatches)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IEnumSketchHatches Interface](#) : Reset Method (IEnumSketchHatches)

Resets the sequence to the beginning of the sketch hatches enumeration.

.NET Syntax

Visual Basic (Declaration)

```
Sub Reset()
```

Visual Basic (Usage)



```
Dim instance As IEnumSketchHatches
```

```
instance.Reset()
```

C#

```
void Reset()
```

C++/CLI

```
void Reset();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Visual Basic for Applications (VBA) Syntax

See [EnumSketchHatches::Reset](#).

Remarks

For use in in-process DLLs only.

See Also

[IEnumSketchHatches Interface](#)

[IEnumSketchHatches Members](#)

Availability

SOLIDWORKS 2000 FCS, Revision Number 8.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

Skip Method (IEnumSketchHatches)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IEnumSketchHatches Interface](#) : Skip Method (IEnumSketchHatches)

Skips the specified number of sketch hatches in the sketch hatches enumeration.

.NET Syntax

Visual Basic (Declaration)

```
Sub Skip( _  
    ByVal Celt As System.Integer _  
)
```

Visual Basic (Usage)



```
Dim instance As IEnumSketchHatches  
Dim Celt As System.Integer  
  
instance.Skip(Celt)
```

C#

```
void Skip(  
    System.int Celt  
)
```

C++/CLI

```
void Skip(  
& System.int Celt  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Celt
Number of sketch hatches to skip

Visual Basic for Applications (VBA) Syntax

See [EnumSketchHatches::Skip](#).

Remarks

For use in in-process DLLs only.

See Also

[IEnumSketchHatches Interface](#)
[IEnumSketchHatches Members](#)

Availability

SOLIDWORKS 2000 FCS, Revision Number 8.0

IEnumSketchPoints (Type)

IEnumSketchPoints Interface

[See Also](#) [Members](#)



[SolidWorks.Interop.sldworks Namespace](#) : IEnumSketchPoints Interface

Allows access to a [sketch points](#) enumeration.

NOTE: Click the **Members** link, located near the top of the topic, to see this interface's methods and properties.

.NET Syntax

Visual Basic (Declaration)

```
Public Interface IEnumSketchPoints
```

Visual Basic (Usage)

```
Dim instance As IEnumSketchPoints
```

C#

```
public interface IEnumSketchPoints
```

C++/CLI

```
public interface class IEnumSketchPoints
```

Visual Basic for Applications (VBA) Syntax

See [EnumSketchPoints](#).

Remarks

For use in in-process DLLs only.

Accessors

[IEnumSketchPoints::Clone](#)

[ISketch::IEnumSketchPoints](#)

[ISketchSpline::IEnumPoints](#)

Access Diagram

[EnumSketchPoints](#)

See Also

[IEnumSketchPoints Members](#)
[SolidWorks.Interop.sldworks Namespace](#)

IEnumSketchPoints Interface Methods

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) : IEnumSketchPoints Interface

For a list of all members of this type, see [IEnumSketchPoints members](#).

Public Methods

Name	Description
Clone	Clones the sketch points enumeration.

 Next	Gets the next sketch point in the sketch points enumeration.
 Reset	Resets the sequence to the beginning of the sketch points enumeration.
 Skip	Skips the specified number of sketch points in the sketch points enumeration.

[Top](#)

 See Also

[IEnumeratorSketchPoints Interface](#)
[SolidWorks.Interop.sldworks Namespace](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

IEnumSketchPoints Interface Members

[See Also](#) [Methods](#)



[SolidWorks.Interop.sldworks Namespace](#) : IEnumSketchPoints Interface

The following tables list the members exposed by [IEnumeratorSketchPoints](#).

 Public Methods

Name	Description
 Clone	Clones the sketch points enumeration.
 Next	Gets the next sketch point in the sketch points enumeration.
 Reset	Resets the sequence to the beginning of the sketch points enumeration.
 Skip	Skips the specified number of sketch points in the sketch points enumeration.

[Top](#)

 See Also

[IEnumeratorSketchPoints Interface](#)
[SolidWorks.Interop.sldworks Namespace](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

Clone Method (IEnumeratorSketchPoints)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IEnumeratorSketchPoints Interface](#) : Clone Method (IEnumeratorSketchPoints)

Clones the sketch points enumeration.

 Visual Basic Syntax

Visual Basic (Declaration)

```
Sub Clone( _  
    ByRef Ppenum As EnumSketchPoints _  
)
```

Visual Basic (Usage)

```
Dim instance As IEnumeratorSketchPoints  
Dim Ppenum As EnumSketchPoints  
  
instance.Clone(Ppenum)
```

C#

```
void Clone(  
    out EnumSketchPoints Ppenum  
)
```

C++/CLI

```
void Clone(  
& [Out] EnumSketchPoints^ Ppenum
```

)

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Ppenum

Pointer to the cloned [sketch points enumeration](#)

Visual Basic for Applications (VBA) Syntax

See [EnumSketchPoints::Clone](#).

Remarks

For use in in-process DLLs only.

See Also

[IEnumSketchPoints Interface](#)

[IEnumSketchPoints Members](#)

Availability

SOLIDWORKS 99, datecode 1999207

SOLIDWORKS API Help

[Send comments on this topic.](#)

Next Method (IEnumSketchPoints)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IEnumSketchPoints Interface](#) : Next Method (IEnumSketchPoints)

Gets the next sketch point in the sketch points enumeration.

.NET Syntax

Visual Basic (Declaration)

```
Sub Next( _  
    ByVal Celt As System.Integer, _  
    ByRef Rgelt As SketchPoint, _  
    ByRef PceltFetched As System.Integer _  
)
```

Visual Basic (Usage)



```
Dim instance As IEnumSketchPoints  
Dim Celt As System.Integer  
Dim Rgelt As SketchPoint  
Dim PceltFetched As System.Integer  
  
instance.Next(Celt, Rgelt, PceltFetched)
```

C#

```
void Next(  
    System.int Celt,  
    out SketchPoint Rgelt,  
    out System.int PceltFetched  
)
```

C++/CLI

```
void Next(  
& System.int Celt,  
& [Out] SketchPoint^ Rgelt,  
& [Out] System.int PceltFetched  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Celt

Number of sketch points for the sketch points enumeration

Rgelt

Pointer to an array of [sketch points](#) of size Celt

PceltFetched

Pointer to the number of sketch points returned from the list; this value can be less than celt if you ask for more sketch points than exist, or it can be NULL if no more sketch points exist

Visual Basic for Applications (VBA) Syntax

See [EnumSketchPoints::Next](#).

Remarks

For use in in-process DLLs only.

See Also

[IEnumSketchPoints Interface](#)

[IEnumSketchPoints Members](#)

Availability

SOLIDWORKS 99, datecode 1999207

SOLIDWORKS API Help

[Send comments on this topic.](#)

Reset Method (IEnumSketchPoints)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IEnumSketchPoints Interface](#) : Reset Method (IEnumSketchPoints)

Resets the sequence to the beginning of the sketch points enumeration.

.NET Syntax

Visual Basic (Declaration)

```
Sub Reset()
```

Visual Basic (Usage)



```
Dim instance As IEnumSketchPoints  
instance.Reset()
```

C#

```
void Reset()
```

C++/CLI

```
void Reset();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Visual Basic for Applications (VBA) Syntax

See [EnumSketchPoints::Reset](#).

Remarks

For use in in-process DLLs only.

See Also

Availability

SOLIDWORKS 99, datecode 1999207

SOLIDWORKS API Help

[Send comments](#) on this topic.

Skip Method (IEnumSketchPoints)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IEnumSketchPoints Interface](#) : Skip Method (IEnumSketchPoints)

Skips the specified number of sketch points in the sketch points enumeration.

.NET Syntax

Visual Basic (Declaration)

```
Sub Skip( _  
    ByVal Celt As System.Integer _  
)
```

Visual Basic (Usage)



```
Dim instance As IEnumSketchPoints  
Dim Celt As System.Integer  
  
instance.Skip(Celt)
```

C#

```
void Skip(  
    System.int Celt  
)
```

C++/CLI

```
void Skip(  
& System.int Celt  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Celt
Number of sketch points to skip

Visual Basic for Applications (VBA) Syntax

See [EnumSketchPoints::Skip](#).

Remarks

For use in in-process DLLs only.

See Also

[IEnumSketchPoints Interface](#)
[IEnumSketchPoints Members](#)

Availability

SOLIDWORKS 99, datecode 1999207

IEnumSketchSegments (Type)

IEnumSketchSegments Interface

[See Also](#) [Members](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) : IEnumSketchSegments Interface

Allows access to the [sketch segments](#) enumeration.

NOTE: Click the **Members** link, located near the top of the topic, to see this interface's methods and properties.

.NET Syntax

Visual Basic (Declaration)

```
Public Interface IEnumSketchSegments
```

Visual Basic (Usage)



```
Dim instance As IEnumSketchSegments
```

C#

```
public interface IEnumSketchSegments
```

C++/CLI

```
public interface class IEnumSketchSegments
```

Visual Basic for Applications (VBA) Syntax

See [EnumSketchSegments](#).

Example

[Select All Sketch Segments \(C++\)](#)

Remarks

For use in in-process DLLs only.

Accessors

- [IEnumSketchSegments::Clone](#)
- [IModelDoc2::ICreateClippedSplines](#)
- [IModelDoc2::ICreateSplinesByEqnParams](#)
- [ISketch::IEnumSketchSegments](#)
- [ISketch::IEnumSketchTextSegments](#)

Access Diagram

[EnumSketchSegments](#)

See Also

- [IEnumSketchSegments Members](#)
- [SolidWorks.Interop.sldworks Namespace](#)

IEnumSketchSegments Interface Methods

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) : IEnumSketchSegments Interface

For a list of all members of this type, see [IEnumerableSketchSegments members](#).

Public Methods

Name	Description
 Clone	Clones the sketch segments enumeration.
 Next	Gets the next sketch segment in the sketch segments enumeration.
 Reset	Resets the sequence to the beginning of the sketch segments enumeration.
 Skip	Skips the specified number of sketch segments in the sketch segments enumeration.

[Top](#)

See Also

[IEnumerableSketchSegments Interface](#)
[SolidWorks.Interop.sldworks Namespace](#)

IEnumeratorSketchSegments Interface Members

[See Also](#) [Methods](#)



[SolidWorks.Interop.sldworks Namespace](#) : IEnumeratorSketchSegments Interface

The following tables list the members exposed by [IEnumeratorSketchSegments](#).

Public Methods

Name	Description
 Clone	Clones the sketch segments enumeration.
 Next	Gets the next sketch segment in the sketch segments enumeration.
 Reset	Resets the sequence to the beginning of the sketch segments enumeration.
 Skip	Skips the specified number of sketch segments in the sketch segments enumeration.

[Top](#)

See Also

[IEnumeratorSketchSegments Interface](#)
[SolidWorks.Interop.sldworks Namespace](#)

Clone Method (IEnumeratorSketchSegments)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IEnumeratorSketchSegments Interface](#) : Clone Method (IEnumeratorSketchSegments)

Clones the sketch segments enumeration.

Visual Basic Syntax

Visual Basic (Declaration)

```
Sub Clone( _  
    ByRef Ppenum As EnumSketchSegments _  
)
```

Visual Basic (Usage)

```
Dim instance As IEnumeratorSketchSegments  
Dim Ppenum As EnumSketchSegments  
  
instance.Clone(Ppenum)
```

Copy Code

C#

```
void Clone(  
    out EnumSketchSegments Ppenum  
)
```

C++/CLI

```
void Clone(  
& [Out] EnumSketchSegments^ Ppenum  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Ppenum

Pointer to the cloned [sketch segments enumeration](#)

Visual Basic for Applications (VBA) Syntax

See [EnumSketchSegments::Clone](#).

Remarks

For use in in-process DLLs only.

See Also

[IEnumSketchSegments Interface](#)

[IEnumSketchSegments Members](#)

Availability

SOLIDWORKS 99, datecode 1999207

SOLIDWORKS API Help

[Send comments](#) on this topic.

Next Method (IEnumSketchSegments)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IEnumSketchSegments Interface](#) : Next Method (IEnumSketchSegments)

Gets the next sketch segment in the sketch segments enumeration.

.NET Syntax

Visual Basic (Declaration)

```
Sub Next( _  
    ByVal Celt As System.Integer, _  
    ByRef Rgelt As SketchSegment, _  
    ByRef PceltFetched As System.Integer _  
)
```

Visual Basic (Usage)

```
Dim instance As IEnumSketchSegments  
Dim Celt As System.Integer  
Dim Rgelt As SketchSegment  
Dim PceltFetched As System.Integer
```

```
instance.Next(Celt, Rgelt, PceltFetched)
```

C#



```
void Next(  
    System.int Celt,  
    out SketchSegment Rgelt,  
    out System.int PceltFetched  
)
```

C++/CLI

```
void Next(  
    & System.int Celt,  
    & [Out] SketchSegment^ Rgelt,  
    & [Out] System.int PceltFetched  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Celt

Number of sketch segments for the sketch segments enumeration

Rgelt

Pointer to an array of [sketch segments](#) of size Celt

PceltFetched

Pointer to the number of sketch segments returned from the list; this value can be less than celt if you ask for more sketch segments than exist, or it can be NULL if no more sketch segments exist

Visual Basic for Applications (VBA) Syntax

See [EnumSketchSegments::Next](#).

Example

[Select All Sketch Segments \(C++\)](#)

Remarks

For use in in-process DLLs only.

See Also

[IEnumSketchSegments Interface](#)

[IEnumSketchSegments Members](#)

Availability

SOLIDWORKS 99, datecode 1999207

SOLIDWORKS API Help

[Send comments on this topic.](#)

Reset Method (IEnumSketchSegments)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IEnumSketchSegments Interface](#) : Reset Method (IEnumSketchSegments)

Resets the sequence to the beginning of the sketch segments enumeration.

.NET Syntax

Visual Basic (Declaration)

```
Sub Reset()
```

Visual Basic (Usage)



```
Dim instance As IEnumSketchSegments
```

```
instance.Reset()
```

C#

```
void Reset()
```

C++/CLI

```
void Reset();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Visual Basic for Applications (VBA) Syntax

See [EnumSketchSegments::Reset](#).

Remarks

For use in in-process DLLs only.

See Also

[IEnumSketchSegments Interface](#)
[IEnumSketchSegments Members](#)

Availability

SOLIDWORKS 99, datecode 1999207

SOLIDWORKS API Help

[Send comments on this topic.](#)

Skip Method (IEnumSketchSegments)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IEnumSketchSegments Interface](#) : Skip Method (IEnumSketchSegments)

Skips the specified number of sketch segments in the sketch segments enumeration.

.NET Syntax

Visual Basic (Declaration)

```
Sub Skip(  
    ByVal Celt As System.Integer _  
)
```

Visual Basic (Usage)



```
Dim instance As IEnumSketchSegments  
Dim Celt As System.Integer  
  
instance.Skip(Celt)
```

C#

```
void Skip(  
    System.int Celt  
)
```

C++/CLI

```
void Skip(  
&    System.int Celt  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Celt
Number of sketch segments to skip

Visual Basic for Applications (VBA) Syntax

See [EnumSketchSegments::Skip](#).

Remarks

For use in in-process DLLs only.

See Also

[IEnumSketchSegments Interface](#)
[IEnumSketchSegments Members](#)

Availability

SOLIDWORKS 99, datecode 1999207