

SOLIDWORKS API (.NET VBA C#) — Reference

(170/337): IModelDoc (part 6 of 13)

SOLIDWORKS API Documentation (converted from CHM)

IModelDoc (part 6 of 13) (Type)

SOLIDWORKS API Help

[Send comments](#) on this topic.

GetLayerManager Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : GetLayerManager Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::GetLayerManager](#).

.NET Syntax

Visual Basic (Declaration)

```
Function GetLayerManager() As System.Object
```

Visual Basic (Usage)



```
Dim instance As IModelDoc  
Dim value As System.Object  
  
value = instance.GetLayerManager()
```

C#

```
System.object GetLayerManager()
```

C++/CLI

```
System.Object^ GetLayerManager();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Visual Basic for Applications (VBA) Syntax

See [ModelDoc::GetLayerManager](#).

See Also

[IModelDoc Interface](#)
[IModelDoc Members](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

GetLightSourceCount Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : GetLightSourceCount Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::GetLightSourceCount](#).

.NET Syntax

Visual Basic (Declaration)

```
Function GetLightSourceCount() As System.Integer
```

Visual Basic (Usage)



```
Dim instance As IModelDoc  
Dim value As System.Integer  
  
value = instance.GetLightSourceCount()
```

C#

```
System.int GetLightSourceCount()
```

C++/CLI

```
System.int GetLightSourceCount();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Visual Basic for Applications (VBA) Syntax

See [ModelDoc::GetLightSourceCount](#).

See Also

[IModelDoc Interface](#)
[IModelDoc Members](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

GetLightSourceExtProperty Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : GetLightSourceExtProperty Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::GetLightSourceExtProperty](#).

.NET Syntax

Visual Basic (Declaration)

```
Function GetLightSourceExtProperty( _  
    ByVal ID As System.Integer, _  
    ByVal PropertyId As System.Integer _  
) As System.Object
```

Visual Basic (Usage)



```
Dim instance As IModelDoc  
Dim ID As System.Integer  
Dim PropertyId As System.Integer  
Dim value As System.Object
```

```
value = instance.GetLightSourceExtProperty(ID, PropertyId)
```

C#

```
System.object GetLightSourceExtProperty(  
    System.int ID,  
    System.int PropertyId  
)
```

C++/CLI

```
System.Object^ GetLightSourceExtProperty(  
& System.int ID,  
& System.int PropertyId  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

ID

PropertyId

Visual Basic for Applications (VBA) Syntax

See [ModelDoc::GetLightSourceExtProperty](#).

See Also

GetLightSourceIdFromName Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : GetLightSourceIdFromName Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::GetLightSourceIdFromName](#).

.NET Syntax

Visual Basic (Declaration)

```
Function GetLightSourceIdFromName( _  
    ByVal LightName As System.String _  
) As System.Integer
```

Visual Basic (Usage)



```
Dim instance As IModelDoc  
Dim LightName As System.String  
Dim value As System.Integer  
  
value = instance.GetLightSourceIdFromName(LightName)
```

C#

```
System.int GetLightSourceIdFromName(  
    System.string LightName  
)
```

C++/CLI

```
System.int GetLightSourceIdFromName(  
& System.String^ LightName  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

LightName

Visual Basic for Applications (VBA) Syntax

See [ModelDoc::GetLightSourceIdFromName](#).

See Also

[IModelDoc Interface](#)
[IModelDoc Members](#)

GetLightSourceName Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : GetLightSourceName Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::GetLightSourceName](#).

.NET Syntax

Visual Basic (Declaration)

```
Function GetLightSourceName( _  
    ByVal ID As System.Integer _  
) As System.String
```

Visual Basic (Usage)

```
Dim instance As IModelDoc
Dim ID As System.Integer
Dim value As System.String

value = instance.GetLightSourceName(ID)
```

C#

```
System.string GetLightSourceName(
    System.int ID
)
```

C++/CLI

```
System.String^ GetLightSourceName(
    & System.int ID
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

ID

Visual Basic for Applications (VBA) Syntax

See [ModelDoc::GetLightSourceName](#).

See Also

[IModelDoc Interface](#)
[IModelDoc Members](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

GetLineCount Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : GetLineCount Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::GetLineCount](#).

.NET Syntax

Visual Basic (Declaration)

```
Function GetLineCount() As System.Integer
```

Visual Basic (Usage)

```
Dim instance As IModelDoc
Dim value As System.Integer

value = instance.GetLineCount()
```

C#

```
System.int GetLineCount()
```

C++/CLI

```
System.int GetLineCount();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Visual Basic for Applications (VBA) Syntax

See [ModelDoc::GetLineCount](#).

See Also

[IModelDoc Interface](#)
[IModelDoc Members](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

GetLines Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : GetLines Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::GetLines](#).

.NET Syntax

Visual Basic (Declaration)

```
Function GetLines() As System.Object
```

Visual Basic (Usage)



```
Dim instance As IModelDoc  
Dim value As System.Object  
  
value = instance.GetLines()
```

C#

```
System.object GetLines()
```

C++/CLI

```
System.Object^ GetLines();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Visual Basic for Applications (VBA) Syntax

See [ModelDoc::GetLines](#).

See Also

[IModelDoc Interface](#)
[IModelDoc Members](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

GetMassProperties Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : GetMassProperties Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::GetMassProperties](#).

.NET Syntax

Visual Basic (Declaration)

```
Function GetMassProperties() As System.Object
```

Visual Basic (Usage)



```
Dim instance As IModelDoc  
Dim value As System.Object  
  
value = instance.GetMassProperties()
```

C#

```
System.Object GetMassProperties()
```

C++/CLI

```
System.Object^ GetMassProperties();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Visual Basic for Applications (VBA) Syntax

See [ModelDoc::GetMassProperties](#).

See Also

[IModelDoc Interface](#)
[IModelDoc Members](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

GetMassProperties2 Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : GetMassProperties2 Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::GetMassProperties2](#).

.NET Syntax

Visual Basic (Declaration)

```
Function GetMassProperties2( _  
    ByRef Status As System.Integer _  
) As System.Object
```

Visual Basic (Usage)



```
Dim instance As IModelDoc  
Dim Status As System.Integer  
Dim value As System.Object  
  
value = instance.GetMassProperties2(Status)
```

C#

```
System.Object GetMassProperties2(  
    out System.int Status  
)
```

C++/CLI

```
System.Object^ GetMassProperties2(  
& [Out] System.int Status  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Status

Visual Basic for Applications (VBA) Syntax

See [ModelDoc::GetMassProperties2](#).

See Also

[IModelDoc Interface](#)
[IModelDoc Members](#)

GetModelViewCount Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : GetModelViewCount Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::GetModelViewCount](#).

.NET Syntax

Visual Basic (Declaration)

```
Function GetModelViewCount() As System.Integer
```

Visual Basic (Usage)



```
Dim instance As IModelDoc  
Dim value As System.Integer  
  
value = instance.GetModelViewCount()
```

C#

```
System.int GetModelViewCount()
```

C++/CLI

```
System.int GetModelViewCount();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Visual Basic for Applications (VBA) Syntax

See [ModelDoc::GetModelViewCount](#).

See Also

[IModelDoc Interface](#)
[IModelDoc Members](#)

GetModelViewNames Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : GetModelViewNames Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::GetModelViewNames](#).

.NET Syntax

Visual Basic (Declaration)

```
Function GetModelViewNames() As System.Object
```

Visual Basic (Usage)



```
Dim instance As IModelDoc  
Dim value As System.Object  
  
value = instance.GetModelViewNames()
```

C#

```
System.object GetModelViewNames()
```

C++/CLI

```
System.Object^ GetModelViewNames();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Visual Basic for Applications (VBA) Syntax

See [ModelDoc::GetModelViewNames](#).

See Also

[IModelDoc Interface](#)
[IModelDoc Members](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

GetNext Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : GetNext Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::GetNext](#).

.NET Syntax

Visual Basic (Declaration)

```
Function GetNext() As System.Object
```

Visual Basic (Usage)



```
Dim instance As IModelDoc  
Dim value As System.Object  
  
value = instance.GetNext()
```

C#

```
System.object GetNext()
```

C++/CLI

```
System.Object^ GetNext();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Visual Basic for Applications (VBA) Syntax

See [ModelDoc::GetNext](#).

See Also

[IModelDoc Interface](#)
[IModelDoc Members](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

GetNumDependencies Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : GetNumDependencies Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::GetNumDependencies](#).

.NET Syntax

Visual Basic (Declaration)

```
Function GetNumDependencies( _  
    ByVal Traverseflag As System.Integer, _  
    ByVal Searchflag As System.Integer _  
) As System.Integer
```

Visual Basic (Usage)

```
Dim instance As IModelDoc  
Dim Traverseflag As System.Integer  
Dim Searchflag As System.Integer  
Dim value As System.Integer  
  
value = instance.GetNumDependencies(Traverseflag, Searchflag)
```

C#

```
System.int GetNumDependencies(  
    System.int Traverseflag,  
    System.int Searchflag  
)
```

C++/CLI

```
System.int GetNumDependencies(  
& System.int Traverseflag,  
& System.int Searchflag  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Traverseflag

Searchflag

Visual Basic for Applications (VBA) Syntax

See [ModelDoc::GetNumDependencies](#).

See Also

[IModelDoc Interface](#)
[IModelDoc Members](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

GetPathName Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : GetPathName Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::GetPathName](#).

.NET Syntax

Visual Basic (Declaration)

```
Function GetPathName() As System.String
```

Visual Basic (Usage)

```
Dim instance As IModelDoc  
Dim value As System.String  
  
value = instance.GetPathName()
```

C#

```
System.string GetPathName()
```

C++/CLI

```
System.String^ GetPathName();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Visual Basic for Applications (VBA) Syntax

See [ModelDoc::GetPathName](#).

See Also

[IModelDoc Interface](#)
[IModelDoc Members](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

GetPointLightProperties Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : GetPointLightProperties Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::GetPointLightProperties](#).

.NET Syntax

Visual Basic (Declaration)

```
Function GetPointLightProperties( _  
    ByVal Name As System.String, _  
    ByRef Ambient As System.Double, _  
    ByRef Diffuse As System.Double, _  
    ByRef Specular As System.Double, _  
    ByRef Colour As System.Integer, _  
    ByRef Enabled As System.Boolean, _  
    ByRef Fixed As System.Boolean, _  
    ByRef X As System.Double, _  
    ByRef Y As System.Double, _  
    ByRef Z As System.Double _  
) As System.Boolean
```

Visual Basic (Usage)



```
Dim instance As IModelDoc  
Dim Name As System.String  
Dim Ambient As System.Double  
Dim Diffuse As System.Double  
Dim Specular As System.Double  
Dim Colour As System.Integer  
Dim Enabled As System.Boolean  
Dim Fixed As System.Boolean  
Dim X As System.Double  
Dim Y As System.Double  
Dim Z As System.Double  
Dim value As System.Boolean
```

```
value = instance.GetPointLightProperties(Name, Ambient, Diffuse, Specular, Colour, Enabled, Fixed,  
X, Y, Z)
```

C#

```
System.bool GetPointLightProperties(  
    System.string Name,  
    ref System.double Ambient,  
    ref System.double Diffuse,  
    ref System.double Specular,  
    ref System.int Colour,  
    ref System.bool Enabled,  
    ref System.bool Fixed,  
    ref System.double X,  
    ref System.double Y,  
    ref System.double Z  
)
```

C++/CLI

```

System.bool GetPointLightProperties(
& System.String^ Name,
& System.double% Ambient,
& System.double% Diffuse,
& System.double% Specular,
& System.int% Colour,
& System.bool% Enabled,
& System.bool% Fixed,
& System.double% X,
& System.double% Y,
& System.double% Z
)

```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Name

Ambient

Diffuse

Specular

Colour

Enabled

Fixed

X

Y

Z

Visual Basic for Applications (VBA) Syntax

See [ModelDoc::GetPointLightProperties](#).

See Also

[IModelDoc Interface](#)
[IModelDoc Members](#)

SOLIDWORKS API Help

[Send comments on this topic.](#)

GetPopupMenuMode Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : GetPopupMenuMode Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::GetPopupMenuMode](#).

.NET Syntax

Visual Basic (Declaration)

```
Function GetPopupMenuMode() As System.Integer
```

Visual Basic (Usage)



```

Dim instance As IModelDoc
Dim value As System.Integer

value = instance.GetPopupMenuMode()

```

C#

```
System.int GetPopupMenuMode()
```

C++/CLI

```
System.int GetPopupMenuMode();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Visual Basic for Applications (VBA) Syntax

See [ModelDoc::GetPopupMenuMode](#).

See Also

[IModelDoc Interface](#)
[IModelDoc Members](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

GetPropertyExtension Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : GetPropertyExtension Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::GetPropertyExtension](#).

.NET Syntax

Visual Basic (Declaration)

```
Function GetPropertyExtension( _  
    ByVal ID As System.Integer _  
) As System.Object
```

Visual Basic (Usage)



```
Dim instance As IModelDoc  
Dim ID As System.Integer  
Dim value As System.Object  
  
value = instance.GetPropertyExtension(ID)
```

C#

```
System.object GetPropertyExtension(  
    System.int ID  
)
```

C++/CLI

```
System.Object^ GetPropertyExtension(  
&    System.int ID  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

ID

Visual Basic for Applications (VBA) Syntax

See [ModelDoc::GetPropertyExtension](#).

See Also

[IModelDoc Interface](#)
[IModelDoc Members](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

GetPropertyManagerPage Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : GetPropertyManagerPage Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::GetPropertyManagerPage](#).

.NET Syntax

Visual Basic (Declaration)

```
Function GetPropertyManagerPage( _  
    ByVal DialogId As System.Integer, _  
    ByVal Title As System.String, _  
    ByVal Handler As System.Object _  
) As PropertyManagerPage
```

Visual Basic (Usage)



```
Dim instance As IModelDoc  
Dim DialogId As System.Integer  
Dim Title As System.String  
Dim Handler As System.Object  
Dim value As PropertyManagerPage  
  
value = instance.GetPropertyManagerPage(DialogId, Title, Handler)
```

C#

```
PropertyManagerPage GetPropertyManagerPage(  
    System.int DialogId,  
    System.string Title,  
    System.object Handler  
)
```

C++/CLI

```
PropertyManagerPage^ GetPropertyManagerPage(  
& System.int DialogId,  
& System.String^ Title,  
& System.Object^ Handler  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

DialogId

Title

Handler

Visual Basic for Applications (VBA) Syntax

See [ModelDoc::GetPropertyManagerPage](#).

See Also

[IModelDoc Interface](#)
[IModelDoc Members](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

GetRayIntersectionsPoints Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : GetRayIntersectionsPoints Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::GetRayIntersectionsPoints](#).

.NET Syntax

Visual Basic (Declaration)

```
Function GetRayIntersectionsPoints() As System.Object
```

Visual Basic (Usage)



```
Dim instance As IModelDoc  
Dim value As System.Object  
  
value = instance.GetRayIntersectionsPoints()
```

C#

```
System.object GetRayIntersectionsPoints()
```

C++/CLI

```
System.Object^ GetRayIntersectionsPoints();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Visual Basic for Applications (VBA) Syntax

See [ModelDoc::GetRayIntersectionsPoints](#).

See Also

[IModelDoc Interface](#)
[IModelDoc Members](#)

SOLIDWORKS API Help

[Send comments on this topic.](#)

GetRayIntersectionsTopology Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : GetRayIntersectionsTopology Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::GetRayIntersectionsTopology](#).

.NET Syntax

Visual Basic (Declaration)

```
Function GetRayIntersectionsTopology() As System.Object
```

Visual Basic (Usage)



```
Dim instance As IModelDoc  
Dim value As System.Object  
  
value = instance.GetRayIntersectionsTopology()
```

C#

```
System.object GetRayIntersectionsTopology()
```

C++/CLI

```
System.Object^ GetRayIntersectionsTopology();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Visual Basic for Applications (VBA) Syntax

See [ModelDoc::GetRayIntersectionsTopology](#).

See Also

[IModelDoc Interface](#)
[IModelDoc Members](#)

SOLIDWORKS API Help

[Send comments on this topic.](#)

GetSaveFlag Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : GetSaveFlag Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::GetSaveFlag](#).

.NET Syntax

Visual Basic (Declaration)

```
Function GetSaveFlag() As System.Boolean
```

Visual Basic (Usage)



```
Dim instance As IModelDoc  
Dim value As System.Boolean  
  
value = instance.GetSaveFlag()
```

C#

```
System.bool GetSaveFlag()
```

C++/CLI

```
System.bool GetSaveFlag();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Visual Basic for Applications (VBA) Syntax

See [ModelDoc::GetSaveFlag](#).

See Also

[IModelDoc Interface](#)
[IModelDoc Members](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

GetSceneBkgDIB Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : GetSceneBkgDIB Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::GetSceneBkgDIB](#).

.NET Syntax

Visual Basic (Declaration)

```
Function GetSceneBkgDIB() As System.Integer
```

Visual Basic (Usage)



```
Dim instance As IModelDoc  
Dim value As System.Integer  
  
value = instance.GetSceneBkgDIB()
```

C#

```
System.int GetSceneBkgDIB()
```

C++/CLI

```
System.int GetSceneBkgDIB();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Visual Basic for Applications (VBA) Syntax

See [ModelDoc::GetSceneBkgDIB](#).

 See Also

[IModelDoc Interface](#)
[IModelDoc Members](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

GetSceneExtProperty Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : GetSceneExtProperty Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::GetSceneExtProperty](#).

 .NET Syntax

Visual Basic (Declaration)

```
Function GetSceneExtProperty( _  
    ByVal PropertyId As System.Integer _  
) As System.Object
```

Visual Basic (Usage)



```
Dim instance As IModelDoc  
Dim PropertyId As System.Integer  
Dim value As System.Object  
  
value = instance.GetSceneExtProperty(PropertyId)
```

C#

```
System.object GetSceneExtProperty(  
    System.int PropertyId  
)
```

C++/CLI

```
System.Object^ GetSceneExtProperty(  
& System.int PropertyId  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

PropertyId

 Visual Basic for Applications (VBA) Syntax

See [ModelDoc::GetSceneExtProperty](#).

 See Also

[IModelDoc Interface](#)
[IModelDoc Members](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

GetSpotlightProperties Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : GetSpotlightProperties Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::GetSpotlightProperties](#).

 .NET Syntax

Visual Basic (Declaration)

```

Function GetSpotlightProperties( _
    ByVal Name As System.String, _
    ByRef Ambient As System.Double, _
    ByRef Diffuse As System.Double, _
    ByRef Specular As System.Double, _
    ByRef Colour As System.Integer, _
    ByRef Enabled As System.Boolean, _
    ByRef Fixed As System.Boolean, _
    ByRef X As System.Double, _
    ByRef Y As System.Double, _
    ByRef Z As System.Double, _
    ByRef Targetx As System.Double, _
    ByRef Targety As System.Double, _
    ByRef Targetz As System.Double, _
    ByRef ConeAngle As System.Double _
) As System.Boolean

```

Visual Basic (Usage)



```

Dim instance As IModelDoc
Dim Name As System.String
Dim Ambient As System.Double
Dim Diffuse As System.Double
Dim Specular As System.Double
Dim Colour As System.Integer
Dim Enabled As System.Boolean
Dim Fixed As System.Boolean
Dim X As System.Double
Dim Y As System.Double
Dim Z As System.Double
Dim Targetx As System.Double
Dim Targety As System.Double
Dim Targetz As System.Double
Dim ConeAngle As System.Double
Dim value As System.Boolean

```

```

value = instance.GetSpotlightProperties(Name, Ambient, Diffuse, Specular, Colour, Enabled, Fixed,
X, Y, Z, Targetx, Targety, Targetz, ConeAngle)

```

C#

```

System.bool GetSpotlightProperties(
    System.string Name,
    ref System.double Ambient,
    ref System.double Diffuse,
    ref System.double Specular,
    ref System.int Colour,
    ref System.bool Enabled,
    ref System.bool Fixed,
    ref System.double X,
    ref System.double Y,
    ref System.double Z,
    ref System.double Targetx,
    ref System.double Targety,
    ref System.double Targetz,
    ref System.double ConeAngle
)

```

C++/CLI

```

System.bool GetSpotlightProperties(
    & System.String^ Name,
    & System.double% Ambient,
    & System.double% Diffuse,
    & System.double% Specular,
    & System.int% Colour,
    & System.bool% Enabled,
    & System.bool% Fixed,

```

```
& System.double% X,  
& System.double% Y,  
& System.double% Z,  
& System.double% Targetx,  
& System.double% Targety,  
& System.double% Targetz,  
& System.double% ConeAngle  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Name

Ambient

Diffuse

Specular

Colour

Enabled

Fixed

X

Y

Z

Targetx

Targety

Targetz

ConeAngle

Visual Basic for Applications (VBA) Syntax

See [ModelDoc::GetSpotlightProperties](#).

See Also

[IModelDoc Interface](#)
[IModelDoc Members](#)

SOLIDWORKS API Help

[Send comments on this topic.](#)

GetStandardViewRotation Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : GetStandardViewRotation Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::GetStandardViewRotation](#).

.NET Syntax

Visual Basic (Declaration)

```
Function GetStandardViewRotation( _  
    ByVal ViewId As System.Integer _  
) As System.Object
```

Visual Basic (Usage)



```
Dim instance As IModelDoc  
Dim ViewId As System.Integer  
Dim value As System.Object
```

```
value = instance.GetStandardViewRotation(ViewId)
```

C#

```
System.Object GetStandardViewRotation(  
    System.Int ViewId  
)
```

C++/CLI

```
System.Object^ GetStandardViewRotation(  
& System.Int ViewId  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

ViewId

Visual Basic for Applications (VBA) Syntax

See [ModelDoc::GetStandardViewRotation](#).

See Also

[IModelDoc Interface](#)
[IModelDoc Members](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

GetTessellationQuality Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : GetTessellationQuality Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::GetTessellationQuality](#).

.NET Syntax

Visual Basic (Declaration)

```
Function GetTessellationQuality() As System.Integer
```

Visual Basic (Usage)



```
Dim instance As IModelDoc  
Dim value As System.Integer  
  
value = instance.GetTessellationQuality()
```

C#

```
System.Int GetTessellationQuality()
```

C++/CLI

```
System.Int GetTessellationQuality();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Visual Basic for Applications (VBA) Syntax

See [ModelDoc::GetTessellationQuality](#).

See Also

[IModelDoc Interface](#)
[IModelDoc Members](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

GetTitle Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : GetTitle Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::GetTitle](#).

.NET Syntax

Visual Basic (Declaration)

```
Function GetTitle() As System.String
```

Visual Basic (Usage)



```
Dim instance As IModelDoc  
Dim value As System.String  
  
value = instance.GetTitle()
```

C#

```
System.string GetTitle()
```

C++/CLI

```
System.String^ GetTitle();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Visual Basic for Applications (VBA) Syntax

See [ModelDoc::GetTitle](#).

See Also

[IModelDoc Interface](#)
[IModelDoc Members](#)

SOLIDWORKS API Help

[Send comments on this topic.](#)

GetToolbarVisibility Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : GetToolbarVisibility Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::GetToolbarVisibility](#).

.NET Syntax

Visual Basic (Declaration)

```
Function GetToolbarVisibility( _  
    ByVal Toolbar As System.Integer _  
) As System.Boolean
```

Visual Basic (Usage)



```
Dim instance As IModelDoc  
Dim Toolbar As System.Integer  
Dim value As System.Boolean  
  
value = instance.GetToolbarVisibility(Toolbar)
```

C#

```
System.bool GetToolbarVisibility(  
    System.int Toolbar  
)
```

C++/CLI

```
System.bool GetToolbarVisibility(  
& System.int Toolbar  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Toolbar

Visual Basic for Applications (VBA) Syntax

See [ModelDoc::GetToolbarVisibility](#).

See Also

[IModelDoc Interface](#)
[IModelDoc Members](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

GetType Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : GetType Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::GetType](#).

.NET Syntax

Visual Basic (Declaration)

```
Function GetType() As System.Integer
```

Visual Basic (Usage)



```
Dim instance As IModelDoc  
Dim value As System.Integer  
  
value = instance.GetType()
```

C#

```
System.int GetType()
```

C++/CLI

```
System.int GetType();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Visual Basic for Applications (VBA) Syntax

See [ModelDoc::GetType](#).

See Also

[IModelDoc Interface](#)
[IModelDoc Members](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

GetUnits Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : GetUnits Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::GetUnits](#).

.NET Syntax

Visual Basic (Declaration)

```
Function GetUnits() As System.Object
```

Visual Basic (Usage)



```
Dim instance As IModelDoc  
Dim value As System.Object  
  
value = instance.GetUnits()
```

C#

```
System.Object GetUnits()
```

C++/CLI

```
System.Object^ GetUnits();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Visual Basic for Applications (VBA) Syntax

See [ModelDoc::GetUnits](#).

See Also

[IModelDoc Interface](#)
[IModelDoc Members](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

GetUpdateStamp Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : GetUpdateStamp Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::GetUpdateStamp](#).

.NET Syntax

Visual Basic (Declaration)

```
Function GetUpdateStamp() As System.Integer
```

Visual Basic (Usage)



```
Dim instance As IModelDoc  
Dim value As System.Integer  
  
value = instance.GetUpdateStamp()
```

C#

```
System.int GetUpdateStamp()
```

C++/CLI

```
System.int GetUpdateStamp();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Visual Basic for Applications (VBA) Syntax

See [ModelDoc::GetUpdateStamp](#).

See Also

[IModelDoc Interface](#)
[IModelDoc Members](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

GetUserPreferenceDoubleValue Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : GetUserPreferenceDoubleValue Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::GetUserPreferenceDoubleValue](#).

.NET Syntax

Visual Basic (Declaration)

```
Function GetUserPreferenceDoubleValue(  
    ByVal UserPreferenceValue As System.Integer _  
) As System.Double
```

Visual Basic (Usage)



```
Dim instance As IModelDoc  
Dim UserPreferenceValue As System.Integer  
Dim value As System.Double  
  
value = instance.GetUserPreferenceDoubleValue(UserPreferenceValue)
```

C#

```
System.double GetUserPreferenceDoubleValue(  
    System.int UserPreferenceValue  
)
```

C++/CLI

```
System.double GetUserPreferenceDoubleValue(  
    & System.int UserPreferenceValue  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

UserPreferenceValue

Visual Basic for Applications (VBA) Syntax

See [ModelDoc::GetUserPreferenceDoubleValue](#).

See Also

[IModelDoc Interface](#)
[IModelDoc Members](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

GetUserPreferenceIntegerValue Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : GetUserPreferenceIntegerValue Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::GetUserPreferenceIntegerValue](#).

.NET Syntax

Visual Basic (Declaration)

```
Function GetUserPreferenceIntegerValue( _  
    ByVal UserPreferenceValue As System.Integer _  
) As System.Integer
```

Visual Basic (Usage)



```
Dim instance As IModelDoc  
Dim UserPreferenceValue As System.Integer  
Dim value As System.Integer  
  
value = instance.GetUserPreferenceIntegerValue(UserPreferenceValue)
```

C#

```
System.int GetUserPreferenceIntegerValue(  
    System.int UserPreferenceValue  
)
```

C++/CLI

```
System.int GetUserPreferenceIntegerValue(  
& System.int UserPreferenceValue  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

UserPreferenceValue

Visual Basic for Applications (VBA) Syntax

See [ModelDoc::GetUserPreferenceIntegerValue](#).

See Also

[IModelDoc Interface](#)
[IModelDoc Members](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

GetUserPreferenceStringValue Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : GetUserPreferenceStringValue Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::GetUserPreferenceStringValue](#).

.NET Syntax

Visual Basic (Declaration)

```
Function GetUserPreferenceStringValue( _  
    ByVal UserPreference As System.Integer _  
) As System.String
```

Visual Basic (Usage)



```
Dim instance As IModelDoc  
Dim UserPreference As System.Integer  
Dim value As System.String  
  
value = instance.GetUserPreferenceStringValue(UserPreference)
```

C#

```
System.string GetUserPreferenceStringValue(  
    System.int UserPreference  
)
```

C++/CLI

```
System.String^ GetUserPreferenceStringValue(  
& System.int UserPreference  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

UserPreference

Visual Basic for Applications (VBA) Syntax

See [ModelDoc::GetUserPreferenceStringValue](#).

See Also

[IModelDoc Interface](#)
[IModelDoc Members](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

GetUserPreferenceTextFormat Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : GetUserPreferenceTextFormat Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::GetUserPreferenceTextFormat](#).

.NET Syntax

Visual Basic (Declaration)

```
Function GetUserPreferenceTextFormat( _  
    ByVal UserPreferenceValue As System.Integer _  
) As System.Object
```

Visual Basic (Usage)



```
Dim instance As IModelDoc  
Dim UserPreferenceValue As System.Integer  
Dim value As System.Object  
  
value = instance.GetUserPreferenceTextFormat(UserPreferenceValue)
```

C#

```
System.object GetUserPreferenceTextFormat(  
    System.int UserPreferenceValue  
)
```

C++/CLI

```
System.Object^ GetUserPreferenceTextFormat(  
& System.int UserPreferenceValue  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

UserPreferenceValue

Visual Basic for Applications (VBA) Syntax

See [ModelDoc::GetUserPreferenceTextFormat](#).

See Also

[IModelDoc Interface](#)
[IModelDoc Members](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

GetUserPreferenceToggle Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : GetUserPreferenceToggle Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::GetUserPreferenceToggle](#).

.NET Syntax

Visual Basic (Declaration)

```
Function GetUserPreferenceToggle( _  
    ByVal UserPreferenceToggle As System.Integer _  
) As System.Boolean
```

Visual Basic (Usage)



```
Dim instance As IModelDoc  
Dim UserPreferenceToggle As System.Integer  
Dim value As System.Boolean  
  
value = instance.GetUserPreferenceToggle(UserPreferenceToggle)
```

C#

```
System.bool GetUserPreferenceToggle(  
    System.int UserPreferenceToggle  
)
```

C++/CLI

```
System.bool GetUserPreferenceToggle(  
    & System.int UserPreferenceToggle  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

UserPreferenceToggle

Visual Basic for Applications (VBA) Syntax

See [ModelDoc::GetUserPreferenceToggle](#).

See Also

[IModelDoc Interface](#)
[IModelDoc Members](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

GetUserUnit Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : GetUserUnit Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::GetUserUnit](#).

.NET Syntax

Visual Basic (Declaration)

```
Function GetUserUnit( _  
    ByVal UnitType As System.Integer _  
) As System.Object
```

Visual Basic (Usage)



```
Dim instance As IModelDoc  
Dim UnitType As System.Integer  
Dim value As System.Object  
  
value = instance.GetUserUnit(UnitType)
```

C#

```
System.object GetUserUnit(  
    System.int UnitType  
)
```

C++/CLI

```
System.Object^ GetUserUnit(  
& System.int UnitType  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

UnitType

Visual Basic for Applications (VBA) Syntax

See [ModelDoc2::GetUserUnit](#).

See Also

[IModelDoc Interface](#)
[IModelDoc Members](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

GetVisibilityOfConstructPlanes Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : GetVisibilityOfConstructPlanes Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::GetVisibilityOfConstructPlanes](#).

.NET Syntax

Visual Basic (Declaration)

```
Function GetVisibilityOfConstructPlanes() As System.Boolean
```

Visual Basic (Usage)



```
Dim instance As IModelDoc  
Dim value As System.Boolean  
  
value = instance.GetVisibilityOfConstructPlanes()
```

C#

```
System.bool GetVisibilityOfConstructPlanes()
```

C++/CLI

```
System.bool GetVisibilityOfConstructPlanes();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Visual Basic for Applications (VBA) Syntax

See [ModelDoc::GetVisibilityOfConstructPlanes](#).

See Also

[IModelDoc Interface](#)
[IModelDoc Members](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

GraphicsRedraw Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : GraphicsRedraw Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::GraphicsRedraw](#).

.NET Syntax

Visual Basic (Declaration)

```
Sub GraphicsRedraw()
```

Visual Basic (Usage)



```
Dim instance As IModelDoc  
  
instance.GraphicsRedraw()
```

C#

```
void GraphicsRedraw()
```

C++/CLI

```
void GraphicsRedraw();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Visual Basic for Applications (VBA) Syntax

See [ModelDoc::GraphicsRedraw](#).

See Also

[IModelDoc Interface](#)
[IModelDoc Members](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

GraphicsRedraw2 Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : GraphicsRedraw2 Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::GraphicsRedraw2](#).

.NET Syntax

Visual Basic (Declaration)

```
Sub GraphicsRedraw2()
```

Visual Basic (Usage)



```
Dim instance As IModelDoc  
  
instance.GraphicsRedraw2()
```

C#

```
void GraphicsRedraw2()
```

C++/CLI

```
void GraphicsRedraw2();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Visual Basic for Applications (VBA) Syntax

See [ModelDoc::GraphicsRedraw2](#).

See Also

[IModelDoc Interface](#)
[IModelDoc Members](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

GridOptions Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : GridOptions Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::GridOptions](#).

.NET Syntax

Visual Basic (Declaration)

```
Sub GridOptions( _  
    ByVal DispGrid As System.Boolean, _  
    ByVal GridSpacing As System.Double, _  
    ByVal Snap As System.Boolean, _  
    ByVal DotStyle As System.Boolean, _  
    ByVal NMajor As System.Short, _  
    ByVal NMinor As System.Short, _  
    ByVal Align2edge As System.Boolean, _  
    ByVal AngleSnap As System.Boolean, _  
    ByVal AngleUnit As System.Double, _  
    ByVal MinorAuto As System.Boolean _  
)
```

Visual Basic (Usage)



```
Dim instance As IModelDoc  
Dim DispGrid As System.Boolean  
Dim GridSpacing As System.Double  
Dim Snap As System.Boolean  
Dim DotStyle As System.Boolean  
Dim NMajor As System.Short  
Dim NMinor As System.Short  
Dim Align2edge As System.Boolean  
Dim AngleSnap As System.Boolean  
Dim AngleUnit As System.Double  
Dim MinorAuto As System.Boolean
```

```
instance.GridOptions(DispGrid, GridSpacing, Snap, DotStyle, NMajor, NMinor, Align2edge, AngleSnap,  
AngleUnit, MinorAuto)
```

C#

```
void GridOptions(  
    System.bool DispGrid,  
    System.double GridSpacing,  
    System.bool Snap,  
    System.bool DotStyle,  
    System.short NMajor,
```

```

System.short NMinor,
System.bool Align2edge,
System.bool AngleSnap,
System.double AngleUnit,
System.bool MinorAuto
)

```

C++/CLI

```

void GridOptions(
& System.bool DispGrid,
& System.double GridSpacing,
& System.bool Snap,
& System.bool DotStyle,
& System.short NMajor,
& System.short NMinor,
& System.bool Align2edge,
& System.bool AngleSnap,
& System.double AngleUnit,
& System.bool MinorAuto
)

```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

DispGrid

GridSpacing

Snap

DotStyle

NMajor

NMinor

Align2edge

AngleSnap

AngleUnit

MinorAuto

Visual Basic for Applications (VBA) Syntax

See [ModelDoc::GridOptions](#).

See Also

[IModelDoc Interface](#)

[IModelDoc Members](#)

SOLIDWORKS API Help

[Send comments on this topic.](#)

HideComponent2 Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : HideComponent2 Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::HideComponent2](#).

.NET Syntax

Visual Basic (Declaration)

```
Sub HideComponent2()
```

Visual Basic (Usage)

```
Dim instance As IModelDoc
```

```
instance.HideComponent2()
```

C#



```
void HideComponent2()
```

C++/CLI

```
void HideComponent2();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Visual Basic for Applications (VBA) Syntax

See [ModelDoc::HideComponent2](#).

See Also

[IModelDoc Interface](#)
[IModelDoc Members](#)

SOLIDWORKS API Help

[Send comments on this topic.](#)

HideCosmeticThread Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : HideCosmeticThread Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::HideCosmeticThread](#).

.NET Syntax

Visual Basic (Declaration)

```
Sub HideCosmeticThread()
```

Visual Basic (Usage)



```
Dim instance As IModelDoc  
instance.HideCosmeticThread()
```

C#

```
void HideCosmeticThread()
```

C++/CLI

```
void HideCosmeticThread();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Visual Basic for Applications (VBA) Syntax

See [ModelDoc::HideCosmeticThread](#).

See Also

[IModelDoc Interface](#)
[IModelDoc Members](#)

SOLIDWORKS API Help

[Send comments on this topic.](#)

HideDimension Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : HideDimension Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::HideDimension](#).

.NET Syntax

Visual Basic (Declaration)

```
Sub HideDimension()
```

Visual Basic (Usage)



```
Dim instance As IModelDoc  
  
instance.HideDimension()
```

C#

```
void HideDimension()
```

C++/CLI

```
void HideDimension();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Visual Basic for Applications (VBA) Syntax

See [ModelDoc::HideDimension](#).

See Also

[IModelDoc Interface](#)
[IModelDoc Members](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

HideFeatureDimensions Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : HideFeatureDimensions Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::HideFeatureDimensions](#).

.NET Syntax

Visual Basic (Declaration)

```
Sub HideFeatureDimensions()
```

Visual Basic (Usage)



```
Dim instance As IModelDoc  
  
instance.HideFeatureDimensions()
```

C#

```
void HideFeatureDimensions()
```

C++/CLI

```
void HideFeatureDimensions();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Visual Basic for Applications (VBA) Syntax

See [ModelDoc::HideFeatureDimensions](#).

See Also

[IModelDoc Interface](#)
[IModelDoc Members](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

HideShowBodies Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : HideShowBodies Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::HideShowBodies](#).

.NET Syntax

Visual Basic (Declaration)

```
Sub HideShowBodies()
```

Visual Basic (Usage)



```
Dim instance As IModelDoc  
instance.HideShowBodies()
```

C#

```
void HideShowBodies()
```

C++/CLI

```
void HideShowBodies();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Visual Basic for Applications (VBA) Syntax

See [ModelDoc::HideShowBodies](#).

See Also

[IModelDoc Interface](#)
[IModelDoc Members](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

HideSolidBody Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : HideSolidBody Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::HideSolidBody](#).

.NET Syntax

Visual Basic (Declaration)

```
Sub HideSolidBody()
```

Visual Basic (Usage)



```
Dim instance As IModelDoc  
instance.HideSolidBody()
```

C#

```
void HideSolidBody()
```

C++/CLI

```
void HideSolidBody();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Visual Basic for Applications (VBA) Syntax

See [ModelDoc::HideSolidBody](#).

See Also

[IModelDoc Interface](#)
[IModelDoc Members](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

HoleWizard Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : HoleWizard Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::HoleWizard](#).

Visual Basic Syntax

Visual Basic (Declaration)

```
Sub HoleWizard( _  
    ByVal Depth As System.Double, _  
    ByVal EndType As System.Short, _  
    ByVal Flip As System.Boolean, _  
    ByVal Dir As System.Boolean, _  
    ByVal HType As System.Integer, _  
    ByVal D1 As System.Double, _  
    ByVal D2 As System.Double, _  
    ByVal D3 As System.Double, _  
    ByVal D4 As System.Double, _  
    ByVal D5 As System.Double, _  
    ByVal D6 As System.Double, _  
    ByVal D7 As System.Double, _  
    ByVal D8 As System.Double, _  
    ByVal D9 As System.Double, _  
    ByVal D10 As System.Double, _  
    ByVal D11 As System.Double, _  
    ByVal D12 As System.Double _  
)
```

Visual Basic (Usage)



```
Dim instance As IModelDoc  
Dim Depth As System.Double  
Dim EndType As System.Short  
Dim Flip As System.Boolean  
Dim Dir As System.Boolean  
Dim HType As System.Integer  
Dim D1 As System.Double  
Dim D2 As System.Double  
Dim D3 As System.Double  
Dim D4 As System.Double  
Dim D5 As System.Double  
Dim D6 As System.Double  
Dim D7 As System.Double  
Dim D8 As System.Double  
Dim D9 As System.Double  
Dim D10 As System.Double  
Dim D11 As System.Double  
Dim D12 As System.Double
```

```
instance.HoleWizard(Depth, EndType, Flip, Dir, HType, D1, D2, D3, D4, D5, D6, D7, D8, D9, D10,  
D11, D12)
```

C#

```
void HoleWizard(  
    System.double Depth,  
    System.short EndType,  
    System.bool Flip,
```

```

        System.bool Dir,
        System.int HType,
        System.double D1,
        System.double D2,
        System.double D3,
        System.double D4,
        System.double D5,
        System.double D6,
        System.double D7,
        System.double D8,
        System.double D9,
        System.double D10,
        System.double D11,
        System.double D12
    )

```

C++/CLI

```

void HoleWizard(
&    System.double Depth,
&    System.short EndType,
&    System.bool Flip,
&    System.bool Dir,
&    System.int HType,
&    System.double D1,
&    System.double D2,
&    System.double D3,
&    System.double D4,
&    System.double D5,
&    System.double D6,
&    System.double D7,
&    System.double D8,
&    System.double D9,
&    System.double D10,
&    System.double D11,
&    System.double D12
)

```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Depth

EndType

Flip

Dir

HType

D1

D2

D3

D4

D5

D6

D7

D8

D9

D10

D11

D12

Visual Basic for Applications (VBA) Syntax

See [ModelDoc::HoleWizard](#).

See Also

[IModelDoc Interface](#)
[IModelDoc Members](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

IActiveView Property (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : IActiveView Property (IModelDoc)

Obsolete. Superseded by [IModelDoc2::IActiveView](#).

NOTE: This property is a get-only property. Set is not implemented.

.NET Syntax

Visual Basic (Declaration)

```
ReadOnly Property IActiveView As ModelView
```

Visual Basic (Usage)



```
Dim instance As IModelDoc  
Dim value As ModelView  
  
value = instance.IActiveView
```

C#

```
ModelView IActiveView {get;}
```

C++/CLI

```
property ModelView^ IActiveView {  
    ModelView^ get();  
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Visual Basic for Applications (VBA) Syntax

See [ModelDoc::IActiveView](#).

See Also

[IModelDoc Interface](#)
[IModelDoc Members](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

IAddDiameterDimension2 Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : IAddDiameterDimension2 Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::IAddDiameterDimension2](#).

.NET Syntax

Visual Basic (Declaration)

```
Function IAddDiameterDimension2( _  
    ByVal X As System.Double, _  
    ByVal Y As System.Double, _  
    ByVal Z As System.Double _  
) As DisplayDimension
```

Visual Basic (Usage)



```

Dim instance As IModelDoc
Dim X As System.Double
Dim Y As System.Double
Dim Z As System.Double
Dim value As DisplayDimension

value = instance.IAddDiameterDimension2(X, Y, Z)

```

C#

```

DisplayDimension IAddDiameterDimension2(
    System.double X,
    System.double Y,
    System.double Z
)

```

C++/CLI

```

DisplayDimension^ IAddDiameterDimension2(
    & System.double X,
    & System.double Y,
    & System.double Z
)

```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

X

Y

Z

Visual Basic for Applications (VBA) Syntax

See [ModelDoc2.IAddDiameterDimension2](#).

See Also

[IModelDoc Interface](#)

[IModelDoc Members](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

IAddDimension2 Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : IAddDimension2 Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2.IAddDimension2](#).

.NET Syntax

Visual Basic (Declaration)

```

Function IAddDimension2( _
    ByVal X As System.Double, _
    ByVal Y As System.Double, _
    ByVal Z As System.Double _
) As DisplayDimension

```

Visual Basic (Usage)

```

Dim instance As IModelDoc
Dim X As System.Double
Dim Y As System.Double
Dim Z As System.Double
Dim value As DisplayDimension

```



```
value = instance.IAddDimension2(X, Y, Z)
```

C#

```
DisplayDimension IAddDimension2(  
    System.double X,  
    System.double Y,  
    System.double Z  
)
```

C++/CLI

```
DisplayDimension^ IAddDimension2(  
& System.double X,  
& System.double Y,  
& System.double Z  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

X

Y

Z

Visual Basic for Applications (VBA) Syntax

See [ModelDoc::IAddDimension2](#).

See Also

[IModelDoc Interface](#)
[IModelDoc Members](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

IAddHorizontalDimension2 Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : IAddHorizontalDimension2 Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::IAddHorizontalDimension2](#).

.NET Syntax

Visual Basic (Declaration)

```
Function IAddHorizontalDimension2( _  
    ByVal X As System.Double, _  
    ByVal Y As System.Double, _  
    ByVal Z As System.Double _  
) As DisplayDimension
```

Visual Basic (Usage)



```
Dim instance As IModelDoc  
Dim X As System.Double  
Dim Y As System.Double  
Dim Z As System.Double  
Dim value As DisplayDimension
```

```
value = instance.IAddHorizontalDimension2(X, Y, Z)
```

C#

```
DisplayDimension IAddHorizontalDimension2(  
    System.double X,  
    System.double Y,
```

```
        System.double Z
    )
```

C++/CLI

```
DisplayDimension^ IAddHorizontalDimension2(
&    System.double X,
&    System.double Y,
&    System.double Z
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

X

Y

Z

Visual Basic for Applications (VBA) Syntax

See [ModelDoc::IAddHorizontalDimension2](#).

See Also

[IModelDoc Interface](#)

[IModelDoc Members](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

IAddRadialDimension2 Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : IAddRadialDimension2 Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::IAddRadialDimension2](#).

.NET Syntax

Visual Basic (Declaration)

```
Function IAddRadialDimension2( _
    ByVal X As System.Double, _
    ByVal Y As System.Double, _
    ByVal Z As System.Double _
) As DisplayDimension
```

Visual Basic (Usage)



```
Dim instance As IModelDoc
Dim X As System.Double
Dim Y As System.Double
Dim Z As System.Double
Dim value As DisplayDimension
```

```
value = instance.IAddRadialDimension2(X, Y, Z)
```

C#

```
DisplayDimension IAddRadialDimension2(
    System.double X,
    System.double Y,
    System.double Z
)
```

C++/CLI

```
DisplayDimension^ IAddRadialDimension2(
&    System.double X,
&    System.double Y,
```

```
& System.double Z  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

X

Y

Z

Visual Basic for Applications (VBA) Syntax

See [ModelDoc::IAddRadialDimension2](#).

See Also

[IModelDoc Interface](#)

[IModelDoc Members](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

IAddVerticalDimension2 Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : IAddVerticalDimension2 Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::IAddVerticalDimension2](#).

.NET Syntax

Visual Basic (Declaration)

```
Function IAddVerticalDimension2( _  
    ByVal X As System.Double, _  
    ByVal Y As System.Double, _  
    ByVal Z As System.Double _  
) As DisplayDimension
```

Visual Basic (Usage)



```
Dim instance As IModelDoc  
Dim X As System.Double  
Dim Y As System.Double  
Dim Z As System.Double  
Dim value As DisplayDimension
```

```
value = instance.IAddVerticalDimension2(X, Y, Z)
```

C#

```
DisplayDimension IAddVerticalDimension2(  
    System.double X,  
    System.double Y,  
    System.double Z  
)
```

C++/CLI

```
DisplayDimension^ IAddVerticalDimension2(  
& System.double X,  
& System.double Y,  
& System.double Z  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

X

Y

Visual Basic for Applications (VBA) Syntax

See [ModelDoc2::AddVerticalDimension2](#).

See Also

[IModelDoc Interface](#)
[IModelDoc Members](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

ICreateArc Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : ICreateArc Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::ICreateArc](#).

.NET Syntax

Visual Basic (Declaration)

```
Sub ICreateArc( _
    ByRef P1 As System.Double, _
    ByRef P2 As System.Double, _
    ByRef P3 As System.Double, _
    ByVal Dir As System.Short _
)
```

Visual Basic (Usage)



```
Dim instance As IModelDoc
Dim P1 As System.Double
Dim P2 As System.Double
Dim P3 As System.Double
Dim Dir As System.Short

instance.ICreateArc(P1, P2, P3, Dir)
```

C#

```
void ICreateArc(
    ref System.double P1,
    ref System.double P2,
    ref System.double P3,
    System.short Dir
)
```

C++/CLI

```
void ICreateArc(
    & System.double% P1,
    & System.double% P2,
    & System.double% P3,
    & System.short Dir
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

P1

P2

P3

Dir

Visual Basic for Applications (VBA) Syntax

See [ModelDoc2::ICreateArc](#).

See Also

[IModelDoc Interface](#)
[IModelDoc Members](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

ICreateArc2 Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : ICreateArc2 Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::ICreateArc2](#).

.NET Syntax

Visual Basic (Declaration)

```
Function ICreateArc2( _  
    ByVal XC As System.Double, _  
    ByVal YC As System.Double, _  
    ByVal Zc As System.Double, _  
    ByVal Xp1 As System.Double, _  
    ByVal Yp1 As System.Double, _  
    ByVal Zp1 As System.Double, _  
    ByVal Xp2 As System.Double, _  
    ByVal Yp2 As System.Double, _  
    ByVal Zp2 As System.Double, _  
    ByVal Direction As System.Short _  
) As SketchSegment
```

Visual Basic (Usage)



```
Dim instance As IModelDoc  
Dim XC As System.Double  
Dim YC As System.Double  
Dim Zc As System.Double  
Dim Xp1 As System.Double  
Dim Yp1 As System.Double  
Dim Zp1 As System.Double  
Dim Xp2 As System.Double  
Dim Yp2 As System.Double  
Dim Zp2 As System.Double  
Dim Direction As System.Short  
Dim value As SketchSegment
```

```
value = instance.ICreateArc2(XC, YC, Zc, Xp1, Yp1, Zp1, Xp2, Yp2, Zp2, Direction)
```

C#

```
SketchSegment ICreateArc2(  
    System.double XC,  
    System.double YC,  
    System.double Zc,  
    System.double Xp1,  
    System.double Yp1,  
    System.double Zp1,  
    System.double Xp2,  
    System.double Yp2,  
    System.double Zp2,  
    System.short Direction  
)
```

C++/CLI

```

SketchSegment^ ICreateArc2(
& System.double XC,
& System.double YC,
& System.double Zc,
& System.double Xp1,
& System.double Yp1,
& System.double Zp1,
& System.double Xp2,
& System.double Yp2,
& System.double Zp2,
& System.short Direction
)

```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

XC

YC

Zc

Xp1

Yp1

Zp1

Xp2

Yp2

Zp2

Direction

Visual Basic for Applications (VBA) Syntax

See [ModelDoc2::ICreateArc2](#).

See Also

[IModelDoc Interface](#)
[IModelDoc Members](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

ICreateCenterLine Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : ICreateCenterLine Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::ICreateCenterLine](#).

.NET Syntax

Visual Basic (Declaration)

```

Sub ICreateCenterLine( _
    ByRef P1 As System.Double, _
    ByRef P2 As System.Double _
)

```

Visual Basic (Usage)



```

Dim instance As IModelDoc
Dim P1 As System.Double
Dim P2 As System.Double

```

```
instance.ICreateCenterLine(P1, P2)
```

C#

```

void ICreateCenterLine(
    ref System.double P1,

```

```
    ref System.double P2
)
```

C++/CLI

```
void ICreateCenterLine(
&    System.double% P1,
&    System.double% P2
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

P1

P2

Visual Basic for Applications (VBA) Syntax

See [ModelDoc2::ICreateCenterLine](#).

See Also

[IModelDoc Interface](#)
[IModelDoc Members](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

ICreateCircle2 Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : ICreateCircle2 Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::ICreateCircle2](#).

.NET Syntax

Visual Basic (Declaration)

```
Function ICreateCircle2( _
    ByVal XC As System.Double, _
    ByVal YC As System.Double, _
    ByVal Zc As System.Double, _
    ByVal Xp As System.Double, _
    ByVal Yp As System.Double, _
    ByVal Zp As System.Double _
) As SketchSegment
```

Visual Basic (Usage)



```
Dim instance As IModelDoc
Dim XC As System.Double
Dim YC As System.Double
Dim Zc As System.Double
Dim Xp As System.Double
Dim Yp As System.Double
Dim Zp As System.Double
Dim value As SketchSegment
```

```
value = instance.ICreateCircle2(XC, YC, Zc, Xp, Yp, Zp)
```

C#

```
SketchSegment ICreateCircle2(
    System.double XC,
    System.double YC,
    System.double Zc,
    System.double Xp,
    System.double Yp,
```

```
        System.double Zp
    )
```

C++/CLI

```
SketchSegment^ ICreateCircle2(
&    System.double XC,
&    System.double YC,
&    System.double Zc,
&    System.double Xp,
&    System.double Yp,
&    System.double Zp
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

XC

YC

Zc

Xp

Yp

Zp

Visual Basic for Applications (VBA) Syntax

See [ModelDoc::ICreateCircle2](#).

See Also

[IModelDoc Interface](#)
[IModelDoc Members](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

ICreateCircleByRadius Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : ICreateCircleByRadius Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::ICreateCircleByRadius](#).

.NET Syntax

Visual Basic (Declaration)

```
Sub ICreateCircleByRadius( _
    ByRef P1 As System.Double, _
    ByVal Radius As System.Double _
)
```

Visual Basic (Usage)



```
Dim instance As IModelDoc
Dim P1 As System.Double
Dim Radius As System.Double
```

```
instance.ICreateCircleByRadius(P1, Radius)
```

C#

```
void ICreateCircleByRadius(
    ref System.double P1,
    System.double Radius
)
```

C++/CLI

```
void ICreateCircleByRadius(  
& System.double% P1,  
& System.double Radius  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

P1

Radius

Visual Basic for Applications (VBA) Syntax

See [ModelDoc::ICreateCircleByRadius](#).

See Also

[IModelDoc Interface](#)
[IModelDoc Members](#)