

SOLIDWORKS API (.NET VBA C#) — Reference (171/337): IModelDoc (part 7 of 13)

SOLIDWORKS API Documentation (converted from CHM)

IModelDoc (part 7 of 13) (Type)

SOLIDWORKS API Help

[Send comments](#) on this topic.

ICreateCircleByRadius2 Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : ICreateCircleByRadius2 Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::ICreateCircleByRadius2](#).

.NET Syntax

Visual Basic (Declaration)

```
Function ICreateCircleByRadius2( _  
    ByVal XC As System.Double, _  
    ByVal YC As System.Double, _  
    ByVal Zc As System.Double, _  
    ByVal Radius As System.Double _  
) As SketchSegment
```

Visual Basic (Usage)



```
Dim instance As IModelDoc  
Dim XC As System.Double  
Dim YC As System.Double  
Dim Zc As System.Double  
Dim Radius As System.Double  
Dim value As SketchSegment  
  
value = instance.ICreateCircleByRadius2(XC, YC, Zc, Radius)
```

C#

```
SketchSegment ICreateCircleByRadius2(  
    System.double XC,  
    System.double YC,  
    System.double Zc,  
    System.double Radius  
)
```

C++/CLI

```
SketchSegment^ ICreateCircleByRadius2(  
& System.double XC,  
& System.double YC,  
& System.double Zc,  
& System.double Radius  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

XC

YC

Zc

Radius

Visual Basic for Applications (VBA) Syntax

See [ModelDoc::ICreateCircleByRadius2](#).

See Also

[IModelDoc Interface](#)
[IModelDoc Members](#)

ICreateClippedSplines Method (IModelDoc)

[See Also](#)[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : ICreateClippedSplines Method (IModelDoc)Obsolete. Superseded by [IModelDoc2::ICreateClippedSplines](#).

.NET Syntax

Visual Basic (Declaration)

```
Function ICreateClippedSplines( _
    ByRef PropArray As System.Integer, _
    ByRef KnotsArray As System.Double, _
    ByRef CntrlPntCoordArray As System.Double, _
    ByVal X1 As System.Double, _
    ByVal Y1 As System.Double, _
    ByVal X2 As System.Double, _
    ByVal Y2 As System.Double _
) As EnumSketchSegments
```

Visual Basic (Usage)



```
Dim instance As IModelDoc
Dim PropArray As System.Integer
Dim KnotsArray As System.Double
Dim CntrlPntCoordArray As System.Double
Dim X1 As System.Double
Dim Y1 As System.Double
Dim X2 As System.Double
Dim Y2 As System.Double
Dim value As EnumSketchSegments
```

```
value = instance.ICreateClippedSplines(PropArray, KnotsArray, CntrlPntCoordArray, X1, Y1, X2, Y2)
```

C#

```
EnumSketchSegments ICreateClippedSplines(
    ref System.int PropArray,
    ref System.double KnotsArray,
    ref System.double CntrlPntCoordArray,
    System.double X1,
    System.double Y1,
    System.double X2,
    System.double Y2
)
```

C++/CLI

```
EnumSketchSegments^ ICreateClippedSplines(
    & System.int% PropArray,
    & System.double% KnotsArray,
    & System.double% CntrlPntCoordArray,
    & System.double X1,
    & System.double Y1,
    & System.double X2,
    & System.double Y2
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).**Parameters***PropArray**KnotsArray**CntrlPntCoordArray**X1**Y1**X2*

Visual Basic for Applications (VBA) Syntax

See [ModelDoc::ICreateClippedSplines](#).

See Also

[IModelDoc Interface](#)
[IModelDoc Members](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

ICreateEllipse Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : ICreateEllipse Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::ICreateEllipse](#).

.NET Syntax

Visual Basic (Declaration)

```
Sub ICreateEllipse( _
    ByRef Center As System.Double, _
    ByRef Major As System.Double, _
    ByRef Minor As System.Double _
)
```

Visual Basic (Usage)



```
Dim instance As IModelDoc
Dim Center As System.Double
Dim Major As System.Double
Dim Minor As System.Double
```

```
instance.ICreateEllipse(Center, Major, Minor)
```

C#

```
void ICreateEllipse(
    ref System.double Center,
    ref System.double Major,
    ref System.double Minor
)
```

C++/CLI

```
void ICreateEllipse(
    & System.double% Center,
    & System.double% Major,
    & System.double% Minor
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Center

Major

Minor

Visual Basic for Applications (VBA) Syntax

See [ModelDoc::ICreateEllipse](#).

See Also

[IModelDoc Interface](#)
[IModelDoc Members](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

ICreateEllipse2 Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : ICreateEllipse2 Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::ICreateEllipse2](#).

.NET Syntax

Visual Basic (Declaration)

```
Function ICreateEllipse2( _  
    ByVal CenterX As System.Double, _  
    ByVal CenterY As System.Double, _  
    ByVal CenterZ As System.Double, _  
    ByVal MajorX As System.Double, _  
    ByVal MajorY As System.Double, _  
    ByVal MajorZ As System.Double, _  
    ByVal MinorX As System.Double, _  
    ByVal MinorY As System.Double, _  
    ByVal MinorZ As System.Double _  
) As SketchSegment
```

Visual Basic (Usage)



```
Dim instance As IModelDoc  
Dim CenterX As System.Double  
Dim CenterY As System.Double  
Dim CenterZ As System.Double  
Dim MajorX As System.Double  
Dim MajorY As System.Double  
Dim MajorZ As System.Double  
Dim MinorX As System.Double  
Dim MinorY As System.Double  
Dim MinorZ As System.Double  
Dim value As SketchSegment
```

```
value = instance.ICreateEllipse2(CenterX, CenterY, CenterZ, MajorX, MajorY, MajorZ, MinorX,  
MinorY, MinorZ)
```

C#

```
SketchSegment ICreateEllipse2(  
    System.double CenterX,  
    System.double CenterY,  
    System.double CenterZ,  
    System.double MajorX,  
    System.double MajorY,  
    System.double MajorZ,  
    System.double MinorX,  
    System.double MinorY,  
    System.double MinorZ  
)
```

C++/CLI

```
SketchSegment^ ICreateEllipse2(  
& System.double CenterX,  
& System.double CenterY,  
& System.double CenterZ,  
& System.double MajorX,  
& System.double MajorY,  
& System.double MajorZ,  
& System.double MinorX,
```

```
& System.double MinorY,  
& System.double MinorZ  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

CenterX

CenterY

CenterZ

MajorX

MajorY

MajorZ

MinorX

MinorY

MinorZ

Visual Basic for Applications (VBA) Syntax

See [ModelDoc2::ICreateEllipse2](#).

See Also

[IModelDoc Interface](#)

[IModelDoc Members](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

ICreateEllipticalArc2 Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : ICreateEllipticalArc2 Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::ICreateEllipticalArc2](#).

.NET Syntax

Visual Basic (Declaration)

```
Function ICreateEllipticalArc2( _  
    ByVal CenterX As System.Double, _  
    ByVal CenterY As System.Double, _  
    ByVal CenterZ As System.Double, _  
    ByVal MajorX As System.Double, _  
    ByVal MajorY As System.Double, _  
    ByVal MajorZ As System.Double, _  
    ByVal MinorX As System.Double, _  
    ByVal MinorY As System.Double, _  
    ByVal MinorZ As System.Double, _  
    ByVal StartX As System.Double, _  
    ByVal StartY As System.Double, _  
    ByVal StartZ As System.Double, _  
    ByVal EndX As System.Double, _  
    ByVal EndY As System.Double, _  
    ByVal EndZ As System.Double _  
) As SketchSegment
```

Visual Basic (Usage)

```
Dim instance As IModelDoc  
Dim CenterX As System.Double  
Dim CenterY As System.Double  
Dim CenterZ As System.Double  
Dim MajorX As System.Double  
Dim MajorY As System.Double  
Dim MajorZ As System.Double  
Dim MinorX As System.Double
```

 Copy Code

```

Dim MinorY As System.Double
Dim MinorZ As System.Double
Dim StartX As System.Double
Dim StartY As System.Double
Dim StartZ As System.Double
Dim EndX As System.Double
Dim EndY As System.Double
Dim EndZ As System.Double
Dim value As SketchSegment

```

```

value = instance.ICreateEllipticalArc2(CenterX, CenterY, CenterZ, MajorX, MajorY, MajorZ, MinorX,
MinorY, MinorZ, StartX, StartY, StartZ, EndX, EndY, EndZ)

```

C#

```

SketchSegment ICreateEllipticalArc2(
    System.double CenterX,
    System.double CenterY,
    System.double CenterZ,
    System.double MajorX,
    System.double MajorY,
    System.double MajorZ,
    System.double MinorX,
    System.double MinorY,
    System.double MinorZ,
    System.double StartX,
    System.double StartY,
    System.double StartZ,
    System.double EndX,
    System.double EndY,
    System.double EndZ
)

```

C++/CLI

```

SketchSegment^ ICreateEllipticalArc2(
    & System.double CenterX,
    & System.double CenterY,
    & System.double CenterZ,
    & System.double MajorX,
    & System.double MajorY,
    & System.double MajorZ,
    & System.double MinorX,
    & System.double MinorY,
    & System.double MinorZ,
    & System.double StartX,
    & System.double StartY,
    & System.double StartZ,
    & System.double EndX,
    & System.double EndY,
    & System.double EndZ
)

```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

CenterX

CenterY

CenterZ

MajorX

MajorY

MajorZ

MinorX

MinorY

MinorZ

StartX

StartY

StartZ

EndX

EndY

EndZ

Visual Basic for Applications (VBA) Syntax

See [ModelDoc::ICreateEllipticalArc2](#).

See Also

[IModelDoc Interface](#)
[IModelDoc Members](#)

SOLIDWORKS API Help

[Send comments on this topic.](#)

ICreateEllipticalArcByCenter Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : ICreateEllipticalArcByCenter Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::ICreateEllipticalArcByCenter](#).

.NET Syntax

Visual Basic (Declaration)

```
Sub ICreateEllipticalArcByCenter( _  
    ByRef Center As System.Double, _  
    ByRef Major As System.Double, _  
    ByRef Minor As System.Double, _  
    ByRef Start As System.Double, _  
    ByRef End As System.Double _  
)
```

Visual Basic (Usage)



```
Dim instance As IModelDoc  
Dim Center As System.Double  
Dim Major As System.Double  
Dim Minor As System.Double  
Dim Start As System.Double  
Dim End As System.Double  
  
instance.ICreateEllipticalArcByCenter(Center, Major, Minor, Start, End)
```

C#

```
void ICreateEllipticalArcByCenter(  
    ref System.double Center,  
    ref System.double Major,  
    ref System.double Minor,  
    ref System.double Start,  
    ref System.double End  
)
```

C++/CLI

```
void ICreateEllipticalArcByCenter(  
& System.double% Center,  
& System.double% Major,  
& System.double% Minor,  
& System.double% Start,  
& System.double% End  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Center
Major
Minor
Start
End

Visual Basic for Applications (VBA) Syntax

See [ModelDoc2::ICreateEllipticalArcByCenter](#).

See Also

[IModelDoc Interface](#)
[IModelDoc Members](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

ICreateFeatureMgrView Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : ICreateFeatureMgrView Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::ICreateFeatureMgrView](#).

.NET Syntax

Visual Basic (Declaration)

```
Function ICreateFeatureMgrView( _  
    ByRef Bitmap As System.Integer _  
) As FeatMgrView
```

Visual Basic (Usage)



```
Dim instance As IModelDoc  
Dim Bitmap As System.Integer  
Dim value As FeatMgrView  
  
value = instance.ICreateFeatureMgrView(Bitmap)
```

C#

```
FeatMgrView ICreateFeatureMgrView(  
    ref System.int Bitmap  
)
```

C++/CLI

```
FeatMgrView^ ICreateFeatureMgrView(  
& System.int% Bitmap  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Bitmap

Visual Basic for Applications (VBA) Syntax

See [ModelDoc2::ICreateFeatureMgrView](#).

See Also

[IModelDoc Interface](#)
[IModelDoc Members](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

ICreateFeatureMgrView2 Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : ICreateFeatureMgrView2 Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::ICreateFeatureMgrView2](#).

.NET Syntax

Visual Basic (Declaration)

```
Function ICreateFeatureMgrView2( _  
    ByRef Bitmap As System.Integer, _  
    ByVal ToolTip As System.String _  
) As FeatMgrView
```

Visual Basic (Usage)



```
Dim instance As IModelDoc  
Dim Bitmap As System.Integer  
Dim ToolTip As System.String  
Dim value As FeatMgrView
```

```
value = instance.ICreateFeatureMgrView2(Bitmap, ToolTip)
```

C#

```
FeatMgrView ICreateFeatureMgrView2(  
    ref System.int Bitmap,  
    System.string ToolTip  
)
```

C++/CLI

```
FeatMgrView^ ICreateFeatureMgrView2(  
& System.int% Bitmap,  
& System.String^ ToolTip  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Bitmap

ToolTip

Visual Basic for Applications (VBA) Syntax

See [ModelDoc::ICreateFeatureMgrView2](#).

See Also

[IModelDoc Interface](#)
[IModelDoc Members](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

ICreateFeatureMgrView3 Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : ICreateFeatureMgrView3 Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::ICreateFeatureMgrView3](#).

.NET Syntax

Visual Basic (Declaration)

```
Function ICreateFeatureMgrView3( _  
    ByRef Bitmap As System.Integer, _
```

```
ByVal ToolTip As System.String, _  
ByVal WhichPane As System.Integer _  
) As FeatMgrView
```

Visual Basic (Usage)



```
Dim instance As IModelDoc  
Dim Bitmap As System.Integer  
Dim ToolTip As System.String  
Dim WhichPane As System.Integer  
Dim value As FeatMgrView  
  
value = instance.ICreateFeatureMgrView3(Bitmap, ToolTip, WhichPane)
```

C#

```
FeatMgrView ICreateFeatureMgrView3(  
    ref System.int Bitmap,  
    System.string ToolTip,  
    System.int WhichPane  
)
```

C++/CLI

```
FeatMgrView^ ICreateFeatureMgrView3(  
& System.int% Bitmap,  
& System.String^ ToolTip,  
& System.int WhichPane  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Bitmap

ToolTip

WhichPane

Visual Basic for Applications (VBA) Syntax

See [ModelDoc::ICreateFeatureMgrView3](#).

See Also

[IModelDoc Interface](#)
[IModelDoc Members](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

ICreateLine Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : ICreateLine Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::ICreateLine](#).

.NET Syntax

Visual Basic (Declaration)

```
Sub ICreateLine( _  
    ByRef P1 As System.Double, _  
    ByRef P2 As System.Double _  
)
```

Visual Basic (Usage)



```
Dim instance As IModelDoc  
Dim P1 As System.Double
```

```
Dim P2 As System.Double  
  
instance.ICreateLine(P1, P2)
```

C#

```
void ICreateLine(  
    ref System.double P1,  
    ref System.double P2  
)
```

C++/CLI

```
void ICreateLine(  
& System.double% P1,  
& System.double% P2  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

P1

P2

Visual Basic for Applications (VBA) Syntax

See [ModelDoc::ICreateLine](#).

See Also

[IModelDoc Interface](#)
[IModelDoc Members](#)

SOLIDWORKS API Help

[Send comments on this topic.](#)

ICreateLine2 Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : ICreateLine2 Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::ICreateLine2](#).

.NET Syntax

Visual Basic (Declaration)

```
Function ICreateLine2(  
    ByVal P1x As System.Double, _  
    ByVal P1y As System.Double, _  
    ByVal P1z As System.Double, _  
    ByVal P2x As System.Double, _  
    ByVal P2y As System.Double, _  
    ByVal P2z As System.Double _  
) As SketchSegment
```

Visual Basic (Usage)



```
Dim instance As IModelDoc  
Dim P1x As System.Double  
Dim P1y As System.Double  
Dim P1z As System.Double  
Dim P2x As System.Double  
Dim P2y As System.Double  
Dim P2z As System.Double  
Dim value As SketchSegment
```

```
value = instance.ICreateLine2(P1x, P1y, P1z, P2x, P2y, P2z)
```

C#

```
SketchSegment ICreateLine2(  
    System.double P1x,  
    System.double P1y,  
    System.double P1z,  
    System.double P2x,  
    System.double P2y,  
    System.double P2z  
)
```

C++/CLI

```
SketchSegment^ ICreateLine2(  
& System.double P1x,  
& System.double P1y,  
& System.double P1z,  
& System.double P2x,  
& System.double P2y,  
& System.double P2z  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

P1x

P1y

P1z

P2x

P2y

P2z

Visual Basic for Applications (VBA) Syntax

See [ModelDoc::ICreateLine2](#).

See Also

[IModelDoc Interface](#)

[IModelDoc Members](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

ICreatePlaneAtAngle2 Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : ICreatePlaneAtAngle2 Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::ICreatePlaneAtAngle2](#).

.NET Syntax

Visual Basic (Declaration)

```
Function ICreatePlaneAtAngle2( _  
    ByVal Val As System.Double, _  
    ByVal FlipDir As System.Boolean _  
) As RefPlane
```

Visual Basic (Usage)



```
Dim instance As IModelDoc  
Dim Val As System.Double  
Dim FlipDir As System.Boolean  
Dim value As RefPlane
```

```
value = instance.ICreatePlaneAtAngle2(Val, FlipDir)
```

C#

```
RefPlane ICreatePlaneAtAngle2(  
    System.double Val,  
    System.bool FlipDir  
)
```

C++/CLI

```
RefPlane^ ICreatePlaneAtAngle2(  
& System.double Val,  
& System.bool FlipDir  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Val

FlipDir

Visual Basic for Applications (VBA) Syntax

See [ModelDoc::ICreatePlaneAtAngle2](#).

See Also

[IModelDoc Interface](#)
[IModelDoc Members](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

ICreatePlaneAtOffset2 Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : ICreatePlaneAtOffset2 Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::ICreatePlaneAtOffset2](#).

.NET Syntax

Visual Basic (Declaration)

```
Function ICreatePlaneAtOffset2( _  
    ByVal Val As System.Double, _  
    ByVal FlipDir As System.Boolean _  
) As RefPlane
```

Visual Basic (Usage)



```
Dim instance As IModelDoc  
Dim Val As System.Double  
Dim FlipDir As System.Boolean  
Dim value As RefPlane
```

```
value = instance.ICreatePlaneAtOffset2(Val, FlipDir)
```

C#

```
RefPlane ICreatePlaneAtOffset2(  
    System.double Val,  
    System.bool FlipDir  
)
```

C++/CLI

```
RefPlane^ ICreatePlaneAtOffset2(  
& System.double Val,  
& System.bool FlipDir  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Val

FlipDir

Visual Basic for Applications (VBA) Syntax

See [ModelDoc::ICreatePlaneAtOffset2](#).

See Also

[IModelDoc Interface](#)
[IModelDoc Members](#)

SOLIDWORKS API Help

[Send comments on this topic.](#)

ICreatePlaneAtSurface2 Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : ICreatePlaneAtSurface2 Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::ICreatePlaneAtSurface2](#).

.NET Syntax

Visual Basic (Declaration)

```
Function ICreatePlaneAtSurface2( _  
    ByVal InterIndex As System.Integer, _  
    ByVal ProjOpt As System.Boolean, _  
    ByVal ReverseDir As System.Boolean, _  
    ByVal NormalPlane As System.Boolean, _  
    ByVal Angle As System.Double _  
) As RefPlane
```

Visual Basic (Usage)



```
Dim instance As IModelDoc  
Dim InterIndex As System.Integer  
Dim ProjOpt As System.Boolean  
Dim ReverseDir As System.Boolean  
Dim NormalPlane As System.Boolean  
Dim Angle As System.Double  
Dim value As RefPlane
```

```
value = instance.ICreatePlaneAtSurface2(InterIndex, ProjOpt, ReverseDir, NormalPlane, Angle)
```

C#

```
RefPlane ICreatePlaneAtSurface2(  
    System.int InterIndex,  
    System.bool ProjOpt,  
    System.bool ReverseDir,  
    System.bool NormalPlane,  
    System.double Angle  
)
```

C++/CLI

```
RefPlane^ ICreatePlaneAtSurface2(  
& System.int InterIndex,  
& System.bool ProjOpt,  
& System.bool ReverseDir,  
& System.bool NormalPlane,  
& System.double Angle  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

InterIndex

ProjOpt

ReverseDir

NormalPlane

Angle

Visual Basic for Applications (VBA) Syntax

See [ModelDoc::ICreatePlaneAtSurface2](#).

See Also

[IModelDoc Interface](#)
[IModelDoc Members](#)

SOLIDWORKS API Help

[Send comments on this topic.](#)

ICreatePlaneFixed Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : ICreatePlaneFixed Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::ICreatePlaneFixed](#).

.NET Syntax

Visual Basic (Declaration)

```
Sub ICreatePlaneFixed( _  
    ByRef P1 As System.Double, _  
    ByRef P2 As System.Double, _  
    ByRef P3 As System.Double, _  
    ByVal UseGlobal As System.Boolean _  
)
```

Visual Basic (Usage)



```
Dim instance As IModelDoc  
Dim P1 As System.Double  
Dim P2 As System.Double  
Dim P3 As System.Double  
Dim UseGlobal As System.Boolean  
  
instance.ICreatePlaneFixed(P1, P2, P3, UseGlobal)
```

C#

```
void ICreatePlaneFixed(  
    ref System.double P1,  
    ref System.double P2,  
    ref System.double P3,  
    System.bool UseGlobal  
)
```

C++/CLI

```
void ICreatePlaneFixed(  
& System.double% P1,  
& System.double% P2,  
& System.double% P3,  
& System.bool UseGlobal  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

P1

P2

P3

UseGlobal

Visual Basic for Applications (VBA) Syntax

See [ModelDoc::ICreatePlaneFixed](#).

See Also

[IModelDoc Interface](#)
[IModelDoc Members](#)

SOLIDWORKS API Help

[Send comments on this topic.](#)

ICreatePlanePerCurveAndPassPoint2 Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : ICreatePlanePerCurveAndPassPoint2 Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::ICreatePlanePerCurveAndPassPoint2](#).

.NET Syntax

Visual Basic (Declaration)

```
Function ICreatePlanePerCurveAndPassPoint2( _  
    ByVal OrigAtCurve As System.Boolean _  
) As RefPlane
```

Visual Basic (Usage)



```
Dim instance As IModelDoc  
Dim OrigAtCurve As System.Boolean  
Dim value As RefPlane  
  
value = instance.ICreatePlanePerCurveAndPassPoint2(OrigAtCurve)
```

C#

```
RefPlane ICreatePlanePerCurveAndPassPoint2(  
    System.bool OrigAtCurve  
)
```

C++/CLI

```
RefPlane^ ICreatePlanePerCurveAndPassPoint2(  
& System.bool OrigAtCurve  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

OrigAtCurve

Visual Basic for Applications (VBA) Syntax

See [ModelDoc::ICreatePlanePerCurveAndPassPoint2](#).

See Also

[IModelDoc Interface](#)
[IModelDoc Members](#)

SOLIDWORKS API Help

[Send comments on this topic.](#)

ICreatePlaneThru3Points2 Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : ICreatePlaneThru3Points2 Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::ICreatePlaneThru3Points2](#).

.NET Syntax

Visual Basic (Declaration)

```
Function ICreatePlaneThru3Points2() As RefPlane
```

Visual Basic (Usage)



```
Dim instance As IModelDoc  
Dim value As RefPlane  
  
value = instance.ICreatePlaneThru3Points2()
```

C#

```
RefPlane ICreatePlaneThru3Points2()
```

C++/CLI

```
RefPlane^ ICreatePlaneThru3Points2();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Visual Basic for Applications (VBA) Syntax

See [ModelDoc::ICreatePlaneThru3Points2](#).

See Also

[IModelDoc Interface](#)
[IModelDoc Members](#)

SOLIDWORKS API Help

[Send comments on this topic.](#)

ICreatePoint2 Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : ICreatePoint2 Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::ICreatePoint2](#).

.NET Syntax

Visual Basic (Declaration)

```
Function ICreatePoint2( _  
    ByVal PointX As System.Double, _  
    ByVal PointY As System.Double, _  
    ByVal PointZ As System.Double _  
) As SketchPoint
```

Visual Basic (Usage)



```
Dim instance As IModelDoc  
Dim PointX As System.Double  
Dim PointY As System.Double  
Dim PointZ As System.Double  
Dim value As SketchPoint  
  
value = instance.ICreatePoint2(PointX, PointY, PointZ)
```

C#

```
SketchPoint ICreatePoint2(  
    System.double PointX,  
    System.double PointY,  
    System.double PointZ  
)
```

C++/CLI

```
SketchPoint^ ICreatePoint2(  
&    System.double PointX,  
&    System.double PointY,  
&    System.double PointZ  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

PointX

PointY

PointZ

Visual Basic for Applications (VBA) Syntax

See [ModelDoc::ICreatePoint2](#).

See Also

[IModelDoc Interface](#)
[IModelDoc Members](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

ICreateSpline Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : ICreateSpline Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::ICreateSpline](#).

.NET Syntax

Visual Basic (Declaration)

```
Function ICreateSpline( _  
    ByVal PointCount As System.Integer, _  
    ByRef PointData As System.Double _  
) As SketchSegment
```

Visual Basic (Usage)

```
Dim instance As IModelDoc  
Dim PointCount As System.Integer  
Dim PointData As System.Double  
Dim value As SketchSegment
```

```
value = instance.ICreateSpline(PointCount, PointData)
```

C#

```
SketchSegment ICreateSpline(  
    System.int PointCount,  
    ref System.double PointData  
)
```

C++/CLI

```
SketchSegment^ ICreateSpline(  
&    System.int PointCount,
```



```
& System.double% PointData
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

PointCount

PointData

Visual Basic for Applications (VBA) Syntax

See [ModelDoc2::ICreateSpline](#).

See Also

[IModelDoc Interface](#)
[IModelDoc Members](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

ICreateSplineByEqnParams Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : ICreateSplineByEqnParams Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::ICreateSplineByEqnParams](#).

.NET Syntax

Visual Basic (Declaration)

```
Function ICreateSplineByEqnParams( _  
    ByRef PropArray As System.Integer, _  
    ByRef KnotsArray As System.Double, _  
    ByRef CntrlPntCoordArray As System.Double _  
    ) As SketchSegment
```

Visual Basic (Usage)



```
Dim instance As IModelDoc  
Dim PropArray As System.Integer  
Dim KnotsArray As System.Double  
Dim CntrlPntCoordArray As System.Double  
Dim value As SketchSegment  
  
value = instance.ICreateSplineByEqnParams(PropArray, KnotsArray, CntrlPntCoordArray)
```

C#

```
SketchSegment ICreateSplineByEqnParams(  
    ref System.int PropArray,  
    ref System.double KnotsArray,  
    ref System.double CntrlPntCoordArray  
)
```

C++/CLI

```
SketchSegment^ ICreateSplineByEqnParams(  
& System.int% PropArray,  
& System.double% KnotsArray,  
& System.double% CntrlPntCoordArray  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

PropArray

KnotsArray

CntrlPntCoordArray

Visual Basic for Applications (VBA) Syntax

See [ModelDoc::ICreateSplinesByEqnParams](#).

See Also

[IModelDoc Interface](#)
[IModelDoc Members](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

ICreateSplinesByEqnParams Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : ICreateSplinesByEqnParams Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::ICreateSplinesByEqnParams](#).

.NET Syntax

Visual Basic (Declaration)

```
Function ICreateSplinesByEqnParams( _  
    ByRef PropArray As System.Integer, _  
    ByRef KnotsArray As System.Double, _  
    ByRef CntrlPntCoordArray As System.Double _  
    ) As EnumSketchSegments
```

Visual Basic (Usage)



```
Dim instance As IModelDoc  
Dim PropArray As System.Integer  
Dim KnotsArray As System.Double  
Dim CntrlPntCoordArray As System.Double  
Dim value As EnumSketchSegments  
  
value = instance.ICreateSplinesByEqnParams(PropArray, KnotsArray, CntrlPntCoordArray)
```

C#

```
EnumSketchSegments ICreateSplinesByEqnParams(  
    ref System.int PropArray,  
    ref System.double KnotsArray,  
    ref System.double CntrlPntCoordArray  
)
```

C++/CLI

```
EnumSketchSegments^ ICreateSplinesByEqnParams(  
& System.int% PropArray,  
& System.double% KnotsArray,  
& System.double% CntrlPntCoordArray  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

PropArray

KnotsArray

CntrlPntCoordArray

Visual Basic for Applications (VBA) Syntax

See [ModelDoc::ICreateSplinesByEqnParams](#).

See Also

[IModelDoc Interface](#)
[IModelDoc Members](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

IFeatureByPositionReverse Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : IFeatureByPositionReverse Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::IFeatureByPositionReverse](#).

.NET Syntax

Visual Basic (Declaration)

```
Function IFeatureByPositionReverse( _  
    ByVal Num As System.Integer _  
) As Feature
```

Visual Basic (Usage)



```
Dim instance As IModelDoc  
Dim Num As System.Integer  
Dim value As Feature
```

```
value = instance.IFeatureByPositionReverse(Num)
```

C#

```
Feature IFeatureByPositionReverse(  
    System.int Num  
)
```

C++/CLI

```
Feature^ IFeatureByPositionReverse(  
& System.int Num  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Num

Visual Basic for Applications (VBA) Syntax

See [ModelDoc::IFeatureByPositionReverse](#).

See Also

[IModelDoc Interface](#)
[IModelDoc Members](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

IFeatureFillet2 Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : IFeatureFillet2 Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::IFeatureFillet2](#).

.NET Syntax

Visual Basic (Declaration)

```

Function IFeatureFillet2( _
    ByVal R1 As System.Double, _
    ByVal Propagate As System.Boolean, _
    ByVal Ftyp As System.Boolean, _
    ByVal VarRadTyp As System.Boolean, _
    ByVal OverflowType As System.Integer, _
    ByVal NRadii As System.Integer, _
    ByRef Radii As System.Double _
) As System.Integer

```

Visual Basic (Usage)



```

Dim instance As IModelDoc
Dim R1 As System.Double
Dim Propagate As System.Boolean
Dim Ftyp As System.Boolean
Dim VarRadTyp As System.Boolean
Dim OverflowType As System.Integer
Dim NRadii As System.Integer
Dim Radii As System.Double
Dim value As System.Integer

```

```
value = instance.IFeatureFillet2(R1, Propagate, Ftyp, VarRadTyp, OverflowType, NRadii, Radii)
```

C#

```

System.int IFeatureFillet2(
    System.double R1,
    System.bool Propagate,
    System.bool Ftyp,
    System.bool VarRadTyp,
    System.int OverflowType,
    System.int NRadii,
    ref System.double Radii
)

```

C++/CLI

```

System.int IFeatureFillet2(
    & System.double R1,
    & System.bool Propagate,
    & System.bool Ftyp,
    & System.bool VarRadTyp,
    & System.int OverflowType,
    & System.int NRadii,
    & System.double% Radii
)

```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

R1

Propagate

Ftyp

VarRadTyp

OverflowType

NRadii

Radii

Visual Basic for Applications (VBA) Syntax

See [ModelDoc::IFeatureFillet2](#).

See Also

IFeatureFillet3 Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : IFeatureFillet3 Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::IFeatureFillet3](#).

.NET Syntax

Visual Basic (Declaration)

```
Function IFeatureFillet3( _  
    ByVal R1 As System.Double, _  
    ByVal Propagate As System.Boolean, _  
    ByVal Ftyp As System.Integer, _  
    ByVal VarRadTyp As System.Boolean, _  
    ByVal OverflowType As System.Integer, _  
    ByVal NRadii As System.Integer, _  
    ByRef Radii As System.Double, _  
    ByVal UseHelpPoint As System.Boolean, _  
    ByVal UseTangentHoldLine As System.Boolean _  
) As System.Integer
```

Visual Basic (Usage)



```
Dim instance As IModelDoc  
Dim R1 As System.Double  
Dim Propagate As System.Boolean  
Dim Ftyp As System.Integer  
Dim VarRadTyp As System.Boolean  
Dim OverflowType As System.Integer  
Dim NRadii As System.Integer  
Dim Radii As System.Double  
Dim UseHelpPoint As System.Boolean  
Dim UseTangentHoldLine As System.Boolean  
Dim value As System.Integer
```

```
value = instance.IFeatureFillet3(R1, Propagate, Ftyp, VarRadTyp, OverflowType, NRadii, Radii,  
UseHelpPoint, UseTangentHoldLine)
```

C#

```
System.int IFeatureFillet3(  
    System.double R1,  
    System.bool Propagate,  
    System.int Ftyp,  
    System.bool VarRadTyp,  
    System.int OverflowType,  
    System.int NRadii,  
    ref System.double Radii,  
    System.bool UseHelpPoint,  
    System.bool UseTangentHoldLine  
)
```

C++/CLI

```
System.int IFeatureFillet3(  
& System.double R1,  
& System.bool Propagate,  
& System.int Ftyp,  
& System.bool VarRadTyp,  
& System.int OverflowType,  
& System.int NRadii,  
& System.double% Radii,  
& System.bool UseHelpPoint,
```

```
& System.bool UseTangentHoldLine  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

R1

Propagate

Ftyp

VarRadTyp

OverflowType

NRadii

Radii

UseHelpPoint

UseTangentHoldLine

Visual Basic for Applications (VBA) Syntax

See [ModelDoc::IFeatureFillet3](#).

See Also

[IModelDoc Interface](#)
[IModelDoc Members](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

IFeatureFillet4 Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : IFeatureFillet4 Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::IFeatureFillet4](#).

.NET Syntax

Visual Basic (Declaration)

```
Function IFeatureFillet4(  
    ByVal R1 As System.Double, _  
    ByVal Propagate As System.Boolean, _  
    ByVal UniformRadius As System.Boolean, _  
    ByVal Ftyp As System.Integer, _  
    ByVal VarRadTyp As System.Boolean, _  
    ByVal OverflowType As System.Integer, _  
    ByVal NRadii As System.Integer, _  
    ByRef Radii As System.Double, _  
    ByVal UseHelpPoint As System.Boolean, _  
    ByVal UseTangentHoldLine As System.Boolean, _  
    ByVal CornerType As System.Boolean, _  
    ByVal SetbackDistCount As System.Integer, _  
    ByRef SetBackDistances As System.Double _  
) As System.Integer
```

Visual Basic (Usage)



```
Dim instance As IModelDoc  
Dim R1 As System.Double  
Dim Propagate As System.Boolean  
Dim UniformRadius As System.Boolean  
Dim Ftyp As System.Integer  
Dim VarRadTyp As System.Boolean  
Dim OverflowType As System.Integer  
Dim NRadii As System.Integer  
Dim Radii As System.Double  
Dim UseHelpPoint As System.Boolean  
Dim UseTangentHoldLine As System.Boolean
```

```

Dim CornerType As System.Boolean
Dim SetbackDistCount As System.Integer
Dim SetBackDistances As System.Double
Dim value As System.Integer

```

```

value = instance.IFeatureFillet4(R1, Propagate, UniformRadius, Ftyp, VarRadTyp, OverflowType,
NRadii, Radii, UseHelpPoint, UseTangentHoldLine, CornerType, SetbackDistCount, SetBackDistances)

```

C#

```

System.int IFeatureFillet4(
    System.double R1,
    System.bool Propagate,
    System.bool UniformRadius,
    System.int Ftyp,
    System.bool VarRadTyp,
    System.int OverflowType,
    System.int NRadii,
    ref System.double Radii,
    System.bool UseHelpPoint,
    System.bool UseTangentHoldLine,
    System.bool CornerType,
    System.int SetbackDistCount,
    ref System.double SetBackDistances
)

```

C++/CLI

```

System.int IFeatureFillet4(
    & System.double R1,
    & System.bool Propagate,
    & System.bool UniformRadius,
    & System.int Ftyp,
    & System.bool VarRadTyp,
    & System.int OverflowType,
    & System.int NRadii,
    & System.double% Radii,
    & System.bool UseHelpPoint,
    & System.bool UseTangentHoldLine,
    & System.bool CornerType,
    & System.int SetbackDistCount,
    & System.double% SetBackDistances
)

```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

R1

Propagate

UniformRadius

Ftyp

VarRadTyp

OverflowType

NRadii

Radii

UseHelpPoint

UseTangentHoldLine

CornerType

SetbackDistCount

SetBackDistances

Visual Basic for Applications (VBA) Syntax

See [ModelDoc::IFeatureFillet4](#).

See Also

[IModelDoc Interface](#)
[IModelDoc Members](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

IFeatureReferenceCurve Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : IFeatureReferenceCurve Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::IFeatureReferenceCurve](#).

.NET Syntax

Visual Basic (Declaration)

```
Function IFeatureReferenceCurve( _  
    ByVal NumOfCurves As System.Integer, _  
    ByVal BaseCurves As System.IntPtr, _  
    ByVal Merge As System.Boolean, _  
    ByVal FromFileName As System.String, _  
    ByRef ErrorCode As System.Integer _  
    ) As ReferenceCurve
```

Visual Basic (Usage)



```
Dim instance As IModelDoc  
Dim NumOfCurves As System.Integer  
Dim BaseCurves As System.IntPtr  
Dim Merge As System.Boolean  
Dim FromFileName As System.String  
Dim ErrorCode As System.Integer  
Dim value As ReferenceCurve  
  
value = instance.IFeatureReferenceCurve(NumOfCurves, BaseCurves, Merge, FromFileName, ErrorCode)
```

C#

```
ReferenceCurve IFeatureReferenceCurve(  
    System.int NumOfCurves,  
    System.IntPtr BaseCurves,  
    System.bool Merge,  
    System.string FromFileName,  
    out System.int ErrorCode  
)
```

C++/CLI

```
ReferenceCurve^ IFeatureReferenceCurve(  
& System.int NumOfCurves,  
& System.IntPtr BaseCurves,  
& System.bool Merge,  
& System.String^ FromFileName,  
& [Out] System.int ErrorCode  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

NumOfCurves

BaseCurves

Merge

FromFileName

ErrorCode

Visual Basic for Applications (VBA) Syntax

See [ModelDoc::IFeatureReferenceCurve](#).

See Also

[IModelDoc Interface](#)
[IModelDoc Members](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

IFirstFeature Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : IFirstFeature Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::IFirstFeature](#).

.NET Syntax

Visual Basic (Declaration)

```
Function IFirstFeature() As Feature
```

Visual Basic (Usage)



```
Dim instance As IModelDoc  
Dim value As Feature
```

```
value = instance.IFirstFeature()
```

C#

```
Feature IFirstFeature()
```

C++/CLI

```
Feature^ IFirstFeature();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Visual Basic for Applications (VBA) Syntax

See [ModelDoc::IFirstFeature](#).

See Also

[IModelDoc Interface](#)
[IModelDoc Members](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

IGet3rdPartyStorage Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : IGet3rdPartyStorage Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::IGet3rdPartyStorage](#).

.NET Syntax

Visual Basic (Declaration)

```
Function IGet3rdPartyStorage( _  
    ByVal StringIn As System.String, _  
    ByVal IsStoring As System.Boolean _  
) As System.Object
```

Visual Basic (Usage)



```
Dim instance As IModelDoc  
Dim StringIn As System.String
```

```
Dim IsStoring As System.Boolean
Dim value As System.Object

value = instance.IGet3rdPartyStorage(StringIn, IsStoring)
```

C#

```
System.object IGet3rdPartyStorage(
    System.string StringIn,
    System.bool IsStoring
)
```

C++/CLI

```
System.Object^ IGet3rdPartyStorage(
    & System.String^ StringIn,
    & System.bool IsStoring
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

StringIn

IsStoring

Visual Basic for Applications (VBA) Syntax

See [ModelDoc2::IGet3rdPartyStorage](#).

See Also

[IModelDoc Interface](#)
[IModelDoc Members](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

IGetActiveConfiguration Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : IGetActiveConfiguration Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::IGetActiveConfiguration](#).

.NET Syntax

Visual Basic (Declaration)

```
Function IGetActiveConfiguration() As Configuration
```

Visual Basic (Usage)



```
Dim instance As IModelDoc
Dim value As Configuration

value = instance.IGetActiveConfiguration()
```

C#

```
Configuration IGetActiveConfiguration()
```

C++/CLI

```
Configuration^ IGetActiveConfiguration();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Visual Basic for Applications (VBA) Syntax

See [ModelDoc2::IGetActiveConfiguration](#).

See Also

[IModelDoc Interface](#)
[IModelDoc Members](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

IGetActiveSketch Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : IGetActiveSketch Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::IGetActiveSketch](#).

.NET Syntax

Visual Basic (Declaration)

```
Function IGetActiveSketch() As Sketch
```

Visual Basic (Usage)



```
Dim instance As IModelDoc  
Dim value As Sketch  
  
value = instance.IGetActiveSketch()
```

C#

```
Sketch IGetActiveSketch()
```

C++/CLI

```
Sketch^ IGetActiveSketch();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Visual Basic for Applications (VBA) Syntax

See [ModelDoc::IGetActiveSketch](#).

See Also

[IModelDoc Interface](#)
[IModelDoc Members](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

IGetActiveSketch2 Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : IGetActiveSketch2 Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::IGetActiveSketch2](#).

.NET Syntax

Visual Basic (Declaration)

```
Function IGetActiveSketch2() As Sketch
```

Visual Basic (Usage)



```
Dim instance As IModelDoc  
Dim value As Sketch  
  
value = instance.IGetActiveSketch2()
```

C#

```
Sketch IGetActiveSketch2()
```

C++/CLI

```
Sketch^ IGetActiveSketch2();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Visual Basic for Applications (VBA) Syntax

See [ModelDoc::IGetActiveSketch2](#).

See Also

[IModelDoc Interface](#)
[IModelDoc Members](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

IGetAngularUnits Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : IGetAngularUnits Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::IGetAngularUnits](#).

.NET Syntax

Visual Basic (Declaration)

```
Function IGetAngularUnits() As System.Short
```

Visual Basic (Usage)



```
Dim instance As IModelDoc  
Dim value As System.Short
```

```
value = instance.IGetAngularUnits()
```

C#

```
System.short IGetAngularUnits()
```

C++/CLI

```
System.short IGetAngularUnits();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Visual Basic for Applications (VBA) Syntax

See [ModelDoc::IGetAngularUnits](#).

See Also

[IModelDoc Interface](#)
[IModelDoc Members](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

IGetColorTable Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : IGetColorTable Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::IGetColorTable](#).

.NET Syntax

Visual Basic (Declaration)

```
Function IGetColorTable() As ColorTable
```

Visual Basic (Usage)



```
Dim instance As IModelDoc  
Dim value As ColorTable  
  
value = instance.IGetColorTable()
```

C#

```
ColorTable IGetColorTable()
```

C++/CLI

```
ColorTable^ IGetColorTable();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Visual Basic for Applications (VBA) Syntax

See [ModelDoc::IGetColorTable](#).

See Also

[IModelDoc Interface](#)
[IModelDoc Members](#)

SOLIDWORKS API Help

[Send comments on this topic.](#)

IGetConfigurationByName Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : IGetConfigurationByName Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::IGetConfigurationByName](#).

.NET Syntax

Visual Basic (Declaration)

```
Function IGetConfigurationByName( _  
    ByVal Name As System.String _  
) As Configuration
```

Visual Basic (Usage)



```
Dim instance As IModelDoc  
Dim Name As System.String  
Dim value As Configuration  
  
value = instance.IGetConfigurationByName(Name)
```

C#

```
Configuration IGetConfigurationByName(  
    System.string Name  
)
```

C++/CLI

```
Configuration^ IGetConfigurationByName(  
& System.String^ Name  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Name

Visual Basic for Applications (VBA) Syntax

See [ModelDoc2::IGetConfigurationByName](#).

See Also

[IModelDoc Interface](#)
[IModelDoc Members](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

IGetConfigurationNames Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : IGetConfigurationNames Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::IGetConfigurationNames](#).

.NET Syntax

Visual Basic (Declaration)

```
Function IGetConfigurationNames( _  
    ByRef Count As System.Integer _  
) As System.String
```

Visual Basic (Usage)



```
Dim instance As IModelDoc  
Dim Count As System.Integer  
Dim value As System.String  
  
value = instance.IGetConfigurationNames(Count)
```

C#

```
System.string IGetConfigurationNames(  
    out System.int Count  
)
```

C++/CLI

```
System.String^ IGetConfigurationNames(  
& [Out] System.int Count  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Count

Visual Basic for Applications (VBA) Syntax

See [ModelDoc2::IGetConfigurationNames](#).

See Also

[IModelDoc Interface](#)
[IModelDoc Members](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

IGetCoordinateSystemXformByName Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : IGetCoordinateSystemXformByName Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::IGetCoordinateSystemXformByName](#).

.NET Syntax

Visual Basic (Declaration)

```
Function IGetCoordinateSystemXformByName( _  
    ByVal NameIn As System.String _  
) As System.Double
```

Visual Basic (Usage)



```
Dim instance As IModelDoc  
Dim NameIn As System.String  
Dim value As System.Double  
  
value = instance.IGetCoordinateSystemXformByName(NameIn)
```

C#

```
System.double IGetCoordinateSystemXformByName(  
    System.string NameIn  
)
```

C++/CLI

```
System.double IGetCoordinateSystemXformByName(  
& System.String^ NameIn  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

NameIn

Visual Basic for Applications (VBA) Syntax

See [ModelDoc2::IGetCoordinateSystemXformByName](#).

See Also

[IModelDoc Interface](#)
[IModelDoc Members](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

IGetCustomInfoNames Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : IGetCustomInfoNames Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::IGetCustomInfoNames](#).

.NET Syntax

Visual Basic (Declaration)

```
Function IGetCustomInfoNames() As System.String
```

Visual Basic (Usage)



```
Dim instance As IModelDoc  
Dim value As System.String  
  
value = instance.IGetCustomInfoNames()
```

C#

```
System.string IGetCustomInfoNames()
```

C++/CLI

```
System.String^ IGetCustomInfoNames();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Visual Basic for Applications (VBA) Syntax

See [ModelDoc::IGetCustomInfoNames](#).

See Also

[IModelDoc Interface](#)
[IModelDoc Members](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

IGetCustomInfoNames2 Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : IGetCustomInfoNames2 Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::IGetCustomInfoNames2](#).

.NET Syntax

Visual Basic (Declaration)

```
Function IGetCustomInfoNames2( _  
    ByVal Configuration As System.String _  
) As System.String
```

Visual Basic (Usage)



```
Dim instance As IModelDoc  
Dim Configuration As System.String  
Dim value As System.String  
  
value = instance.IGetCustomInfoNames2(Configuration)
```

C#

```
System.string IGetCustomInfoNames2(  
    System.string Configuration  
)
```

C++/CLI

```
System.String^ IGetCustomInfoNames2(  
& System.String^ Configuration  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Configuration

Visual Basic for Applications (VBA) Syntax

See [ModelDoc::IGetCustomInfoNames2](#).

See Also

[IModelDoc Interface](#)
[IModelDoc Members](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

IGetDependencies Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : IGetDependencies Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::IGetDependencies](#).

.NET Syntax

Visual Basic (Declaration)

```
Function IGetDependencies( _  
    ByVal Traverseflag As System.Integer, _  
    ByVal Searchflag As System.Integer _  
) As System.String
```

Visual Basic (Usage)



```
Dim instance As IModelDoc  
Dim Traverseflag As System.Integer  
Dim Searchflag As System.Integer  
Dim value As System.String  
  
value = instance.IGetDependencies(Traverseflag, Searchflag)
```

C#

```
System.string IGetDependencies(  
    System.int Traverseflag,  
    System.int Searchflag  
)
```

C++/CLI

```
System.String^ IGetDependencies(  
& System.int Traverseflag,  
& System.int Searchflag  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Traverseflag

Searchflag

Visual Basic for Applications (VBA) Syntax

See [ModelDoc::IGetDependencies](#).

See Also

[IModelDoc Interface](#)
[IModelDoc Members](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

IGetDependencies2 Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : IGetDependencies2 Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::IGetDependencies2](#).

.NET Syntax

Visual Basic (Declaration)

```
Function IGetDependencies2( _  
    ByVal Traverseflag As System.Boolean, _  
    ByVal Searchflag As System.Boolean, _
```

```
ByVal AddReadOnlyInfo As System.Boolean _  
) As System.String
```

Visual Basic (Usage)



```
Dim instance As IModelDoc  
Dim Traverseflag As System.Boolean  
Dim Searchflag As System.Boolean  
Dim AddReadOnlyInfo As System.Boolean  
Dim value As System.String  
  
value = instance.IGetDependencies2(Traverseflag, Searchflag, AddReadOnlyInfo)
```

C#

```
System.string IGetDependencies2(  
    System.bool Traverseflag,  
    System.bool Searchflag,  
    System.bool AddReadOnlyInfo  
)
```

C++/CLI

```
System.String^ IGetDependencies2(  
& System.bool Traverseflag,  
& System.bool Searchflag,  
& System.bool AddReadOnlyInfo  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Traverseflag

Searchflag

AddReadOnlyInfo

Visual Basic for Applications (VBA) Syntax

See [ModelDoc::IGetDependencies2](#).

See Also

[IModelDoc Interface](#)
[IModelDoc Members](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

IGetDesignTable Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : IGetDesignTable Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::IGetDesignTable](#).

.NET Syntax

Visual Basic (Declaration)

```
Function IGetDesignTable() As DesignTable
```

Visual Basic (Usage)



```
Dim instance As IModelDoc  
Dim value As DesignTable  
  
value = instance.IGetDesignTable()
```

C#

```
DesignTable IGetDesignTable()
```

C++/CLI

```
DesignTable^ IGetDesignTable();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Visual Basic for Applications (VBA) Syntax

See [ModelDoc::IGetDesignTable](#).

See Also

[IModelDoc Interface](#)
[IModelDoc Members](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

IGetDetailingDefaults Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : IGetDetailingDefaults Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::IGetDetailingDefaults](#).

.NET Syntax

Visual Basic (Declaration)

```
Function IGetDetailingDefaults() As DetailingDefaults
```

Visual Basic (Usage)



```
Dim instance As IModelDoc  
Dim value As DetailingDefaults
```

```
value = instance.IGetDetailingDefaults()
```

C#

```
DetailingDefaults IGetDetailingDefaults()
```

C++/CLI

```
DetailingDefaults^ IGetDetailingDefaults();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Visual Basic for Applications (VBA) Syntax

See [ModelDoc::IGetDetailingDefaults](#).

See Also

[IModelDoc Interface](#)
[IModelDoc Members](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

IGetEntityName Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : IGetEntityName Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::IGetEntityName](#).

.NET Syntax

Visual Basic (Declaration)

```
Function IGetEntityName( _  
    ByVal Entity As Entity _  
) As System.String
```

Visual Basic (Usage)



```
Dim instance As IModelDoc  
Dim Entity As Entity  
Dim value As System.String  
  
value = instance.IGetEntityName(Entity)
```

C#

```
System.string IGetEntityName(  
    Entity Entity  
)
```

C++/CLI

```
System.String^ IGetEntityName(  
& Entity^ Entity  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Entity

Visual Basic for Applications (VBA) Syntax

See [ModelDoc::IGetEntityName](#).

See Also

[IModelDoc Interface](#)
[IModelDoc Members](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

IGetFirstAnnotation Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : IGetFirstAnnotation Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::IGetFirstAnnotation](#).

.NET Syntax

Visual Basic (Declaration)

```
Function IGetFirstAnnotation() As Annotation
```

Visual Basic (Usage)



```
Dim instance As IModelDoc  
Dim value As Annotation  
  
value = instance.IGetFirstAnnotation()
```

C#

```
Annotation IGetFirstAnnotation()
```

C++/CLI

```
Annotation^ IGetFirstAnnotation();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Visual Basic for Applications (VBA) Syntax

See [ModelDoc2::IGetFirstAnnotation](#).

See Also

[IModelDoc Interface](#)
[IModelDoc Members](#)

SOLIDWORKS API Help

[Send comments on this topic.](#)

IGetFirstAnnotation2 Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : IGetFirstAnnotation2 Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::IGetFirstAnnotation2](#).

.NET Syntax

Visual Basic (Declaration)

```
Function IGetFirstAnnotation2() As Annotation
```

Visual Basic (Usage)



```
Dim instance As IModelDoc  
Dim value As Annotation
```

```
value = instance.IGetFirstAnnotation2()
```

C#

```
Annotation IGetFirstAnnotation2()
```

C++/CLI

```
Annotation^ IGetFirstAnnotation2();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Visual Basic for Applications (VBA) Syntax

See [ModelDoc2::IGetFirstAnnotation2](#).

See Also

[IModelDoc Interface](#)
[IModelDoc Members](#)

SOLIDWORKS API Help

[Send comments on this topic.](#)

IGetFirstModelView Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : IGetFirstModelView Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::IGetFirstModelView](#).

.NET Syntax

Visual Basic (Declaration)

```
Function IGetFirstModelView() As ModelView
```

Visual Basic (Usage)



```
Dim instance As IModelDoc  
Dim value As ModelView  
  
value = instance.IGetFirstModelView()
```

C#

```
ModelView IGetFirstModelView()
```

C++/CLI

```
ModelView^ IGetFirstModelView();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Visual Basic for Applications (VBA) Syntax

See [ModelDoc::IGetFirstModelView](#).

See Also

[IModelDoc Interface](#)
[IModelDoc Members](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

IGetLayerManager Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : IGetLayerManager Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::IGetLayerManager](#).

.NET Syntax

Visual Basic (Declaration)

```
Function IGetLayerManager() As LayerMgr
```

Visual Basic (Usage)



```
Dim instance As IModelDoc  
Dim value As LayerMgr  
  
value = instance.IGetLayerManager()
```

C#

```
LayerMgr IGetLayerManager()
```

C++/CLI

```
LayerMgr^ IGetLayerManager();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Visual Basic for Applications (VBA) Syntax

See [ModelDoc::IGetLayerManager](#).

See Also

[IModelDoc Interface](#)
[IModelDoc Members](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

IGetLines Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : IGetLines Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::IGetLines](#).

.NET Syntax

Visual Basic (Declaration)

```
Function IGetLines() As System.Double
```

Visual Basic (Usage)



```
Dim instance As IModelDoc  
Dim value As System.Double  
  
value = instance.IGetLines()
```

C#

```
System.double IGetLines()
```

C++/CLI

```
System.double IGetLines();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Visual Basic for Applications (VBA) Syntax

See [ModelDoc::IGetLines](#).

See Also

[IModelDoc Interface](#)
[IModelDoc Members](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

IGetMassProperties Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : IGetMassProperties Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::IGetMassProperties](#).

.NET Syntax

Visual Basic (Declaration)

```
Function IGetMassProperties( _  
    ByRef MPropsData As System.Double _  
) As System.Boolean
```

Visual Basic (Usage)



```
Dim instance As IModelDoc  
Dim MPropsData As System.Double  
Dim value As System.Boolean  
  
value = instance.IGetMassProperties(MPropsData)
```

C#

```
System.bool IGetMassProperties(  
    ref System.double MPropsData  
)
```

C++/CLI

```
System.bool IGetMassProperties(  
& System.double% MPropsData  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

MPropsData

Visual Basic for Applications (VBA) Syntax

See [ModelDoc::IGetMassProperties](#).

See Also

[IModelDoc Interface](#)
[IModelDoc Members](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

IGetMassProperties2 Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : IGetMassProperties2 Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::IGetMassProperties2](#).

.NET Syntax

Visual Basic (Declaration)

```
Function IGetMassProperties2( _  
    ByRef Status As System.Integer _  
) As System.Double
```

Visual Basic (Usage)



```
Dim instance As IModelDoc  
Dim Status As System.Integer  
Dim value As System.Double  
  
value = instance.IGetMassProperties2(Status)
```

C#

```
System.double IGetMassProperties2(  
    out System.int Status  
)
```

C++/CLI

```
System.double IGetMassProperties2(  
& [Out] System.int Status  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Status

Visual Basic for Applications (VBA) Syntax

See [ModelDoc::IGetMassProperties2](#).

See Also

IGetModelViewNames Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : IGetModelViewNames Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::IGetModelViewNames](#).

.NET Syntax

Visual Basic (Declaration)

```
Function IGetModelViewNames() As System.String
```

Visual Basic (Usage)



```
Dim instance As IModelDoc  
Dim value As System.String  
  
value = instance.IGetModelViewNames()
```

C#

```
System.string IGetModelViewNames()
```

C++/CLI

```
System.String^ IGetModelViewNames();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Visual Basic for Applications (VBA) Syntax

See [ModelDoc::IGetModelViewNames](#).

See Also

[IModelDoc Interface](#)
[IModelDoc Members](#)

IGetNext Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : IGetNext Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::IGetNext](#).

.NET Syntax

Visual Basic (Declaration)

```
Function IGetNext() As ModelDoc
```

Visual Basic (Usage)



```
Dim instance As IModelDoc  
Dim value As ModelDoc  
  
value = instance.IGetNext()
```

C#

```
ModelDoc IGetNext()
```

C++/CLI

```
ModelDoc^ IGetNext();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Visual Basic for Applications (VBA) Syntax

See [ModelDoc::IGetNext](#).

See Also

[IModelDoc Interface](#)
[IModelDoc Members](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

IGetNumDependencies Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : IGetNumDependencies Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::IGetNumDependencies](#).

.NET Syntax

Visual Basic (Declaration)

```
Function IGetNumDependencies( _  
    ByVal Traverseflag As System.Integer, _  
    ByVal Searchflag As System.Integer _  
) As System.Integer
```

Visual Basic (Usage)



```
Dim instance As IModelDoc  
Dim Traverseflag As System.Integer  
Dim Searchflag As System.Integer  
Dim value As System.Integer  
  
value = instance.IGetNumDependencies(Traverseflag, Searchflag)
```

C#

```
System.int IGetNumDependencies(  
    System.int Traverseflag,  
    System.int Searchflag  
)
```

C++/CLI

```
System.int IGetNumDependencies(  
& System.int Traverseflag,  
& System.int Searchflag  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Traverseflag

Searchflag

Visual Basic for Applications (VBA) Syntax

See [ModelDoc::IGetNumDependencies](#).

See Also

IGetNumDependencies2 Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : IGetNumDependencies2 Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::IGetNumDependencies2](#).

.NET Syntax

Visual Basic (Declaration)

```
Function IGetNumDependencies2( _  
    ByVal Traverseflag As System.Boolean, _  
    ByVal Searchflag As System.Boolean, _  
    ByVal AddReadOnlyInfo As System.Boolean _  
) As System.Integer
```

Visual Basic (Usage)



```
Dim instance As IModelDoc  
Dim Traverseflag As System.Boolean  
Dim Searchflag As System.Boolean  
Dim AddReadOnlyInfo As System.Boolean  
Dim value As System.Integer
```

```
value = instance.IGetNumDependencies2(Traverseflag, Searchflag, AddReadOnlyInfo)
```

C#

```
System.int IGetNumDependencies2(  
    System.bool Traverseflag,  
    System.bool Searchflag,  
    System.bool AddReadOnlyInfo  
)
```

C++/CLI

```
System.int IGetNumDependencies2(  
& System.bool Traverseflag,  
& System.bool Searchflag,  
& System.bool AddReadOnlyInfo  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Traverseflag

Searchflag

AddReadOnlyInfo

Visual Basic for Applications (VBA) Syntax

See [ModelDoc::IGetNumDependencies2](#).

See Also

[IModelDoc Interface](#)
[IModelDoc Members](#)

IGetRayIntersectionsPoints Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : IGetRayIntersectionsPoints Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::IGetRayIntersectionsPoints](#).

.NET Syntax

Visual Basic (Declaration)

```
Function IGetRayIntersectionsPoints() As System.Double
```

Visual Basic (Usage)



```
Dim instance As IModelDoc  
Dim value As System.Double  
  
value = instance.IGetRayIntersectionsPoints()
```

C#

```
System.double IGetRayIntersectionsPoints()
```

C++/CLI

```
System.double IGetRayIntersectionsPoints();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Visual Basic for Applications (VBA) Syntax

See [ModelDoc::IGetRayIntersectionsPoints](#).

See Also

[IModelDoc Interface](#)
[IModelDoc Members](#)

SOLIDWORKS API Help

[Send comments on this topic.](#)

IGetRayIntersectionsTopology Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : IGetRayIntersectionsTopology Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::IGetRayIntersectionsTopology](#).

.NET Syntax

Visual Basic (Declaration)

```
Function IGetRayIntersectionsTopology() As System.Object
```

Visual Basic (Usage)



```
Dim instance As IModelDoc  
Dim value As System.Object  
  
value = instance.IGetRayIntersectionsTopology()
```

C#

```
System.object IGetRayIntersectionsTopology()
```

C++/CLI

```
System.Object^ IGetRayIntersectionsTopology();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Visual Basic for Applications (VBA) Syntax

See [ModelDoc::IGetRayIntersectionsTopology](#).

See Also

[IModelDoc Interface](#)
[IModelDoc Members](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

IGetStandardViewRotation Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : IGetStandardViewRotation Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::IGetStandardViewRotation](#).

.NET Syntax

Visual Basic (Declaration)

```
Function IGetStandardViewRotation( _  
    ByVal ViewId As System.Integer _  
) As System.Double
```

Visual Basic (Usage)



```
Dim instance As IModelDoc  
Dim ViewId As System.Integer  
Dim value As System.Double  
  
value = instance.IGetStandardViewRotation(ViewId)
```

C#

```
System.double IGetStandardViewRotation(  
    System.int ViewId  
)
```

C++/CLI

```
System.double IGetStandardViewRotation(  
    & System.int ViewId  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

ViewId

Visual Basic for Applications (VBA) Syntax

See [ModelDoc::IGetStandardViewRotation](#).

See Also

[IModelDoc Interface](#)
[IModelDoc Members](#)