

# SOLIDWORKS API (.NET VBA C#) — Reference (194/337): IModelDoc2 (part 17 of 17)

SOLIDWORKS API Documentation (converted from CHM)

# IModelDoc2 (part 17 of 17) (Type)

SOLIDWORKS API Help

[Send comments](#) on this topic.

## ViewRotYPlusNinety Method (IModelDoc2)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc2 Interface](#) : ViewRotYPlusNinety Method (IModelDoc2)

Dynamically rotates the view by 90 about y.

### .NET Syntax

Visual Basic (Declaration)

```
Sub ViewRotYPlusNinety()
```

Visual Basic (Usage)



```
Dim instance As IModelDoc2  
instance.ViewRotYPlusNinety()
```

C#

```
void ViewRotYPlusNinety()
```

C++/CLI

```
void ViewRotYPlusNinety();
```

**NOTE:** See [Differences Between Unmanaged C++ and C++/CLI Code](#).

### Visual Basic for Applications (VBA) Syntax

See [ModelDoc2::ViewRotYPlusNinety](#).

### Example

[Rotate Model \(VBA\)](#)  
[Rotate Model \(VB.NET\)](#)  
[Rotate Model \(C#\)](#)

### Remarks

To increase the speed of dynamic view changes with hidden-edge display or hidden-grey display, use [IModelView::StartDynamics](#) and [IModelView::StopDynamics](#).

### See Also

[IModelDoc2 Interface](#)  
[IModelDoc2 Members](#)  
[IModelDoc2::ViewZoomToSelection Method](#)  
[IModelDoc2::ViewZoomToFit2 Method](#)  
[IModelDoc2::ViewZoomTo2 Method](#)  
[IModelDoc2::ViewZoomout Method](#)  
[IModelDoc2::ViewZoomin Method](#)  
[IModelDoc2::ViewRotYMinusNinety Method](#)  
[IModelDoc2::ViewRotXPlusNinety Method](#)  
[IModelDoc2::ViewRotXMinusNinety Method](#)  
[IModelDoc2::ViewRotateplusz Method](#)  
[IModelDoc2::ViewRotateplusy Method](#)  
[IModelDoc2::ViewRotateplusx Method](#)  
[IModelDoc2::ViewRotateminusz Method](#)  
[IModelDoc2::ViewRotateminusy Method](#)  
[IModelDoc2::ViewRotateminusx Method](#)  
[IModelDoc2::ViewRotate Method](#)  
[IModelDoc2::ViewOrientationUndo Method](#)  
[IModelDoc2::ViewZoomto Method](#)  
[IModelDocExtension::ViewZoomToSheet Method](#)

### Availability

SOLIDWORKS 2001Plus FCS, Revision Number 10.0

## ViewRwShading Method (IModelDoc2)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc2 Interface](#) : ViewRwShading Method (IModelDoc2)

Sets the current display subsystem to use renderware.

### .NET Syntax

#### Visual Basic (Declaration)

```
Sub ViewRwShading()
```

#### Visual Basic (Usage)



```
Dim instance As IModelDoc2
```

```
instance.ViewRwShading()
```

#### C#

```
void ViewRwShading()
```

#### C++/CLI

```
void ViewRwShading();
```

**NOTE:** See [Differences Between Unmanaged C++ and C++/CLI Code](#).

### Visual Basic for Applications (VBA) Syntax

See [ModelDoc2::ViewRwShading](#).

### See Also

[IModelDoc2 Interface](#)  
[IModelDoc2 Members](#)

### Availability

SOLIDWORKS 2001Plus FCS, Revision Number 10.0

## ViewTranslate Method (IModelDoc2)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc2 Interface](#) : ViewTranslate Method (IModelDoc2)

Translates the view.

### .NET Syntax

#### Visual Basic (Declaration)

```
Sub ViewTranslate()
```

#### Visual Basic (Usage)



```
Dim instance As IModelDoc2
```

```
instance.ViewTranslate()
```

#### C#

```
void ViewTranslate()
```

#### C++/CLI

```
void ViewTranslate();
```

**NOTE:** See [Differences Between Unmanaged C++ and C++/CLI Code](#).

#### Visual Basic for Applications (VBA) Syntax

See [ModelDoc2::ViewTranslate](#).

#### See Also

[IModelDoc2 Interface](#)  
[IModelDoc2 Members](#)  
[IModelDoc2::ViewTranslateminusx Method](#)  
[IModelDoc2::ViewTranslateminusy Method](#)  
[IModelDoc2::ViewTranslateplusx Method](#)  
[IModelDoc2::ViewTranslateplusy Method](#)

#### Availability

SOLIDWORKS 2001Plus FCS, Revision Number 10.0

SOLIDWORKS API Help

[Send comments](#) on this topic.

### ViewTranslateminusx Method (IModelDoc2)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc2 Interface](#) : ViewTranslateminusx Method (IModelDoc2)

Dynamically shifts the view left.

#### .NET Syntax

Visual Basic (Declaration)

```
Sub ViewTranslateminusx()
```

Visual Basic (Usage)



```
Dim instance As IModelDoc2  
  
instance.ViewTranslateminusx()
```

C#

```
void ViewTranslateminusx()
```

C++/CLI

```
void ViewTranslateminusx();
```

**NOTE:** See [Differences Between Unmanaged C++ and C++/CLI Code](#).

#### Visual Basic for Applications (VBA) Syntax

See [ModelDoc2::ViewTranslateminusx](#).

#### See Also

[IModelDoc2 Interface](#)  
[IModelDoc2 Members](#)  
[IModelDoc2::ViewTranslate Method](#)  
[IModelDoc2::ViewTranslateminusy Method](#)  
[IModelDoc2::ViewTranslateplusx Method](#)  
[IModelDoc2::ViewTranslateplusy Method](#)

#### Availability

SOLIDWORKS 2001Plus FCS, Revision Number 10.0

SOLIDWORKS API Help

[Send comments](#) on this topic.

# ViewTranslateminusy Method (IModelDoc2)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc2 Interface](#) : ViewTranslateminusy Method (IModelDoc2)

Dynamically shifts the view down.

**.NET Syntax**

Visual Basic (Declaration)

Sub ViewTranslateminusy()

Visual Basic (Usage)

Dim instance As [IModelDoc2](#)  
instance.ViewTranslateminusy()

C#

void ViewTranslateminusy()

C++/CLI

void ViewTranslateminusy();

**NOTE:** See [Differences Between Unmanaged C++ and C++/CLI Code](#).

**Visual Basic for Applications (VBA) Syntax**

See [ModelDoc2::ViewTranslateminusy](#).

**See Also**

[IModelDoc2 Interface](#)  
[IModelDoc2 Members](#)  
[IModelDoc2::ViewTranslate Method](#)  
[IModelDoc2::ViewTranslateminusx Method](#)  
[IModelDoc2::ViewTranslateplusx Method](#)  
[IModelDoc2::ViewTranslateplusy Method](#)

**Availability**

SOLIDWORKS 2001Plus FCS, Revision Number 10.0

SOLIDWORKS API Help [Send comments on this topic.](#)

# ViewTranslateplusx Method (IModelDoc2)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc2 Interface](#) : ViewTranslateplusx Method (IModelDoc2)

Dynamically shifts the view right.

**.NET Syntax**

Visual Basic (Declaration)

Sub ViewTranslateplusx()

Visual Basic (Usage)

Dim instance As [IModelDoc2](#)  
instance.ViewTranslateplusx()

C#

void ViewTranslateplusx()

C++/CLI

```
void ViewTranslateplusx();
```

**NOTE:** See [Differences Between Unmanaged C++ and C++/CLI Code](#).

#### Visual Basic for Applications (VBA) Syntax

See [ModelDoc2::ViewTranslateplusx](#).

#### See Also

[IModelDoc2 Interface](#)  
[IModelDoc2 Members](#)  
[IModelDoc2::ViewTranslate Method](#)  
[IModelDoc2::ViewTranslateminusx Method](#)  
[IModelDoc2::ViewTranslateminusy Method](#)  
[IModelDoc2::ViewTranslateplusy Method](#)

#### Availability

SOLIDWORKS 2001Plus FCS, Revision Number 10.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

### ViewTranslateplusy Method (IModelDoc2)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc2 Interface](#) : ViewTranslateplusy Method (IModelDoc2)

Dynamically shifts the view up.

#### .NET Syntax

Visual Basic (Declaration)

```
Sub ViewTranslateplusy()
```

Visual Basic (Usage)



```
Dim instance As IModelDoc2  
  
instance.ViewTranslateplusy()
```

C#

```
void ViewTranslateplusy()
```

C++/CLI

```
void ViewTranslateplusy();
```

**NOTE:** See [Differences Between Unmanaged C++ and C++/CLI Code](#).

#### Visual Basic for Applications (VBA) Syntax

See [ModelDoc2::ViewTranslateplusy](#).

#### See Also

[IModelDoc2 Interface](#)  
[IModelDoc2 Members](#)  
[IModelDoc2::ViewTranslate Method](#)  
[IModelDoc2::ViewTranslateminusx Method](#)  
[IModelDoc2::ViewTranslateminusy Method](#)  
[IModelDoc2::ViewTranslateplusx Method](#)

#### Availability

SOLIDWORKS 2001Plus FCS, Revision Number 10.0

# ViewZoomin Method (IModelDoc2)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc2 Interface](#) : ViewZoomin Method (IModelDoc2)

Zooms the current view in by a factor of 20%.

## .NET Syntax

Visual Basic (Declaration)

Sub ViewZoomin()

Visual Basic (Usage)



Dim instance As [IModelDoc2](#)

instance.ViewZoomin()

C#

void ViewZoomin()

C++/CLI

void ViewZoomin();

**NOTE:** See [Differences Between Unmanaged C++ and C++/CLI Code](#).

## Visual Basic for Applications (VBA) Syntax

See [ModelDoc2::ViewZoomin](#).

## See Also

[IModelDoc2 Interface](#)  
[IModelDoc2 Members](#)  
[IModelDoc2::ViewZoomout Method](#)  
[IModelDoc2::ViewZoomTo2 Method](#)  
[IModelDoc2::ViewZoomToFit2 Method](#)  
[IModelDoc2::ViewZoomToSelection Method](#)  
[IModelDoc2::ViewOrientationUndo Method](#)  
[IModelDoc2::ViewRotate Method](#)  
[IModelDoc2::ViewRotateminusx Method](#)  
[IModelDoc2::ViewRotateminusy Method](#)  
[IModelDoc2::ViewRotateminusz Method](#)  
[IModelDoc2::ViewRotateplusx Method](#)  
[IModelDoc2::ViewRotateplusy Method](#)  
[IModelDoc2::ViewRotateplusz Method](#)  
[IModelDoc2::ViewRotXMinusNinety Method](#)  
[IModelDoc2::ViewRotXPlusNinety Method](#)  
[IModelDoc2::ViewRotYMinusNinety Method](#)  
[IModelDoc2::ViewRotYPlusNinety Method](#)  
[IModelDoc2::ViewZoomto Method](#)  
[IModelDocExtension::ViewZoomToSheet Method](#)

## Availability

SOLIDWORKS 2001Plus FCS, Revision Number 10.0

# ViewZoomout Method (IModelDoc2)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc2 Interface](#) : ViewZoomout Method (IModelDoc2)

Zooms the current view out by a factor of 20%.

## .NET Syntax

Visual Basic (Declaration)

Sub ViewZoomout()

```
Dim instance As IModelDoc2

instance.ViewZoomout()
```

C#

```
void ViewZoomout()
```

C++/CLI

```
void ViewZoomout();
```

**NOTE:** See [Differences Between Unmanaged C++ and C++/CLI Code](#).

## Visual Basic for Applications (VBA) Syntax

See [ModelDoc2::ViewZoomout](#).

## See Also

[IModelDoc2 Interface](#)  
[IModelDoc2 Members](#)  
[IModelDoc2::ViewZoomin Method](#)  
[IModelDoc2::ViewZoomTo2 Method](#)  
[IModelDoc2::ViewZoomtofit2 Method](#)  
[IModelDoc2::ViewZoomToSelection Method](#)  
[IModelDoc2::ViewOrientationUndo Method](#)  
[IModelDoc2::ViewRotate Method](#)  
[IModelDoc2::ViewRotateminusx Method](#)  
[IModelDoc2::ViewRotateminusy Method](#)  
[IModelDoc2::ViewRotateminusz Method](#)  
[IModelDoc2::ViewRotateplusx Method](#)  
[IModelDoc2::ViewRotateplusy Method](#)  
[IModelDoc2::ViewRotateplusz Method](#)  
[IModelDoc2::ViewRotXMinusNinety Method](#)  
[IModelDoc2::ViewRotXPlusNinety Method](#)  
[IModelDoc2::ViewRotYMinusNinety Method](#)  
[IModelDoc2::ViewRotYPlusNinety Method](#)  
[IModelDoc2::ViewZoomto Method](#)  
[IModelDocExtension::ViewZoomToSheet Method](#)

## Availability

SOLIDWORKS 2001Plus FCS, Revision Number 10.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

## ViewZoomto Method (IModelDoc2)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc2 Interface](#) : ViewZoomto Method (IModelDoc2)

Zooms the view to the selected box.

## .NET Syntax

Visual Basic (Declaration)

```
Sub ViewZoomto()
```

Visual Basic (Usage)

```
Dim instance As IModelDoc2

instance.ViewZoomto()
```

C#

```
void ViewZoomto()
```

C++/CLI

```
void ViewZoomto();
```

**NOTE:** See [Differences Between Unmanaged C++ and C++/CLI Code](#).

## Visual Basic for Applications (VBA) Syntax

See [ModelDoc2::ViewZoomto](#).

## Remarks

See [IModelDoc2::ViewZoomTo2](#), which allows you to zoom to an X,Y,Z boxed location.

## See Also

[IModelDoc2 Interface](#)  
[IModelDoc2 Members](#)  
[IModelDoc2::ViewOrientationUndo Method \(\)](#)  
[IModelDoc2::ViewRotate Method \(\)](#)  
[IModelDoc2::ViewRotateminusx Method \(\)](#)  
[IModelDoc2::ViewRotateminusy Method \(\)](#)  
[IModelDoc2::ViewRotateminusz Method \(\)](#)  
[IModelDoc2::ViewRotateplusx Method \(\)](#)  
[IModelDoc2::ViewRotateplusy Method \(\)](#)  
[IModelDoc2::ViewRotateplusz Method \(\)](#)  
[IModelDoc2::ViewRotXMinusNinety Method \(\)](#)  
[IModelDoc2::ViewRotXPlusNinety Method \(\)](#)  
[IModelDoc2::ViewRotYMinusNinety Method \(\)](#)  
[IModelDoc2::ViewRotYPlusNinety Method \(\)](#)  
[IModelDoc2::ViewZoomin Method \(\)](#)  
[IModelDoc2::ViewZoomout Method \(\)](#)  
[IModelDoc2::ViewZoomtofit2 Method \(\)](#)  
[IModelDoc2::ViewZoomToSelection Method \(\)](#)  
[IModelDocExtension::ViewZoomToSheet Method \(\)](#)

## Availability

SOLIDWORKS 2001Plus FCS, Revision Number 10.0

SOLIDWORKS API Help

[Send comments](#) on this topic.

## ViewZoomTo2 Method (IModelDoc2)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc2 Interface](#) : ViewZoomTo2 Method (IModelDoc2)

Zooms to the specified region.

## .NET Syntax

Visual Basic (Declaration)

```
Sub ViewZoomTo2( _  
    ByVal X1 As System.Double, _  
    ByVal Y1 As System.Double, _  
    ByVal Z1 As System.Double, _  
    ByVal X2 As System.Double, _  
    ByVal Y2 As System.Double, _  
    ByVal Z2 As System.Double _  
)
```

Visual Basic (Usage)



```
Dim instance As IModelDoc2  
Dim X1 As System.Double  
Dim Y1 As System.Double  
Dim Z1 As System.Double  
Dim X2 As System.Double  
Dim Y2 As System.Double  
Dim Z2 As System.Double
```

```
instance.ViewZoomTo2(X1, Y1, Z1, X2, Y2, Z2)
```

C#

```
void ViewZoomTo2(  
    System.double X1,  
    System.double Y1,
```

```
        System.double Z1,  
        System.double X2,  
        System.double Y2,  
        System.double Z2  
    )
```

C++/CLI

```
void ViewZoomTo2(  
    & System.double X1,  
    & System.double Y1,  
    & System.double Z1,  
    & System.double X2,  
    & System.double Y2,  
    & System.double Z2  
)
```

**NOTE:** See [Differences Between Unmanaged C++ and C++/CLI Code](#).

#### Parameters

**X1**  
X value for the lower-left point of the zoom area  
**Y1**  
Y value for the lower-left point of the zoom area  
**Z1**  
Z value for the lower-left point of the zoom area  
**X2**  
X value for the upper-right point of the zoom area  
**Y2**  
Y value for the upper-right point of the zoom area  
**Z2**  
Z value for the upper-right point of the zoom area

### Visual Basic for Applications (VBA) Syntax

See [ModelDoc2::ViewZoomTo2](#).

### Example

[Zoom To Region \(VBA\)](#)

### See Also

[IModelDoc2 Interface](#)  
[IModelDoc2 Members](#)  
[IModelDoc2::ViewZoomin Method](#)  
[IModelDoc2::ViewZoomout Method](#)  
[IModelDoc2::ViewZoomto Method](#)  
[IModelDoc2::ViewZoomtofit2 Method](#)  
[IModelDoc2::ViewZoomToSelection Method](#)  
[IModelDoc2::ViewOrientationUndo Method](#)  
[IModelDoc2::ViewRotate Method](#)  
[IModelDoc2::ViewRotateminusx Method](#)  
[IModelDoc2::ViewRotateminusy Method](#)  
[IModelDoc2::ViewRotateminusz Method](#)  
[IModelDoc2::ViewRotateplusx Method](#)  
[IModelDoc2::ViewRotateplusy Method](#)  
[IModelDoc2::ViewRotateplusz Method](#)  
[IModelDoc2::ViewRotXMinusNinety Method](#)  
[IModelDoc2::ViewRotXPlusNinety Method](#)  
[IModelDoc2::ViewRotYMinusNinety Method](#)  
[IModelDoc2::ViewRotYPlusNinety Method](#)  
[IModelDocExtension::ViewZoomToSheet Method](#)

### Availability

SOLIDWORKS 2001Plus FCS, Revision Number 10.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

## ViewZoomtofit Method (IModelDoc2)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc2 Interface](#) : ViewZoomtofit Method (IModelDoc2)

Obsolete. Superseded by [IModelDoc2::ViewZoomtofit2](#).

### .NET Syntax

Visual Basic (Declaration)

```
Sub ViewZoomtofit()
```

Visual Basic (Usage)



```
Dim instance As IModelDoc2  
instance.ViewZoomtofit()
```

C#

```
void ViewZoomtofit()
```

C++/CLI

```
void ViewZoomtofit();
```

**NOTE:** See [Differences Between Unmanaged C++ and C++/CLI Code](#).

### Visual Basic for Applications (VBA) Syntax

See [ModelDoc2::ViewZoomtofit](#).

### See Also

[IModelDoc2 Interface](#)  
[IModelDoc2 Members](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

## ViewZoomtofit2 Method (IModelDoc2)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc2 Interface](#) : ViewZoomtofit2 Method (IModelDoc2)

Zooms the currently active view to fit the screen.

### .NET Syntax

Visual Basic (Declaration)

```
Sub ViewZoomtofit2()
```

Visual Basic (Usage)



```
Dim instance As IModelDoc2  
instance.ViewZoomtofit2()
```

C#

```
void ViewZoomtofit2()
```

C++/CLI

```
void ViewZoomtofit2();
```

**NOTE:** See [Differences Between Unmanaged C++ and C++/CLI Code](#).

### Visual Basic for Applications (VBA) Syntax

See [ModelDoc2::ViewZoomtofit2](#).

### Example

[Access Assembly \(C++\)](#)  
[Change to Isometric and Zoom to Fit View Mode \(VBA\)](#)  
[Get Sketch Points in Wizard Hole \(VBA\)](#)  
[Create Equation-driven Curve \(C#\)](#)  
[Create Equation-driven Curve \(VB.NET\)](#)

[Create Equation-driven Curve \(VBA\)](#)  
[Add Component and Mate \(C++COM\)](#)  
[Add Component and Mate \(VBA\)](#)  
[Add Component and Mate \(VB.NET\)](#)  
[Add Component and Mate \(C#\)](#)

## Remarks

This method differs from `IModelDoc2::ViewZoomtofit` method only in that it zooms in closer to the geometry and has less of a border.

## See Also

[IModelDoc2 Interface](#)  
[IModelDoc2 Members](#)  
[IModelDoc2::ViewZoomin Method](#)  
[IModelDoc2::ViewZoomout Method](#)  
[IModelDoc2::ViewZoomto Method](#)  
[IModelDoc2::ViewZoomTo2 Method](#)  
[IModelDoc2::ViewZoomToSelection Method](#)  
[IModelDoc2::ViewOrientationUndo Method](#)  
[IModelDoc2::ViewRotate Method](#)  
[IModelDoc2::ViewRotateminusx Method](#)  
[IModelDoc2::ViewRotateminusy Method](#)  
[IModelDoc2::ViewRotateminusz Method](#)  
[IModelDoc2::ViewRotateplusx Method](#)  
[IModelDoc2::ViewRotateplusy Method](#)  
[IModelDoc2::ViewRotateplusz Method](#)  
[IModelDoc2::ViewRotXMinusNinety Method](#)  
[IModelDoc2::ViewRotXPlusNinety Method](#)  
[IModelDoc2::ViewRotYMinusNinety Method](#)  
[IModelDoc2::ViewRotYPlusNinety Method](#)  
[IModelDocExtension::ViewZoomToSheet Method](#)

## Availability

SOLIDWORKS 2001Plus FCS, Revision Number 10.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

## ViewZoomToSelection Method (IModelDoc2)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc2 Interface](#) : ViewZoomToSelection Method (IModelDoc2)

Zooms the display to the selection.

## .NET Syntax

Visual Basic (Declaration)

```
Sub ViewZoomToSelection()
```

Visual Basic (Usage)

```
Dim instance As IModelDoc2  
instance.ViewZoomToSelection()
```

C#

```
void ViewZoomToSelection()
```

C++/CLI

```
void ViewZoomToSelection();
```

**NOTE:** See [Differences Between Unmanaged C++ and C++/CLI Code](#).

## Visual Basic for Applications (VBA) Syntax

See [ModelDoc2::ViewZoomToSelection](#).

## Example

[Copy and Paste Feature \(C#\)](#)  
[Copy and Paste Feature \(VB.NET\)](#)

[Copy and Paste Feature \(VBA\)](#)

## See Also

[IModelDoc2 Interface](#)  
[IModelDoc2 Members](#)  
[IModelDoc2::ViewZoomin Method](#)  
[IModelDoc2::ViewZoomout Method](#)  
[IModelDoc2::ViewZoomto Method](#)  
[IModelDoc2::ViewZoomTo2 Method](#)  
[IModelDoc2::ViewZoomtofit2 Method](#)  
[IModelDoc2::ViewOrientationUndo Method](#)  
[IModelDoc2::ViewRotate Method](#)  
[IModelDoc2::ViewRotateminusx Method](#)  
[IModelDoc2::ViewRotateminusy Method](#)  
[IModelDoc2::ViewRotateminusz Method](#)  
[IModelDoc2::ViewRotateplusx Method](#)  
[IModelDoc2::ViewRotateplusy Method](#)  
[IModelDoc2::ViewRotateplusz Method](#)  
[IModelDoc2::ViewRotXMinusNinety Method](#)  
[IModelDoc2::ViewRotXPlusNinety Method](#)  
[IModelDoc2::ViewRotYMinusNinety Method](#)  
[IModelDoc2::ViewRotYPlusNinety Method](#)  
[IModelDocExtension::ViewZoomToSheet Method](#)

## Availability

SOLIDWORKS 2001Plus FCS, Revision Number 10.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

## Visible Property (IModelDoc2)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc2 Interface](#) : Visible Property (IModelDoc2)

Gets or sets the visibility of the active document.

## .NET Syntax

Visual Basic (Declaration)

Property Visible As System.Boolean

Visual Basic (Usage)



```
Dim instance As IModelDoc2  
Dim value As System.Boolean  
  
instance.Visible = value  
  
value = instance.Visible
```

C#

```
System.bool Visible {get; set;}
```

C++/CLI

```
property System.bool Visible {  
    System.bool get();  
    void set ( & System.bool value);  
}
```

**NOTE:** See [Differences Between Unmanaged C++ and C++/CLI Code](#).

### Property Value

True if the document is visible, false if not

## Visual Basic for Applications (VBA) Syntax

See [ModelDoc2::Visible](#).

## Example

[Get Names of Open Documents \(VBA\)](#)  
[Run or Attach to SOLIDWORKS Session \(VBA\)](#)  
[Get Names of Components, Window Handles, and DIBSECTIONS \(C#\)](#)  
[Get Names of Components, Window Handles, and DIBSECTIONS \(VB.NET\)](#)  
[Get Names of Components, Window Handles, and DIBSECTIONS \(VBA\)](#)

## Remarks

User-interface resources are not released by setting this property to false. Opening large numbers of models and then hiding them using this property will eventually cause critical resource shortages and instability.

Instead of setting this property to false to hide a document, consider calling [ISldWorks::CloseDoc](#) to release its user-interface resources. Or open the document invisibly using [ISldWorks::DocumentVisible](#).

## See Also

[IModelDoc2 Interface](#)  
[IModelDoc2 Members](#)

## Availability

SOLIDWORKS 2001Plus FCS, Revision Number 10.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

## WindowRedraw Method (IModelDoc2)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc2 Interface](#) : WindowRedraw Method (IModelDoc2)

Redraws the current window.

## .NET Syntax

Visual Basic (Declaration)

```
Sub WindowRedraw()
```

Visual Basic (Usage)



```
Dim instance As IModelDoc2
```

```
instance.WindowRedraw()
```

C#

```
void WindowRedraw()
```

C++/CLI

```
void WindowRedraw();
```

**NOTE:** See [Differences Between Unmanaged C++ and C++/CLI Code](#).

## Visual Basic for Applications (VBA) Syntax

See [ModelDoc2::WindowRedraw](#).

## Example

[Insert a Note \(VBA\)](#)  
[Running or Attaching to a SOLIDWORKS Session \(VBA\)](#)  
[Anchor a Note \(C#\)](#)  
[Anchor a Note \(VB.NET\)](#)  
[Anchor a Note \(VBA\)](#)

## Remarks

The current window includes the FeatureManager design tree view and the graphics area or graphics areas if you are using the window splitter.

## See Also

[IModelDoc2 Interface](#)  
[IModelDoc2 Members](#)  
[IModelDoc2::GraphicsRedraw2 Method](#)  
[IModelView::DrawHighlightedItems Method](#)  
[IModelView::DrawTransparentFeatureTree Method](#)  
[IModelView::SuppressWaitCursorDuringRedraw Property](#)

## Availability

SOLIDWORKS 2001Plus FCS, Revision Number 10.0