

SOLIDWORKS API (.NET VBA C#) — Reference (197/337): IModelDocExtension (part 3 of 8)

SOLIDWORKS API Documentation (converted from CHM)

IModelDocExtension (part 3 of 8) (Type)

ForceRebuildAll Method (IModelDocExtension)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDocExtension Interface](#) : ForceRebuildAll Method (IModelDocExtension)

Forces a rebuild of all features in all configurations without activating each configuration.

.NET Syntax

Visual Basic (Declaration)

```
Function ForceRebuildAll() As System.Boolean
```

Visual Basic (Usage)



```
Dim instance As IModelDocExtension  
Dim value As System.Boolean
```

```
value = instance.ForceRebuildAll()
```

C#

```
System.bool ForceRebuildAll()
```

C++/CLI

```
System.bool ForceRebuildAll();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Return Value

True if all features in all configurations are rebuilt without activating each configuration, false if not

Visual Basic for Applications (VBA) Syntax

See [ModelDocExtension::ForceRebuildAll](#).

Example

[Rebuild All Features in All Configurations \(C#\)](#)
[Rebuild All Features in All Configurations \(VB.NET\)](#)
[Rebuild All Features in All Configurations \(VBA\)](#)

See Also

[IModelDocExtension Interface](#)
[IModelDocExtension Members](#)
[IModelDocExtension::EditRebuildAll Method \(\)](#)
[IModelDocExtension::Rebuild Method \(\)](#)
[IModelDocExtension::NeedsRebuild2 Property \(\)](#)
[IModelDoc2::EditRebuild3 Method \(\)](#)
[IModelDoc2::ForceRebuild3 Method \(\)](#)
[IConfiguration::NeedsRebuild Property \(\)](#)
[IConfiguration::AddRebuildSaveMark Property \(\)](#)
[IConfigurationManager::AddRebuildSaveMark Method \(\)](#)

Availability

SOLIDWORKS 2017 FCS, Revision Number 25.0

GeodesicSketchOffset Method (IModelDocExtension)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDocExtension Interface](#) : GeodesicSketchOffset Method (IModelDocExtension)

Creates a geodesic sketch offset along the curvature of a surface.

■ .NET Syntax

Visual Basic (Declaration)

```
Function GeodesicSketchOffset( _  
    ByVal Offset As System.Double, _  
    ByVal Reverse As System.Boolean, _  
    ByVal MakeConstruct As System.Boolean _  
) As System.Boolean
```

Visual Basic (Usage)



```
Dim instance As IModelDocExtension  
Dim Offset As System.Double  
Dim Reverse As System.Boolean  
Dim MakeConstruct As System.Boolean  
Dim value As System.Boolean  
  
value = instance.GeodesicSketchOffset(Offset, Reverse, MakeConstruct)
```

C#

```
System.bool GeodesicSketchOffset(  
    System.double Offset,  
    System.bool Reverse,  
    System.bool MakeConstruct  
)
```

C++/CLI

```
System.bool GeodesicSketchOffset(  
& System.double Offset,  
& System.bool Reverse,  
& System.bool MakeConstruct  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Offset

Offset distance

Reverse

True to reverse the offset direction, false to not

MakeConstruct

True to make sketch construction geometry after offsetting, false to not

Return Value

True if the sketch offset is created, false if not

■ Visual Basic for Applications (VBA) Syntax

See [ModelDocExtension::GeodesicSketchOffset](#).

■ Remarks

To create a Euclidean sketch offset, use [IModelDocExtension::SketchOffsetOnSurface](#).

Before calling this method, call [IModelDocExtension::SelectByID2](#) for each edge to offset and set Append to true and Mark to 1.

After calling this method, call [ISketchManager::InsertSketch](#) to rebuild the model with the 3D sketch.

■ See Also

[IModelDocExtension Interface](#)

[IModelDocExtension Members](#)

[ISketchManager::SketchOffset2 Method \(\)](#)

[IModelDoc2::SketchOffsetEdges Method \(\)](#)

[IModelDoc2::SketchOffsetEntities2 Method \(\)](#)

■ Availability

Get3DExperienceModelType Method (IModelDocExtension)

[See Also](#)[SolidWorks.Interop.sldworks Namespace](#) > [IModelDocExtension Interface](#) : Get3DExperienceModelType Method (IModelDocExtension)

Gets the type of 3DEXPERIENCE application that owns this model.

.NET Syntax

Visual Basic (Declaration)

```
Function Get3DExperienceModelType() As System.Integer
```

Visual Basic (Usage)



```
Dim instance As IModelDocExtension
Dim value As System.Integer

value = instance.Get3DExperienceModelType()
```

C#

```
System.int Get3DExperienceModelType()
```

C++/CLI

```
System.int Get3DExperienceModelType();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).**Return Value**Type of 3DEXPERIENCE owner as defined by [sw3DExperienceModelType_e](#)

Visual Basic for Applications (VBA) Syntax

See [ModelDocExtension::Get3DExperienceModelType](#).

See Also

[IModelDocExtension Interface](#)
[IModelDocExtension Members](#)

Availability

SOLIDWORKS 2021 FCS, Revision Number 29

Get3DView Method (IModelDocExtension)

[See Also](#)[SolidWorks.Interop.sldworks Namespace](#) > [IModelDocExtension Interface](#) : Get3DView Method (IModelDocExtension)

Gets the 3D View with the specified name for this part or assembly.

.NET Syntax

Visual Basic (Declaration)

```
Function Get3DView( _
    ByVal Name As System.String _
) As View3D
```

Visual Basic (Usage)



```
Dim instance As IModelDocExtension  
Dim Name As System.String  
Dim value As View3D  
  
value = instance.Get3DView(Name)
```

C#

```
View3D Get3DView(  
    System.string Name  
)
```

C++/CLI

```
View3D^ Get3DView(  
& System.String^ Name  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Name
Name of 3D View to get

Return Value

[IView3D](#)

Visual Basic for Applications (VBA) Syntax

See [ModelDocExtension::Get3DView](#).

Remarks

This method requires that the SOLIDWORKS MBD add-in be loaded. ([ISldWorks::LoadAddIn](#))

See Also

[IModelDocExtension Interface](#)
[IModelDocExtension Members](#)
[IModelDocExtension::Get3DViews Method \(\)](#)
[IModelDocExtension::Capture3DView Method \(\)](#)
[IModelDocExtension::Refresh3DViews Method \(\)](#)
[IModelDocExtension::Get3DViewCount Method \(\)](#)
[IModelDocExtension::Get3DViewNames Method \(\)](#)

Availability

SOLIDWORKS 2015 FCS, Revision Number 23.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

Get3DViewCount Method (IModelDocExtension)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDocExtension Interface](#) : Get3DViewCount Method (IModelDocExtension)

Gets the number of [3D Views](#) in this part or assembly.

.NET Syntax

Visual Basic (Declaration)

```
Function Get3DViewCount() As System.Integer
```

Visual Basic (Usage)

```
Dim instance As IModelDocExtension  
Dim value As System.Integer
```



Copy Code

```
value = instance.Get3DViewCount()
```

C#

```
System.int Get3DViewCount()
```

C++/CLI

```
System.int Get3DViewCount();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Return Value

Number of 3D Views

Visual Basic for Applications (VBA) Syntax

See [ModelDocExtension::Get3DViewCount](#).

Example

[Capture 3D View \(VBA\)](#)
[Capture 3D View \(VB.NET\)](#)
[Capture 3D View \(C#\)](#)

Remarks

This method requires that the SOLIDWORKS MBD add-in be loaded. ([ISldWorks::LoadAddIn](#))

See Also

[IModelDocExtension Interface](#)
[IModelDocExtension Members](#)
[IModelDocExtension::Capture3DView Method \(\)](#)
[IModelDocExtension::Refresh3DViews Method \(\)](#)
[IModelDocExtension::Get3DView Method \(\)](#)
[IModelDocExtension::Get3DViewNames Method \(\)](#)
[IModelDocExtension::Get3DViews Method \(\)](#)

Availability

SOLIDWORKS 2015 FCS, Revision Number 23.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

Get3DViewNames Method (IModelDocExtension)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDocExtension Interface](#) : Get3DViewNames Method (IModelDocExtension)

Gets names of the [3D Views](#) in this part or assembly.

.NET Syntax

Visual Basic (Declaration)

```
Function Get3DViewNames() As System.Object
```

Visual Basic (Usage)



```
Dim instance As IModelDocExtension  
Dim value As System.Object
```

```
value = instance.Get3DViewNames()
```

C#

```
System.object Get3DViewNames()
```

C++/CLI

```
System.Object^ Get3DViewNames();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Return Value

Array of the names of the 3D Views

Visual Basic for Applications (VBA) Syntax

See [ModelDocExtension::Get3DViewNames](#).

Example

[Capture 3D View \(VBA\)](#)
[Capture 3D View \(VB.NET\)](#)
[Capture 3D View \(C#\)](#)

Remarks

This method requires that the SOLIDWORKS MBD add-in be loaded. ([ISldWorks::LoadAddIn](#))

See Also

[IModelDocExtension Interface](#)
[IModelDocExtension Members](#)
[IModelDocExtension::Capture3DView Method \(\)](#)
[IModelDocExtension::Refresh3DViews Method \(\)](#)
[IModelDocExtension::Get3DView Method \(\)](#)
[IModelDocExtension::Get3DViewCount Method \(\)](#)
[IModelDocExtension::Get3DViews Method \(\)](#)

Availability

SOLIDWORKS 2015 FCS, Revision Number 23.0

SOLIDWORKS API Help

[Send comments](#) on this topic.

Get3DViews Method (IModelDocExtension)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDocExtension Interface](#) : Get3DViews Method (IModelDocExtension)

Gets the 3D Views for this part or assembly.

.NET Syntax

Visual Basic (Declaration)

```
Function Get3DViews() As System.Object
```

Visual Basic (Usage)



```
Dim instance As IModelDocExtension  
Dim value As System.Object  
  
value = instance.Get3DViews()
```

C#

```
System.object Get3DViews()
```

C++/CLI

```
System.Object^ Get3DViews();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Return Value

Array of [IView3Ds](#)

Visual Basic for Applications (VBA) Syntax

See [ModelDocExtension::Get3DViews](#).

Remarks

This method requires that the SOLIDWORKS MBD add-in be loaded. ([ISldWorks::LoadAddIn](#))

See Also

[IModelDocExtension Interface](#)
[IModelDocExtension Members](#)
[IModelDocExtension::Refresh3DViews Method \(\)](#)
[IModelDocExtension::Capture3DView Method \(\)](#)
[IModelDocExtension::Get3DView Method \(\)](#)
[IModelDocExtension::Get3DViewCount Method \(\)](#)
[IModelDocExtension::Get3DViewNames Method \(\)](#)

Availability

SOLIDWORKS 2015 FCS, Revision Number 23.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

GetActiveAnnotationView Method (IModelDocExtension)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDocExtension Interface](#) : GetActiveAnnotationView Method (IModelDocExtension)

Gets the active annotation view of this model.

.NET Syntax

Visual Basic (Declaration)

```
Function GetActiveAnnotationView() As System.Object
```

Visual Basic (Usage)



```
Dim instance As IModelDocExtension  
Dim value As System.Object  
  
value = instance.GetActiveAnnotationView()
```

C#

```
System.Object GetActiveAnnotationView()
```

C++/CLI

```
System.Object^ GetActiveAnnotationView();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Return Value

[IAnnotationView](#)

Visual Basic for Applications (VBA) Syntax

See [ModelDocExtension::GetActiveAnnotationView](#).

See Also

[IModelDocExtension Interface](#)
[IModelDocExtension Members](#)

Availability

GetActivePropertyManagerPage Method (IModelDocExtension)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDocExtension Interface](#) : GetActivePropertyManagerPage Method (IModelDocExtension)

Gets the name of the active PropertyManager page.

.NET Syntax

Visual Basic (Declaration)

```
Function GetActivePropertyManagerPage() As System.String
```

Visual Basic (Usage)



```
Dim instance As IModelDocExtension
Dim value As System.String

value = instance.GetActivePropertyManagerPage()
```

C#

```
System.string GetActivePropertyManagerPage()
```

C++/CLI

```
System.String^ GetActivePropertyManagerPage();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Return Value

Name of the active PropertyManager page

Visual Basic for Applications (VBA) Syntax

See [ModelDocExtension::GetActivePropertyManagerPage](#).

Example

[Get Active PropertyManager Page Name \(C#\)](#)
[Get Active PropertyManager Page Name \(VB.NET\)](#)
[Get Active PropertyManager Page Name \(VBA\)](#)

See Also

[IModelDocExtension Interface](#)
[IModelDocExtension Members](#)
[IPropertyManagerPage2 Interface](#)

Availability

SOLIDWORKS 2011 FCS, Revision Number 19.0

GetAdvancedSaveAsOptions Method (IModelDocExtension)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDocExtension Interface](#) : GetAdvancedSaveAsOptions Method (IModelDocExtension)

Gets the advanced **File** > **Save As** options.

.NET Syntax

Visual Basic (Declaration)

```
Function GetAdvancedSaveAsOptions( _  
    ByVal Options As System.Integer _  
) As System.Object
```

Visual Basic (Usage)



```
Dim instance As IModelDocExtension  
Dim Options As System.Integer  
Dim value As System.Object  
  
value = instance.GetAdvancedSaveAsOptions(Options)
```

C#

```
System.object GetAdvancedSaveAsOptions(  
    System.int Options  
)
```

C++/CLI

```
System.Object^ GetAdvancedSaveAsOptions(  
& System.int Options  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Options
Save with references options as defined in [swSaveWithReferencesOptions](#) (see **Remarks**)

Return Value

[IAdvancedSaveAsOptions](#)

Visual Basic for Applications (VBA) Syntax

See [ModelDocExtension::GetAdvancedSaveAsOptions](#).

Example

See the [IAdvancedSaveAsOptions](#) example.

Remarks

Call this method before calling [IModelDocExtension::SaveAs3](#).

[IAdvancedSaveAsOptions::GetItemsNameAndPath](#) returns a list of items according to how the Options parameter is specified in this method.

See Also

[IModelDocExtension Interface](#)
[IModelDocExtension Members](#)

Availability

SOLIDWORKS 2020 SP02, Revision Number 28.2

SOLIDWORKS API Help

[Send comments on this topic.](#)

GetAdvancedSpotLightProperties Method (IModelDocExtension)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDocExtension Interface](#) : GetAdvancedSpotLightProperties Method (IModelDocExtension)

Gets the attenuation-related, advanced properties for the specified SOLIDWORKS spot light in this model.

.NET Syntax

```

Sub GetAdvancedSpotLightProperties( _
    ByVal Name As System.String, _
    ByRef Exponent As System.Double, _
    ByRef AttenuationConst As System.Double, _
    ByRef AttenuationLinear As System.Double, _
    ByRef AttenuationQuad As System.Double _
)

```



```

Dim instance As IModelDocExtension
Dim Name As System.String
Dim Exponent As System.Double
Dim AttenuationConst As System.Double
Dim AttenuationLinear As System.Double
Dim AttenuationQuad As System.Double

```

```

instance.GetAdvancedSpotLightProperties(Name, Exponent, AttenuationConst, AttenuationLinear,
AttenuationQuad)

```

```

void GetAdvancedSpotLightProperties(
    System.string Name,
    out System.double Exponent,
    out System.double AttenuationConst,
    out System.double AttenuationLinear,
    out System.double AttenuationQuad
)

```

```

void GetAdvancedSpotLightProperties(
    & System.String^ Name,
    & [Out] System.double Exponent,
    & [Out] System.double AttenuationConst,
    & [Out] System.double AttenuationLinear,
    & [Out] System.double AttenuationQuad
)

```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Name
SOLIDWORKS light source name

Exponent
Attenuation exponent

AttenuationConst
Constant attenuation factor

AttenuationLinear
Linear attenuation factor

AttenuationQuad
Quadratic attenuation factor

Visual Basic for Applications (VBA) Syntax

See [ModelDocExtension::GetAdvancedSpotLightProperties](#).

Example

[Get Advanced Properties of Spot Light \(VBA\)](#)

Remarks

See the SOLIDWORKS Help for more information about the advanced properties of spot lights.

See Also

Availability

SOLIDWORKS 2008 FCS, Revision Number 16.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

GetAnnotationCount Method (IModelDocExtension)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDocExtension Interface](#) : GetAnnotationCount Method (IModelDocExtension)

Gets the number of annotations on this part.

.NET Syntax

Visual Basic (Declaration)

```
Function GetAnnotationCount() As System.Integer
```

Visual Basic (Usage)



```
Dim instance As IModelDocExtension  
Dim value As System.Integer  
  
value = instance.GetAnnotationCount()
```

C#

```
System.int GetAnnotationCount()
```

C++/CLI

```
System.int GetAnnotationCount();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Return Value

Number of annotations

Visual Basic for Applications (VBA) Syntax

See [ModelDocExtension::GetAnnotationCount](#).

Remarks

Call this method before calling [IModelDocExtension::IGetAnnotations](#).

See Also

[IModelDocExtension Interface](#)
[IModelDocExtension Members](#)
[IModelDocExtension::GetAnnotations Method](#)
[IAnnotation Interface](#)
[IView::GetAnnotationCount Method](#)
[IModelDocExtension::GetAnnotationsByType Method\(\)](#)

Availability

SOLIDWORKS 2005 FCS, Revision Number 13.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

GetAnnotations Method (IModelDocExtension)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDocExtension Interface](#) : GetAnnotations Method (IModelDocExtension)

Gets the annotations on this part.

.NET Syntax

Visual Basic (Declaration)

```
Function GetAnnotations() As System.Object
```

Visual Basic (Usage)



```
Dim instance As IModelDocExtension  
Dim value As System.Object  
  
value = instance.GetAnnotations()
```

C#

```
System.object GetAnnotations()
```

C++/CLI

```
System.Object^ GetAnnotations();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Return Value

Array of [annotations](#)

Visual Basic for Applications (VBA) Syntax

See [ModelDocExtension::GetAnnotations](#).

Example

[Get Annotations \(VBA\)](#)
[Get Annotations \(VB.NET\)](#)
[Get Annotations \(C#\)](#)

Remarks

See Also

[IModelDocExtension Interface](#)
[IModelDocExtension Members](#)
[IModelDocExtension::GetAnnotationCount Method](#)
[IModelDocExtension::IGetAnnotations Method](#)
[IView::GetAnnotations Method](#)
[IModelDocExtension::GetAnnotationsByType Method\(\)](#)

Availability

SOLIDWORKS 2005 FCS, Revision Number 13.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

GetAnnotationsByType Method (IModelDocExtension)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDocExtension Interface](#) : GetAnnotationsByType Method (IModelDocExtension)

Gets the annotations of the specified type in this document.

.NET Syntax

Visual Basic (Declaration)

```
Function GetAnnotationsByType( _  
    ByVal Type As System.Integer _  
) As System.Object
```

```
Dim instance As IModelDocExtension  
Dim Type As System.Integer  
Dim value As System.Object  
  
value = instance.GetAnnotationsByType(Type)
```

C#

```
System.Object GetAnnotationsByType(  
    System.int Type  
)
```

C++/CLI

```
System.Object^ GetAnnotationsByType(  
    & System.int Type  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Type
Annotation type as defined by [swAnnotationType_e](#) (see **Remarks**)

Return Value

Array of [annotations](#)

Visual Basic for Applications (VBA) Syntax

See [ModelDocExtension::GetAnnotationsByType](#).

Remarks

This method does not support swAnnotationType_e.swCThread for parts and assemblies, because in those models cosmetic threads are added as sub-features of holes, not annotations.

See Also

[IModelDocExtension Interface](#)
[IModelDocExtension Members](#)
[IModelDocExtension::GetAnnotations Method \(\)](#)
[IModelDocExtension::GetAnnotationCount Method \(\)](#)
[IView::GetAnnotationsByType Method \(\)](#)

Availability

SOLIDWORKS 2025 SP02, Revision Number 33.2

SOLIDWORKS API Help

[Send comments](#) on this topic.

GetAppearanceSetting Method (IModelDocExtension)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDocExtension Interface](#) : GetAppearanceSetting Method (IModelDocExtension)

Gets the appearance setting for this document.

.NET Syntax

Visual Basic (Declaration)

```
Function GetAppearanceSetting() As AppearanceSetting
```

Visual Basic (Usage)

```
Dim instance As IModelDocExtension  
Dim value As AppearanceSetting  
  
value = instance.GetAppearanceSetting()
```

C#

```
AppearanceSetting GetAppearanceSetting()
```

C++/CLI

```
AppearanceSetting^ GetAppearanceSetting();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Return Value

[IAppearanceSetting](#)

Visual Basic for Applications (VBA) Syntax

See [ModelDocExtension::GetAppearanceSetting](#).

Remarks

After calling this method:

1. Set the properties in the [IAppearanceSetting](#) object.
2. Call [IModelDocExtension::GetDisplayStateSetting](#) to obtain an [IDisplayStateSetting](#) object.
3. Call [IDisplayStateSetting::Names](#) or [IDisplayStateSetting::SetNames](#) to specify the display states.
4. Call [IDisplayStateSetting::Entities](#) or [IDisplayStateSetting::SetEntities](#) to specify the components.
5. Call [IDisplayStateSetting::Option](#) to specify the scope of the display state setting.
6. Get or set the material properties for the specified display states, components, and scope using [IModelDocExtension::DisplayStateSpecMaterialPropertyValues](#).

See Also

[IModelDocExtension Interface](#)
[IModelDocExtension Members](#)

Availability

SOLIDWORKS 2012 FCS, Revision Number 20.0

SOLIDWORKS API Help

[Send comments](#) on this topic.

GetAttachmentCount Method (IModelDocExtension)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDocExtension Interface](#) : GetAttachmentCount Method (IModelDocExtension)

Gets the number of attachments for this document.

.NET Syntax

Visual Basic (Declaration)

```
Function GetAttachmentCount() As System.Integer
```

Visual Basic (Usage)



```
Dim instance As IModelDocExtension  
Dim value As System.Integer  
  
value = instance.GetAttachmentCount()
```

C#

```
System.int GetAttachmentCount()
```

C++/CLI

```
System.int GetAttachmentCount();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Return Value

Number of Attachments for this document

Visual Basic for Applications (VBA) Syntax

See [ModelDocExtension::GetAttachmentCount](#).

Remarks

This method is supported by SOLIDWORKS 2005 and later.

Call this method before calling [IModelDocExtension::!GetAttachments](#) to determine the size of the array for that method.

See Also

[IModelDocExtension Interface](#)
[IModelDocExtension Members](#)
[IModelDocExtension::DeleteAttachment Method](#)
[IModelDocExtension::GetAttachments Method](#)
[IModelDocExtension::InsertAttachment Method](#)

Availability

SOLIDWORKS 2005 FCS, Revision Number 13.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

GetAttachments Method (IModelDocExtension)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDocExtension Interface](#) : GetAttachments Method (IModelDocExtension)

Gets the attachments for this document.

.NET Syntax

Visual Basic (Declaration)

```
Function GetAttachments( _  
    ByRef LinkedVar As System.Object _  
) As System.Object
```

Visual Basic (Usage)



```
Dim instance As IModelDocExtension  
Dim LinkedVar As System.Object  
Dim value As System.Object  
  
value = instance.GetAttachments(LinkedVar)
```

C#

```
System.object GetAttachments(  
    out System.object LinkedVar  
)
```

C++/CLI

```
System.Object^ GetAttachments(  
    & [Out] System.Object^ LinkedVar  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

LinkedVar

Array of VARIANT_BOOL values indicating if a document is linked or not

Return Value

Array of strings of the names of the attachments for this document

Visual Basic for Applications (VBA) Syntax

See [ModelDocExtension::GetAttachments](#).

Remarks

This method is supported by SOLIDWORKS 2005 and later.

There is a one-to-one correspondence between the output arrays.

See Also

[IModelDocExtension Interface](#)
[IModelDocExtension Members](#)
[IModelDocExtension::DeleteAttachment Method](#)
[IModelDocExtension::GetAttachmentCount Method](#)
[IModelDocExtension::GetAttachments Method](#)
[IModelDocExtension::InsertAttachment Method](#)

Availability

SOLIDWORKS 2005 FCS, Revision Number 13.0

SOLIDWORKS API Help

[Send comments](#) on this topic.

GetCalloutVariableString Method (IModelDocExtension)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDocExtension Interface](#) : GetCalloutVariableString Method (IModelDocExtension)

Gets the string for the specified callout variable.

.NET Syntax

Visual Basic (Declaration)

```
Function GetCalloutVariableString( _  
    ByVal Variable As System.Integer _  
) As System.String
```

Visual Basic (Usage)



```
Dim instance As IModelDocExtension  
Dim Variable As System.Integer  
Dim value As System.String  
  
value = instance.GetCalloutVariableString(Variable)
```

C#

```
System.string GetCalloutVariableString(  
    System.int Variable  
)
```

C++/CLI

```
System.String^ GetCalloutVariableString(  
    & System.int Variable  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Variable

Callout variable as defined in [swCalloutVariable_e](#)

Return Value

Callout variable string

Visual Basic for Applications (VBA) Syntax

See [ModelDocExtension::GetCalloutVariableString](#).

Example

[Create Advanced Hole \(VBA\)](#)
[Create Advanced Hole \(VB.NET\)](#)
[Create Advanced Hole \(C#\)](#)

See Also

[IModelDocExtension Interface](#)
[IModelDocExtension Members](#)
[IAdvancedHoleElementData::CalloutString_Property\(\)](#)

Availability

SOLIDWORKS 2018 FCS, Revision Number 26.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

GetCameraById Method (IModelDocExtension)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDocExtension Interface](#) : GetCameraById Method (IModelDocExtension)

Gets a camera using the specified camera ID.

.NET Syntax

Visual Basic (Declaration)

```
Function GetCameraById( _  
    ByVal CameraId As System.Integer _  
) As Camera
```

Visual Basic (Usage)



```
Dim instance As IModelDocExtension  
Dim CameraId As System.Integer  
Dim value As Camera  
  
value = instance.GetCameraById(CameraId)
```

C#

```
Camera GetCameraById(  
    System.int CameraId  
)
```

C++/CLI

```
Camera^ GetCameraById(  
& System.int CameraId  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

CameraId
Camera ID (see **Remarks**)

Return Value

[Camera](#)

Visual Basic for Applications (VBA) Syntax

See [ModelDocExtension::GetCameraById](#).

Example

[Turn Cameras On and Off \(VBA\)](#)

Remarks

A valid ID is $0 \leq \text{ID} \leq (\text{IModelDocExtension::GetCameraCount} - 1)$.

CameraId is reassigned if there are multiple cameras and one of those cameras is deleted. For example:

If...	And Camera2 is deleted, then...
CameraId = 1 for Camera1	CameraId = 1 for Camera1
CameraId = 2 for Camera2	Deleted
CameraId = 3 for Camera3	CameraId = 2 for Camera3

See Also

[IModelDocExtension Interface](#)
[IModelDocExtension Members](#)
[ICamera::GetCameraDefinition Method](#)
[IModelDocExtension::InsertCamera Method](#)

Availability

SOLIDWORKS 2006 FCS, Revision Number 14.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

GetCameraCount Method (IModelDocExtension)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDocExtension Interface](#) : GetCameraCount Method (IModelDocExtension)

Gets the number of cameras in the document.

.NET Syntax

Visual Basic (Declaration)

```
Function GetCameraCount() As System.Integer
```

Visual Basic (Usage)



```
Dim instance As IModelDocExtension  
Dim value As System.Integer
```

```
value = instance.GetCameraCount()
```

C#

```
System.int GetCameraCount()
```

C++/CLI

```
System.int GetCameraCount();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Return Value

Number of cameras in the document

Visual Basic for Applications (VBA) Syntax

See [ModelDocExtension::GetCameraCount](#).

Example

[Turn Cameras On and Off \(VBA\)](#)

See Also

[IModelDocExtension Interface](#)
[IModelDocExtension Members](#)
[IModelDocExtension::GetCameraById Method](#)
[IModelDocExtension::GetCameraDefinition Method](#)
[IModelDocExtension::InsertCamera Method](#)

Availability

SOLIDWORKS 2006 FCS, Revision Number 14.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

GetCameraDefinition Method (IModelDocExtension)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDocExtension Interface](#) : GetCameraDefinition Method (IModelDocExtension)

Gets a camera, but does not add the newly created camera to the model.

.NET Syntax

Visual Basic (Declaration)

```
Function GetCameraDefinition() As Camera
```

Visual Basic (Usage)



```
Dim instance As IModelDocExtension  
Dim value As Camera  
  
value = instance.GetCameraDefinition()
```

C#

```
Camera GetCameraDefinition()
```

C++/CLI

```
Camera^ GetCameraDefinition();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Visual Basic for Applications (VBA) Syntax

See [ModelDocExtension::GetCameraDefinition](#).

Remarks

The model is unchanged.

You should find this method helpful when developing a renderer add-in.

See Also

[IModelDocExtension Interface](#)
[IModelDocExtension Members](#)
[IModelDocExtension::InsertCamera Method](#)
[IModelDocExtension::GetCameraById Method](#)
[IModelDocExtension::GetCameraCount Method](#)

Availability

SOLIDWORKS 2007 FCS, Revision Number 15.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

GetCommandTabs Method (IModelDocExtension)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDocExtension Interface](#) : GetCommandTabs Method (IModelDocExtension)

Gets all of the SOLIDWORKS CommandManager tab names in this document.

.NET Syntax

Visual Basic (Declaration)

```
Function GetCommandTabs() As System.Object
```

Visual Basic (Usage)



```
Dim instance As IModelDocExtension  
Dim value As System.Object  
  
value = instance.GetCommandTabs()
```

C#

```
System.Object GetCommandTabs()
```

C++/CLI

```
System.Object^ GetCommandTabs();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Return Value

Array of CommandManager tab names

Visual Basic for Applications (VBA) Syntax

See [ModelDocExtension::GetCommandTabs](#).

Example

[Activate SOLIDWORKS CommandManager Tab \(VBA\)](#)
[Activate SOLIDWORKS CommandManager Tab \(VB.NET\)](#)
[Activate SOLIDWORKS CommandManager Tab \(C#\)](#)

Remarks

To activate and query the add-in CommandManager tabs, call [ICommandManager::CommandTabs](#).

See Also

[IModelDocExtension Interface](#)
[IModelDocExtension Members](#)
[ICommandManager::GetCommandTab Method \(\)](#)
[ICommandManager::IGetCommandTabs Method \(\)](#)
[ICommandManager::GetCommandTabCount Method \(\)](#)
[IModelDocExtension::ActiveCommandTab Property \(\)](#)
[IModelDocExtension::ActiveCommandTabIndex Property \(\)](#)
[IModelDocExtension::CommandTabVisible Property \(\)](#)

Availability

SOLIDWORKS 2014 FCS, Revision Number 22.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

GetCoordinateSystemTransformByName Method (IModelDocExtension)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDocExtension Interface](#) : GetCoordinateSystemTransformByName Method (IModelDocExtension)

Gets the transform of the specified coordinate system.

.NET Syntax

Visual Basic (Declaration)

```
Function GetCoordinateSystemTransformByName( _  
    ByVal NameIn As System.String _  
) As MathTransform
```

Visual Basic (Usage)



```
Dim instance As IModelDocExtension  
Dim NameIn As System.String  
Dim value As MathTransform  
  
value = instance.GetCoordinateSystemTransformByName(NameIn)
```

C#

```
MathTransform GetCoordinateSystemTransformByName(  
    System.string NameIn  
)
```

C++/CLI

```
MathTransform^ GetCoordinateSystemTransformByName(  
    & System.String^ NameIn  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

NameIn
Name of the coordinate system

Return Value

[Math transform](#)

Visual Basic for Applications (VBA) Syntax

See [ModelDocExtension::GetCoordinateSystemTransformByName](#).

Example

[Get Coordinate System Transform \(VBA\)](#)
[Get Table-driven Pattern Properties \(VBA\)](#)

See Also

[IModelDocExtension Interface](#)
[IModelDocExtension Members](#)
[IModelDoc2::GetCurrentCoordinateSystemName Method](#)
[IModelDoc2::InsertCoordinateSystem Method](#)

Availability

SOLIDWORKS 2003 SP3, Revision Number 11.3

SOLIDWORKS API Help

[Send comments](#) on this topic.

GetCorresponding Method (IModelDocExtension)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDocExtension Interface](#) : GetCorresponding Method (IModelDocExtension)

Obsolete. Superseded by [IModelDocExtension::GetCorresponding2](#).

Visual Basic Syntax

Visual Basic (Declaration)

```
Function GetCorresponding( _  
    ByVal InputObject As System.Object _  
) As System.Object
```

Visual Basic (Usage)



```
Dim instance As IModelDocExtension  
Dim InputObject As System.Object  
Dim value As System.Object  
  
value = instance.GetCorresponding(InputObject)
```

C#

```
System.object GetCorresponding(  
    System.object InputObject  
)
```

C++/CLI

```
System.Object^ GetCorresponding(  
& System.Object^ InputObject  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

InputObject

Pointer to the Dispatch object in the assembly context

Return Value

Pointer to the corresponding object in the underlying part, assembly, or subassembly document

Visual Basic for Applications (VBA) Syntax

See [ModelDocExtension::GetCorresponding](#).

Example

[Get Corresponding Note in Assembly \(VBA\)](#)
[Get Corresponding Note in Part \(VBA\)](#)

Remarks

Given an object in an assembly context, this method gets the corresponding object in the underlying component document regardless of whether the document is a part or an assembly.

You can use this method with any object assigned a persistent reference ID; for example, a [IFeature](#), [IAnnotation](#) or [ISketch](#) object.

See Also

[IModelDocExtension Interface](#)
[IModelDocExtension Members](#)
[IModelDocExtension::GetCorrespondingEntity Method](#)
[IComponent2::GetCorresponding Method](#)
[IComponent2::GetCorrespondingEntity Method](#)
[IComponent2::IGetCorrespondingEntity Method](#)

Availability

SOLIDWORKS 2007 SP1, Revision Number 15.1



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDocExtension Interface](#) : GetCorresponding2 Method (IModelDocExtension)

Gets the object in the underlying part or subassembly document that corresponds to the specified input object in this drawing view or assembly.

VB.NET Syntax

Visual Basic (Declaration)

```
Function GetCorresponding2( _  
    ByVal InputObject As System.Object _  
) As System.Object
```

Visual Basic (Usage)



```
Dim instance As IModelDocExtension  
Dim InputObject As System.Object  
Dim value As System.Object  
  
value = instance.GetCorresponding2(InputObject)
```

C#

```
System.object GetCorresponding2(  
    System.object InputObject  
)
```

C++/CLI

```
System.Object^ GetCorresponding2(  
& System.Object^ InputObject  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

InputObject

Object in this drawing view or assembly (see **Remarks**)

Return Value

Corresponding object in the underlying part or subassembly; null or Nothing if none found (see **Remarks**)

Visual Basic for Applications (VBA) Syntax

See [ModelDocExtension::GetCorresponding2](#).

Example

[Get Corresponding Entities Between Parts and Drawing Views \(VBA\)](#)
[Get Corresponding Entities Between Parts and Drawing Views \(VB.NET\)](#)
[Get Corresponding Entities Between Parts and Drawing Views \(C#\)](#)

Remarks

InputObject can be any object assigned a persistent reference ID; for example, a [IFeature](#), [IAnnotation](#) or [ISketch](#) object.

To get the assembly object corresponding to a given component object, use [IComponent2::GetCorresponding](#).

To get the drawing view object corresponding to a given part or assembly object, use [IView::GetCorresponding](#).

See Also

[IModelDocExtension Interface](#)
[IModelDocExtension Members](#)
[IModelDocExtension::GetCorrespondingEntity2 Method \(\)](#)

Availability

GetCorrespondingEntity Method (IModelDocExtension)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDocExtension Interface](#) : GetCorrespondingEntity Method (IModelDocExtension)

Obsolete. Superseded by [IModelDocExtension::GetCorrespondingEntity2](#).

.NET Syntax

Visual Basic (Declaration)

```
Function GetCorrespondingEntity( _  
    ByVal Entity As System.Object _  
) As System.Object
```

Visual Basic (Usage)



```
Dim instance As IModelDocExtension  
Dim Entity As System.Object  
Dim value As System.Object
```

```
value = instance.GetCorrespondingEntity(Entity)
```

C#

```
System.object GetCorrespondingEntity(  
    System.object Entity  
)
```

C++/CLI

```
System.Object^ GetCorrespondingEntity(  
& System.Object^ Entity  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Entity

Dispatch pointer to a [vertex](#), [face](#), or [edge](#) entity

Return Value

Dispatch pointer to the corresponding entity in the context of the component

Visual Basic for Applications (VBA) Syntax

See [ModelDocExtension::GetCorrespondingEntity](#).

Example

[Get Part for Corresponding Component \(VBA\)](#)
[Open Part from Assembly \(VBA\)](#)

See Also

[IModelDocExtension Interface](#)
[IModelDocExtension Members](#)
[IComponent2::GetCorresponding Method](#)
[IComponent2::GetCorrespondingEntity Method](#)
[IComponent2::GetCorrespondingEntity2 Method](#)
[IModelDocExtension::GetCorrespondingEntity Method](#)

Availability

SOLIDWORKS 2007 SP1, Revision Number 15.1

GetCorrespondingEntity2 Method (IModelDocExtension)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDocExtension Interface](#) : GetCorrespondingEntity2 Method (IModelDocExtension)

Gets the entity in the underlying part or subassembly that corresponds to the specified entity in this assembly or drawing view.

.NET Syntax

Visual Basic (Declaration)

```
Function GetCorrespondingEntity2( _  
    ByVal Entity As System.Object _  
) As System.Object
```

Visual Basic (Usage)



```
Dim instance As IModelDocExtension  
Dim Entity As System.Object  
Dim value As System.Object
```

```
value = instance.GetCorrespondingEntity2(Entity)
```

C#

```
System.object GetCorrespondingEntity2(  
    System.object Entity  
)
```

C++/CLI

```
System.Object^ GetCorrespondingEntity2(  
& System.Object^ Entity  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Entity

Dispatch pointer to a [vertex](#), [face](#), or [edge](#) entity in this drawing view or assembly

Return Value

Corresponding [entity](#) in the underlying part or subassembly; null or Nothing if none found (see **Remarks**)

Visual Basic for Applications (VBA) Syntax

See [ModelDocExtension::GetCorrespondingEntity2](#).

Example

[Get Corresponding Entities Between Parts and Drawing Views \(VBA\)](#)
[Get Corresponding Entities Between Parts and Drawing Views \(VB.NET\)](#)
[Get Corresponding Entities Between Parts and Drawing Views \(C#\)](#)

Remarks

To get the assembly entity corresponding to a given component entity, use [IComponent2::GetCorrespondingEntity](#).

To get the drawing view entity corresponding to a given part or assembly entity, use [IView::GetCorrespondingEntity](#).

See Also

[IModelDocExtension Interface](#)
[IModelDocExtension Members](#)
[IModelDocExtension::GetCorresponding2 Method \(\)](#)

Availability

GetCostingManager Method (IModelDocExtension)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDocExtension Interface](#) : GetCostingManager Method (IModelDocExtension)

Gets the entry-point interface to the SOLIDWORKS Costing API and gets the CostingManager.

.NET Syntax

Visual Basic (Declaration)

```
Function GetCostingManager() As System.Object
```

Visual Basic (Usage)



```
Dim instance As IModelDocExtension
Dim value As System.Object

value = instance.GetCostingManager()
```

C#

```
System.object GetCostingManager()
```

C++/CLI

```
System.Object^ GetCostingManager();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Return Value

[ICostManager](#)

Visual Basic for Applications (VBA) Syntax

See [ModelDocExtension::GetCostingManager](#).

Example

[Create Machining Costing Analysis \(C#\)](#)
[Create Machining Costing Analysis \(VB.NET\)](#)
[Create Machining Costing Analysis \(VBA\)](#)
[Create Sheet Metal Costing Analysis \(C#\)](#)
[Create Sheet Metal Costing Analysis \(VB.NET\)](#)
[Create Sheet Metal Costing Analysis \(VBA\)](#)

Remarks

SOLIDWORKS Costing and its API are only available in SOLIDWORKS Professional and SOLIDWORKS Premium.

See Also

[IModelDocExtension Interface](#)
[IModelDocExtension Members](#)

Availability

SOLIDWORKS API 2013 FCS, Revision Number 21.0

GetCSYSDistances Method (IModelDocExtension)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDocExtension Interface](#) : GetCSYSDistances Method (IModelDocExtension)

Gets the specified distances between two selected coordinate systems.

■ .NET Syntax

Visual Basic (Declaration)

```
Function GetCSYSDistances( _  
    ByRef TotDistance As System.Double, _  
    ByRef XDistance As System.Double, _  
    ByRef YDistance As System.Double, _  
    ByRef ZDistance As System.Double _  
) As System.Boolean
```

Visual Basic (Usage)



```
Dim instance As IModelDocExtension  
Dim TotDistance As System.Double  
Dim XDistance As System.Double  
Dim YDistance As System.Double  
Dim ZDistance As System.Double  
Dim value As System.Boolean  
  
value = instance.GetCSYSDistances(TotDistance, XDistance, YDistance, ZDistance)
```

C#

```
System.bool GetCSYSDistances(  
    out System.double TotDistance,  
    out System.double XDistance,  
    out System.double YDistance,  
    out System.double ZDistance  
)
```

C++/CLI

```
System.bool GetCSYSDistances(  
& [Out] System.double TotDistance,  
& [Out] System.double XDistance,  
& [Out] System.double YDistance,  
& [Out] System.double ZDistance  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

TotDistance
Distance between origins
XDistance
Distance between X axes
YDistance
Distance between Y axes
ZDistance
Distance between Z axes

Return Value

True if distances successfully retrieved, false if not

■ Visual Basic for Applications (VBA) Syntax

See [ModelDocExtension::GetCSYSDistances](#).

■ Remarks

This method corresponds to the SOLIDWORKS measure tool's calculation of distance between two coordinate systems. See **SOLIDWORKS online help > Fundamentals > Measure Tool** for more information.

■ See Also

[IModelDocExtension Interface](#)
[IModelDocExtension Members](#)
[IModelDocExtension::GetCSYSEulersAngularRotation Method\(\)](#)
[IModelDocExtension::GetCSYSXYZAngularRotation Method\(\)](#)

Availability

SOLIDWORKS 2024 SP01, Revision Number 32.1

SOLIDWORKS API Help

[Send comments on this topic.](#)

GetCSYSEulersAngularRotation Method (IModelDocExtension)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDocExtension Interface](#) : GetCSYSEulersAngularRotation Method (IModelDocExtension)

Gets the specified Eulers angular rotation values that transform one selected coordinate system into another.

Visual Basic Syntax

Visual Basic (Declaration)

```
Function GetCSYSEulersAngularRotation( _  
    ByRef phiAngle As System.Double, _  
    ByRef thetaAngle As System.Double, _  
    ByRef psiAngle As System.Double _  
    ) As System.Boolean
```

Visual Basic (Usage)



```
Dim instance As IModelDocExtension  
Dim phiAngle As System.Double  
Dim thetaAngle As System.Double  
Dim psiAngle As System.Double  
Dim value As System.Boolean  
  
value = instance.GetCSYSEulersAngularRotation(phiAngle, thetaAngle, psiAngle)
```

C#

```
System.bool GetCSYSEulersAngularRotation(  
    out System.double phiAngle,  
    out System.double thetaAngle,  
    out System.double psiAngle  
)
```

C++/CLI

```
System.bool GetCSYSEulersAngularRotation(  
& [Out] System.double phiAngle,  
& [Out] System.double thetaAngle,  
& [Out] System.double psiAngle  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

phiAngle

Roll or rotation about the longitudinal axis (see **Remarks**)

thetaAngle

Pitch or rotation about the lateral axis (see **Remarks**)

psiAngle

Yaw or rotation about the vertical axis (see **Remarks**)

Return Value

True if rotation values successfully retrieved, false if not

Visual Basic for Applications (VBA) Syntax

See [ModelDocExtension::GetCSYSEulersAngularRotation](#).

Remarks

phiAngle is the roll or rotation about the longitudinal axis. Rolling corresponds to moving one side of an object upward while moving the other side downward (no pitch or yaw).

thetaAngle is the pitch or rotation around the lateral axis. Pitching corresponds to tilting the front of an object up or down (no yaw or roll).

psiAngle is the yaw or rotation about the vertical axis. Yawing corresponds to turning the front of an object left or right (no pitch or roll).

This method corresponds to the SOLIDWORKS measure tool's calculation of angular rotation between two coordinate systems. See **SOLIDWORKS online help > Fundamentals > Measure Tool** for more information.

Use Wikipedia to learn more about Euler's angles.

See Also

[IModelDocExtension Interface](#)
[IModelDocExtension Members](#)
[IModelDocExtension::GetCSYSDistances Method \(\)](#)
[IModelDocExtension::GetCSYSXYZAngularRotation Method \(\)](#)

Availability

SOLIDWORKS 2024 SP01, Revision Number 32.1

SOLIDWORKS API Help

[Send comments on this topic.](#)

GetCSYSXYZAngularRotation Method (IModelDocExtension)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDocExtension Interface](#) : GetCSYSXYZAngularRotation Method (IModelDocExtension)

Gets the specified Tait-Bryan angular rotation values that transform one selected coordinate system into another.

.NET Syntax

Visual Basic (Declaration)

```
Function GetCSYSXYZAngularRotation( _  
    ByRef XAngle As System.Double, _  
    ByRef YAngle As System.Double, _  
    ByRef ZAngle As System.Double _  
) As System.Boolean
```

Visual Basic (Usage)



```
Dim instance As IModelDocExtension  
Dim XAngle As System.Double  
Dim YAngle As System.Double  
Dim ZAngle As System.Double  
Dim value As System.Boolean
```

```
value = instance.GetCSYSXYZAngularRotation(XAngle, YAngle, ZAngle)
```

C#

```
System.bool GetCSYSXYZAngularRotation(  
    out System.double XAngle,  
    out System.double YAngle,  
    out System.double ZAngle  
)
```

C++/CLI

```
System.bool GetCSYSXYZAngularRotation(  
& [Out] System.double XAngle,  
& [Out] System.double YAngle,  
& [Out] System.double ZAngle  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

XAngle
Angle of rotation between x axes
YAngle
Angle of rotation between y axes
ZAngle
Angle of rotation between z axes

Return Value

True if rotation values successfully retrieved, false if not

Visual Basic for Applications (VBA) Syntax

See [ModelDocExtension::GetCSYSXYZAngularRotation](#).

Remarks

This method corresponds to the SOLIDWORKS measure tool's calculation of angular rotation between two coordinate systems. See **SOLIDWORKS online help > Fundamentals > Measure Tool** for more information.

Use Wikipedia to learn about Tait-Bryan or Cardan angles.

See Also

[IModelDocExtension Interface](#)
[IModelDocExtension Members](#)
[IModelDocExtension::GetCSYSDistances Method \(\)](#)
[IModelDocExtension::GetCSYSEulersAngularRotation Method \(\)](#)

Availability

SOLIDWORKS 2024 SP01, Revision Number 32.1

SOLIDWORKS API Help

[Send comments](#) on this topic.

GetDecal Method (IModelDocExtension)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDocExtension Interface](#) : GetDecal Method (IModelDocExtension)

Gets the specified decal in this model.

.NET Syntax

Visual Basic (Declaration)

```
Function GetDecal( _  
    ByVal ID As System.Integer, _  
    ByVal Configuration As System.String _  
) As Decal
```

Visual Basic (Usage)



```
Dim instance As IModelDocExtension  
Dim ID As System.Integer  
Dim Configuration As System.String  
Dim value As Decal
```

```
value = instance.GetDecal(ID, Configuration)
```

C#

```
Decal GetDecal(  
    System.int ID,  
    System.string Configuration  
)
```

C++/CLI

```
Decal^ GetDecal(  
& System.int ID,  
& System.String^ Configuration  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

ID
Decal ID (see **Remarks**)
Configuration

Name of the configuration where to get the decal

Return Value

[Decal](#)

 Visual Basic for Applications (VBA) Syntax

See [ModelDocExtension::GetDecal](#).

 Example

[Get Mask Types of Each Decal \(VBA\)](#)

 Remarks

The decal ID is the index number of the decal in the model. Call [IModelDocExtension::GetDecalsCount](#) to find out the number of decals in the model and their IDs.

 See Also

[IModelDocExtension Interface](#)
[IModelDocExtension Members](#)
[IDecal Interface](#)
[IModelDocExtension::AddDecal Method](#)
[IModelDocExtension::CreateDecal Method](#)
[IModelDocExtension::DeleteAllDecals Method](#)
[IModelDocExtension::DeleteDecal Method](#)
[IModelDocExtension::GetDecals Method](#)
[IModelDocExtension::GetDecalsCount Method](#)
[IModelDocExtension::HideDecal Method](#)
[IModelDocExtension::IGetDecals Method](#)
[IModelDocExtension::MoveDecal Method](#)
[IModelDocExtension::ReverseDecalsOrder Method](#)

 Availability

SOLIDWORKS 2008 FCS, Revision Number 16.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

GetDecals Method (IModelDocExtension)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDocExtension Interface](#) : GetDecals Method (IModelDocExtension)

Gets the decals applied to the model.

 .NET Syntax

Visual Basic (Declaration)

```
Function GetDecals() As System.Object
```

Visual Basic (Usage)

```
Dim instance As IModelDocExtension  
Dim value As System.Object  
  
value = instance.GetDecals()
```

C#

```
System.object GetDecals()
```

C++/CLI

```
System.Object^ GetDecals();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Return Value

Array of [decals](#)

Visual Basic for Applications (VBA) Syntax

See [ModelDocExtension::GetDecals](#).

See Also

[IModelDocExtension Interface](#)
[IModelDocExtension Members](#)
[IModelDocExtension::IDecal Interface](#)
[IModelDocExtension::AddDecal Method](#)
[IModelDocExtension::CreateDecal Method](#)
[IModelDocExtension::DeleteDecal Method](#)
[IModelDocExtension::DeleteAllDecals Method](#)
[IModelDocExtension::GetDecal Method](#)
[IModelDocExtension::GetDecalsCount Method](#)
[IModelDocExtension::HideDecal Method](#)
[IModelDocExtension::IGetDecals Method](#)
[IModelDocExtension::MoveDecal Method](#)
[IModelDocExtension::ReverseDecalsOrder Method](#)

Availability

SOLIDWORKS 2008 FCS, Revision Number 16.0

SOLIDWORKS API Help

[Send comments](#) on this topic.

GetDecalsCount Method (IModelDocExtension)

See Also [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDocExtension Interface](#) : GetDecalsCount Method (IModelDocExtension)

Gets the number of decals applied to this model.

.NET Syntax

Visual Basic (Declaration)

```
Function GetDecalsCount() As System.Integer
```

Visual Basic (Usage)



```
Dim instance As IModelDocExtension  
Dim value As System.Integer  
  
value = instance.GetDecalsCount()
```

C#

```
System.int GetDecalsCount()
```

C++/CLI

```
System.int GetDecalsCount();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Return Value

Number of decals applied to this model

Visual Basic for Applications (VBA) Syntax

See [ModelDocExtension::GetDecalsCount](#).

Example

[Get Mask Types of Each Decal \(VBA\)](#)

Remarks

Call this method before calling [IModelDocExtension::GetDecals](#) to get the size of the array for that method.

See Also

[IModelDocExtension Interface](#)
[IModelDocExtension Members](#)
[IDecal Interface](#)
[IModelDocExtension::AddDecal Method](#)
[IModelDocExtension::CreateDecal Method](#)
[IModelDocExtension::DeleteAllDecals Method](#)
[IModelDocExtension::DeleteDecal Method](#)
[IModelDocExtension::GetDecal Method](#)
[IModelDocExtension::GetDecals Method](#)
[IModelDocExtension::HideDecal Method](#)
[IModelDocExtension::MoveDecal Method](#)
[IModelDocExtension::ReverseDecalsOrder Method](#)

Availability

SOLIDWORKS 2008 FCS, Revision Number 16.0

SOLIDWORKS API Help

[Send comments](#) on this topic.

GetDependencies Method (IModelDocExtension)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDocExtension Interface](#) : GetDependencies Method (IModelDocExtension)

Gets all of this model's dependencies.

.NET Syntax

Visual Basic (Declaration)

```
Function GetDependencies( _  
    ByVal Traverseflag As System.Boolean, _  
    ByVal Searchflag As System.Boolean, _  
    ByVal AddReadOnlyInfo As System.Boolean, _  
    ByVal ListBrokenRefs As System.Boolean, _  
    ByVal AppendImportedPaths As System.Boolean _  
) As System.Object
```

Visual Basic (Usage)



```
Dim instance As IModelDocExtension  
Dim Traverseflag As System.Boolean  
Dim Searchflag As System.Boolean  
Dim AddReadOnlyInfo As System.Boolean  
Dim ListBrokenRefs As System.Boolean  
Dim AppendImportedPaths As System.Boolean  
Dim value As System.Object
```

```
value = instance.GetDependencies(Traverseflag, Searchflag, AddReadOnlyInfo, ListBrokenRefs,  
AppendImportedPaths)
```

C#

```
System.object GetDependencies(  
    System.bool Traverseflag,  
    System.bool Searchflag,  
    System.bool AddReadOnlyInfo,  
    System.bool ListBrokenRefs,  
    System.bool AppendImportedPaths  
)
```

C++/CLI

```
System.Object^ GetDependencies(  
& System.bool Traverseflag,  
& System.bool Searchflag,  
& System.bool AddReadOnlyInfo,  
& System.bool ListBrokenRefs,  
& System.bool AppendImportedPaths  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Traverseflag

True to traverse all dependency levels, false to get first level (see **Remarks**)

Searchflag

True to use the search rules to find dependencies, false to look where the documents were last saved (see **Remarks**)

AddReadOnlyInfo

True to show read-only information in the returned strings, false to not (see **Remarks**)

ListBrokenRefs

True to get broken references, false to not

AppendImportedPaths

True to append imported path names, false to not (see **Remarks**)

Return Value

Array of strings (see **Remarks**)

Visual Basic for Applications (VBA) Syntax

See [ModelDocExtension::GetDependencies](#).

Example

```
'This example shows how to return all of the dependent files
'for the specied active assembly.

'VBA

'Preconditions:
'1. Open public_documents\SOLIDWORKS\SOLIDWORKS 2021\samples\tutorial\api\arm2.sldasm.
'2. Open the Immediate window.
'3. Optionally set a breakpoint after vDepend is set so you can inspect its contents.

'Postconditions:
'Inspect the Immediate window.

Option Explicit
Sub main()
    Dim swApp                As SldWorks.SldWorks
    Dim swModel              As SldWorks.ModelDoc2
    Dim vDepend              As Variant
    Dim i                    As Long

    Set swApp = CreateObject("SldWorks.Application")
    Set swModel = swApp.ActiveDoc

    vDepend = swModel.Extension.GetDependencies(True, True, True, True, True)

    Debug.Print swModel.GetPathName
    For i = 0 To (UBound(vDepend)) / 3 - 1
        Debug.Print "    " + vDepend(2 * i + i) + " --> Read-only: " + vDepend(2 * i + (i + 2))
    Next i
End Sub
```

Remarks

Calling this method on a drawing document returns a list of all the parts and assemblies used in the drawing. If you set *Traverseflag* to true, then each of the parts within the assembly file is also returned in this array of strings.

Because a derived mirror part is generated from another part, the list of model dependencies returned by this method would include the original part used to generate the derived mirror part.

Library features are completely unassociated. They do not require the library nor do they update when changes are made to the library feature. Therefore, this method does not return library features.

If you use this method with an assembly that contains two documents, Part1 and SubAssem1, an example of what might be returned is:

```
[ "Part1", "C:\temp\Part1.SLDPRPT", "SubAssem1", "c:\temp\SubAssem1.SLDASM" ]
```

If *Traverseflag* is set to true, then all the documents contained in SubAssem1.ASM are returned. Also, suppressed components are recognized and returned by this method as a dependent file.

If *AddReadOnlyInfo* is set to true, then a string of "TRUE" or "FALSE" is added to the list of strings. If Part1 and SubAssem1 are read-only, then the resulting set of strings would be:

```
[ "Part1", "C:\temp\Part1.SLDPRPT", "TRUE", "SubAssem1", "c:\temp\SubAssem1.SLDASM", "FALSE" ]
```

If AppendImportedPaths is set to true, and Part1 was imported, "*imported_file_path*" is appended to the Part1 path. The resulting set of strings would be:

```
[ "Part1", "C:\temp\Part1.SLDPRPT|c:\temp\Creo - Copy\table_wf2.asm.1", "TRUE", "SubAssem1", "c:\temp\SubAssem1.SLDASM", "FALSE" ]
```

NOTE: For assemblies containing suppressed or lightweight components, file references (return value from this method) point to the as-saved component reference because the actual component has not been loaded into memory. Because the suppressed and lightweight components have not actually been loaded, the current search criteria has not been applied to update the file references. Setting Searchflag to true causes this method to apply the current search criteria rules to locate the particular reference and may result in a different return value. Likewise, unsuppressing or resolving these components causes the current search criteria to be applied and updates the assembly's component references in memory, if necessary.

When calling this method with Searchflag set to true, you can explicitly set the search folders first. This is important because this method uses the current SOLIDWORKS directory as its second search criteria. Because the user may have interactively opened files from some random directory, you cannot be certain the current SOLIDWORKS directory is pointing to the desired location. You may want to consider setting the search folders to that of the document being used in this method.

See Also

[IModelDocExtension Interface](#)
[IModelDocExtension Members](#)
[IModelDoc2::GetNumDependencies Method \(\)](#)
[ISldWorks::GetDocumentDependencies2 Method \(\)](#)

Availability

SOLIDWORKS 2018 FCS, Revision Number 26.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

GetDisplayStateSetting Method (IModelDocExtension)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDocExtension Interface](#) : GetDisplayStateSetting Method (IModelDocExtension)

Gets the display state setting for the specified scope.

.NET Syntax

Visual Basic (Declaration)

```
Function GetDisplayStateSetting( _  
    ByVal Option As System.Integer _  
) As DisplayStateSetting
```

Visual Basic (Usage)



```
Dim instance As IModelDocExtension  
Dim Option As System.Integer  
Dim value As DisplayStateSetting  
  
value = instance.GetDisplayStateSetting(Option)
```

C#

```
DisplayStateSetting GetDisplayStateSetting(  
    System.int Option  
)
```

C++/CLI

```
DisplayStateSetting^ GetDisplayStateSetting(  
& System.int Option  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Option

Scope of the display state setting as defined in [swDisplayStateOpts e](#)

Return Value

[IDisplayStateSetting](#)

Visual Basic for Applications (VBA) Syntax

See [ModelDocExtension::GetDisplayStateSetting](#).

Example

[Get Display State Settings \(VBA\)](#)
[Get Display State Settings \(VB.NET\)](#)
[Get Display State Settings \(C#\)](#)
[Change Color of Component in Specific Display State \(C#\)](#)
[Change Color of Component in Specific Display State \(VB.NET\)](#)
[Change Color of Component in Specific Display State \(VBA\)](#)

Remarks

After calling this method:

1. Call [IDisplayStateSetting::Names](#) or [IDisplayStateSetting::SetNames](#) to specify the display states.
2. Call [IDisplayStateSetting::Entities](#) or [IDisplayStateSetting::SetEntities](#) to specify the components.
3. Get or set one or more of the following properties for the specified display states, components, and scope:
 - [IModelDocExtension::DisplayMode](#)
 - [IModelDocExtension::Transparency](#)
 - [IModelDocExtension::Visibility](#)
4. Call [IModelDocExtension::GetAppearanceSetting](#) to obtain the [IAppearanceSetting](#) object.
5. Set the properties in the [IAppearanceSetting](#) object.
6. Get or set the material properties for the specified display states, components, and scope using [IModelDocExtension::DisplayStateSpecMaterialPropertyValues](#).

See Also

[IModelDocExtension Interface](#)
[IModelDocExtension Members](#)

Availability

SOLIDWORKS 2012 FCS, Revision Number 20.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

GetDraftingStandardNames Method (IModelDocExtension)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDocExtension Interface](#) : GetDraftingStandardNames Method (IModelDocExtension)

Get the names of all currently available drafting standards.

.NET Syntax

Visual Basic (Declaration)

```
Function GetDraftingStandardNames() As System.Object
```

Visual Basic (Usage)



```
Dim instance As IModelDocExtension  
Dim value As System.Object  
  
value = instance.GetDraftingStandardNames()
```

C#

```
System.object GetDraftingStandardNames()
```

C++/CLI

```
System.Object^ GetDraftingStandardNames();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Return Value

Array of strings of the names of all currently available drafting standard names

Visual Basic for Applications (VBA) Syntax

See [ModelDocExtension::GetDraftingStandardNames](#).

Example

[Change Drafting Standard to Custom \(VBA\)](#)

See Also

[IModelDocExtension Interface](#)
[IModelDocExtension Members](#)
[IModelDocExtension::CopyDraftingStandard Method](#)
[IModelDocExtension::DeleteDraftingStandard Method](#)
[IModelDocExtension::LoadDraftingStandard Method](#)
[IModelDocExtension::RenameDraftingStandard Method](#)
[IModelDocExtension::SaveDraftingStandard Method](#)

Availability

SOLIDWORKS 2009 FCS, Revision Number 17.0

SOLIDWORKS API Help

[Send comments](#) on this topic.

GetFlattenSheetMetalPersistReference Method (IModelDocExtension)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDocExtension Interface](#) : GetFlattenSheetMetalPersistReference Method (IModelDocExtension)

Gets a byte array of persistent reference IDs for the specified entity (a face, edge, or vertex) in a flattened sheet metal part.

.NET Syntax

Visual Basic (Declaration)

```
Function GetFlattenSheetMetalPersistReference( _  
    ByVal DispObj As System.Object _  
) As System.Object
```

Visual Basic (Usage)



```
Dim instance As IModelDocExtension  
Dim DispObj As System.Object  
Dim value As System.Object  
  
value = instance.GetFlattenSheetMetalPersistReference(DispObj)
```

C#

```
System.object GetFlattenSheetMetalPersistReference(  
    System.object DispObj  
)
```

C++/CLI

```
System.Object^ GetFlattenSheetMetalPersistReference(  
    & System.Object^ DispObj  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

DispObj
Entity (a face, edge, or vertex) in the flattened sheet metal part whose persistent reference IDs you want

Return Value

Byte array of persistent reference IDs

Visual Basic for Applications (VBA) Syntax

See [ModelDocExtension::GetFlattenSheetMetalPersistReference](#).

Example

[Set and Get Sheet Metal Part's Persistent Reference IDs \(C#\)](#)
[Set and Get Sheet Metal Part's Persistent Reference IDs \(VB.NET\)](#)
[Set and Get Sheet Metal Part's Persistent Reference IDs \(VBA\)](#)

Remarks

The sheet metal part must be in the flattened state when this method is called. You can then pass the byte array of persistent reference IDs to [IModelDocExtension::GetSheetMetalObjectsByPersistReference](#) or [IModelDocExtension::!GetSheetMetalObjectsByPersistReference](#), which gets the objects that correspond to the persistent reference IDs in the folded configuration of the sheet metal part.

See [Persistent Reference IDs](#) for more information.

See Also

[IModelDocExtension Interface](#)
[IModelDocExtension Members](#)
[IModelDocExtension::GetObjectByPersistReference3 Method](#)
[IModelDocExtension::GetPersistReference3 Method](#)
[IModelDocExtension::GetPersistReferenceCount3 Method](#)
[IModelDocExtension::!GetObjectByPersistReference3 Method](#)
[IModelDocExtension::!GetPersistReference3 Method](#)

Availability

SOLIDWORKS 2010 FCS, Revision Number 18.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

GetGeneralTableAnnotation Method (IModelDocExtension)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDocExtension Interface](#) : GetGeneralTableAnnotation Method (IModelDocExtension)

Creates a general table annotation for SOLIDWORKS MBD 3D PDF.

.NET Syntax

Visual Basic (Declaration)

```
Function GetGeneralTableAnnotation( _  
    ByVal UseAnchorPoint As System.Boolean, _  
    ByVal X As System.Double, _  
    ByVal Y As System.Double, _  
    ByVal AnchorType As System.Integer, _  
    ByVal TableTemplate As System.String, _  
    ByVal Rows As System.Integer, _  
    ByVal Columns As System.Integer _  
) As TableAnnotation
```

Visual Basic (Usage)



```
Dim instance As IModelDocExtension  
Dim UseAnchorPoint As System.Boolean  
Dim X As System.Double  
Dim Y As System.Double  
Dim AnchorType As System.Integer  
Dim TableTemplate As System.String  
Dim Rows As System.Integer  
Dim Columns As System.Integer  
Dim value As TableAnnotation
```

```
value = instance.GetGeneralTableAnnotation(UseAnchorPoint, X, Y, AnchorType, TableTemplate, Rows,  
Columns)
```

C#

```

TableAnnotation GetGeneralTableAnnotation(
    System.bool UseAnchorPoint,
    System.double X,
    System.double Y,
    System.int AnchorType,
    System.string TableTemplate,
    System.int Rows,
    System.int Columns
)

```

C++/CLI

```

TableAnnotation^ GetGeneralTableAnnotation(
    & System.bool UseAnchorPoint,
    & System.double X,
    & System.double Y,
    & System.int AnchorType,
    & System.String^ TableTemplate,
    & System.int Rows,
    & System.int Columns
)

```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

UseAnchorPoint

True to anchor the table by AnchorType and ignore any coordinates specified by X and Y, false to use the coordinates specified by X and Y

X

X coordinate of this table annotation; valid only if UseAnchorPoint is false

Y

Y coordinate of this table annotation; valid only if UseAnchorPoint is false

AnchorType

Type of anchor as defined in [swBOMConfigurationAnchorType_e](#); valid only if UseAnchorPoint is true, and TableTemplate is empty (see **Remarks**)

TableTemplate

Path and file name of the general table template to use (see **Remarks**)

Rows

Number of rows in the table annotation; valid only if TableTemplate is empty (see **Remarks**)

Columns

Number of columns in the table annotation; valid only if TableTemplate is empty (see **Remarks**)

Return Value

[ITableAnnotation](#)

Visual Basic for Applications (VBA) Syntax

See [ModelDocExtension::GetGeneralTableAnnotation](#).

Example

[Create General Table Annotation for SOLIDWORKS MBD 3D PDF \(C#\)](#)
[Create General Table Annotation for SOLIDWORKS MBD 3D PDF \(VB.NET\)](#)
[Create General Table Annotation for SOLIDWORKS MBD 3D PDF \(VBA\)](#)

Remarks

If TableTemplate is...	Then this method..
A valid path and file name	Ignores AnchorType, Rows, and Columns and creates a general table annotation based on TableTemplate.
Empty	Creates a general table annotation using the specified parameters except TableTemplate.

This method creates an object for the specified table annotation, but it does not insert the table annotation in the model.

Use [IModelDocExtension::InsertGeneralTableAnnotation](#) to create and insert a table annotation in the model.

See Also

[IModelDocExtension Interface](#)
[IModelDocExtension Members](#)
[IMBD3DPdfData Interface](#)

Availability

SOLIDWORKS 2016 FCS, Revision Number 24.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

GetKeepLightInRenderScene Method (IModelDocExtension)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDocExtension Interface](#) : GetKeepLightInRenderScene Method (IModelDocExtension)

Gets whether a light is kept when the scene changes.

.NET Syntax

Visual Basic (Declaration)

```
Function GetKeepLightInRenderScene( _  
    ByVal ID As System.Integer _  
) As System.Boolean
```

Visual Basic (Usage)



```
Dim instance As IModelDocExtension  
Dim ID As System.Integer  
Dim value As System.Boolean  
  
value = instance.GetKeepLightInRenderScene(ID)
```

C#

```
System.bool GetKeepLightInRenderScene(  
    System.int ID  
)
```

C++/CLI

```
System.bool GetKeepLightInRenderScene(  
& System.int ID  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

ID
Light ID

Return Value

True if the light is kept when the scene changes, false if the light is deleted when the scene changes

Visual Basic for Applications (VBA) Syntax

See [ModelDocExtension::GetKeepLightInRenderScene](#).

See Also

[IModelDocExtension Interface](#)
[IModelDocExtension Members](#)
[IModelDocExtension::SetKeepLightInRenderScene Method](#)

SOLIDWORKS API Help

[Send comments on this topic.](#)

GetLastFeatureAdded Method (IModelDocExtension)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDocExtension Interface](#) : GetLastFeatureAdded Method (IModelDocExtension)

Gets the last feature added to the model.

.NET Syntax

Visual Basic (Declaration)

```
Function GetLastFeatureAdded() As Feature
```

Visual Basic (Usage)



```
Dim instance As IModelDocExtension  
Dim value As Feature  
  
value = instance.GetLastFeatureAdded()
```

C#

```
Feature GetLastFeatureAdded()
```

C++/CLI

```
Feature^ GetLastFeatureAdded();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Return Value

[Feature](#)

Visual Basic for Applications (VBA) Syntax

See [ModelDocExtension::GetLastFeatureAdded](#).

Remarks

This method can access subfeature types such as mates, drawing views, and so on. For example, if you just added the first coincident mate to MateGroup, then IModelDocExtension::GetLastFeatureAdded will return Coincident1. [IModelDoc2::FeatureByPositionReverse](#) and [IModelDoc2::IFeatureByPositionReverse](#) will return MateGroup.

See Also

[IModelDocExtension Interface](#)
[IModelDocExtension Members](#)

Availability

SOLIDWORKS 2004 FCS, Revision Number 12.0

SOLIDWORKS API Help

[Send comments](#) on this topic.

GetLicenseType Method (IModelDocExtension)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDocExtension Interface](#) : GetLicenseType Method (IModelDocExtension)

Gets the type of SOLIDWORKS license used when the model was created.

.NET Syntax

Visual Basic (Declaration)

```
Function GetLicenseType() As System.Integer
```

Visual Basic (Usage)



```
Dim instance As IModelDocExtension  
Dim value As System.Integer  
  
value = instance.GetLicenseType()
```

C#

```
System.int GetLicenseType()
```

C++/CLI

```
System.int GetLicenseType();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Return Value

Type of SOLIDWORKS license as defined in [swLicenseType_e](#)

Visual Basic for Applications (VBA) Syntax

See [ModelDocExtension::GetLicenseType](#).

Example

[Get License Type of SOLIDWORKS \(C#\)](#)
[Get License Type of SOLIDWORKS \(VB.NET\)](#)
[Get License Type of SOLIDWORKS \(VBA\)](#)

Remarks

This method always returns 0 (swLicenseType_e.swLicenseType_Full) for files saved under any commercial SOLIDWORKS license.

To get the license type of this SOLIDWORKS installation, use [ISldWorks::GetCurrentLicenseType](#).

See Also

[IModelDocExtension Interface](#)
[IModelDocExtension Members](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

GetLightEnabledInRender Method (IModelDocExtension)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDocExtension Interface](#) : GetLightEnabledInRender Method (IModelDocExtension)

Gets whether a light is on in this model.

.NET Syntax

Visual Basic (Declaration)

```
Function GetLightEnabledInRender( _  
    ByVal ID As System.Integer _  
) As System.Boolean
```

Visual Basic (Usage)



```
Dim instance As IModelDocExtension  
Dim ID As System.Integer  
Dim value As System.Boolean  
  
value = instance.GetLightEnabledInRender(ID)
```

C#

```
System.bool GetLightEnabledInRender(  
    System.int ID  
)
```

C++/CLI

```
System.bool GetLightEnabledInRender(  
& System.int ID  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

ID
Light ID

Return Value

True of the light is on, false if not

Visual Basic for Applications (VBA) Syntax

See [ModelDocExtension::GetLightEnabledInRender](#).

See Also

[IModelDocExtension Interface](#)
[IModelDocExtension Members](#)
[IModelDocExtension::SetLightEnabledInRender Method](#)

Availability

SOLIDWORKS 2008 FCS, Revision Number 16.0

SOLIDWORKS API Help

[Send comments](#) on this topic.

GetMassProperties Method (IModelDocExtension)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDocExtension Interface](#) : GetMassProperties Method (IModelDocExtension)

Obsolete. Superseded by [IModelDocExtension::GetMassProperties2](#).

.NET Syntax

Visual Basic (Declaration)

```
Function GetMassProperties( _  
    ByVal Accuracy As System.Integer, _  
    ByRef Status As System.Integer _  
) As System.Object
```

Visual Basic (Usage)



```
Dim instance As IModelDocExtension  
Dim Accuracy As System.Integer  
Dim Status As System.Integer  
Dim value As System.Object  
  
value = instance.GetMassProperties(Accuracy, Status)
```

C#

```
System.object GetMassProperties(  
    System.int Accuracy,  
    out System.int Status  
)
```

C++/CLI

```
System.Object^ GetMassProperties(  
    & System.int Accuracy,  
    & [Out] System.int Status  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Accuracy

- 0 = as is
- 1 = default
- 2 = maximum

Status

Status of the mass property results as defined in [swMassPropertiesStatus_e](#)

Return Value

Array of size 13 (see **Remarks**)

Visual Basic for Applications (VBA) Syntax

See [ModelDocExtension::GetMassProperties](#).

Remarks

The return value is a 0-based array of doubles as follows:

[CenterOfMassX, CenterOfMassY, CenterOfMassZ, Volume, Area, Mass, MomXX, MomYY, MomZZ, MomXY, MomZX, MomYZ, Accuracy]

You can use [ISldWorks::GetUserPreferenceDoubleValue](#) and `swMaterialPropertyDensity` to get the density of the SOLIDWORKS part. If the user did not explicitly set the density, then SOLIDWORKS uses a value of 1.0. You can also derive the density of the body by calculating:

Density = (Mass / Volume)

This method returns metric units unless specified otherwise.

If this object is...	Then...
An assembly	- SOLIDWORKS does not include any suppressed components in the mass property analysis. See IComponent2::GetSuppression to determine the state of each assembly component. - This method returns the moments of inertia (MOI) about the assembly center-of-gravity coordinate system aligned with the assembly axes.
A part	The calculated origin for the returned values are based on the default coordinate systems of the model document. They are not based on the selected coordinate system.

This method supports multibody parts.

See Also

[IModelDocExtension Interface](#)
[IModelDocExtension Members](#)
[IModelDocExtension::CreateMassProperty Method](#)
[IMassProperty Interface](#)
[IModelDocExtension::IGetMassProperties Method](#)
[IModelDocExtension::GetMassPropertiesSelectedComp Method](#)

Availability

SOLIDWORKS 2003 FCS, Revision Number 11.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

GetMassProperties2 Method (IModelDocExtension)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDocExtension Interface](#) : GetMassProperties2 Method (IModelDocExtension)

Obsolete. Superseded by [IMassProperty2](#).

.NET Syntax

Visual Basic (Declaration)

```
Function GetMassProperties2( _  
    ByVal Accuracy As System.Integer, _  
    ByRef Status As System.Integer, _  
    ByVal UseSelected As System.Boolean _  
) As System.Object
```

Visual Basic (Usage)

```
Dim instance As IModelDocExtension  
Dim Accuracy As System.Integer  
Dim Status As System.Integer
```



```
Dim UseSelected As System.Boolean
Dim value As System.Object

value = instance.GetMassProperties2(Accuracy, Status, UseSelected)
```

C#

```
System.Object GetMassProperties2(
    System.int Accuracy,
    out System.int Status,
    System.bool UseSelected
)
```

C++/CLI

```
System.Object^ GetMassProperties2(
    & System.int Accuracy,
    & [Out] System.int Status,
    & System.bool UseSelected
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Accuracy

- 0 = as is
- 1 = default
- 2 = maximum

Status

Error code as defined in [swMassPropertiesStatus_e](#)

UseSelected

True to return the mass properties of the selected components only, false to return the mass properties of the entire model, excluding suppressed components

Return Value

Array of size 12 (see **Remarks**)

Visual Basic for Applications (VBA) Syntax

See [ModelDocExtension::GetMassProperties2](#).

Example

[Get Mass Properties \(VBA\)](#)
[Get Mass Properties \(VB.NET\)](#)
[Get Mass Properties \(C#\)](#)

Remarks

If this model is...

An assembly

A part

Then pre-select...

Components for which to get mass properties. This method returns the center of mass and moments of inertia in the coordinate system of the assembly.

Solid bodies for which to get mass properties. The calculated origin for the returned values is based on the default coordinate system of the part. It is not based on the selected coordinate system.

The return value is a 0-based array of doubles as follows:

[CenterOfMassX, CenterOfMassY, CenterOfMassZ, Volume, SurfaceArea, Mass, MomXX, MomYY, MomZZ, MomXY, MomZX, MomYZ]

Where:

- Mom NN = NN -component of the moment of inertia taken at the center of mass and aligned with the output coordinate system

You can use [ISldWorks::GetUserPreferenceDoubleValue](#) and [swMaterialPropertyDensity](#) to get the density of the SOLIDWORKS part. If the user did not explicitly set the density, then SOLIDWORKS uses a value of 1.0. You can also derive the density of the body by calculating:

$$\text{Density} = (\text{Mass} / \text{Volume})$$

This method:

- returns values in metric units.
- supports multibody parts.

See Also

[IModelDocExtension Interface](#)
[IModelDocExtension Members](#)
[IModelDocExtension::CreateMassProperty Method \(\)](#)
[IMassProperty Interface](#)

Availability

SOLIDWORKS 2016 FCS, Revision Number 24.0

SOLIDWORKS API Help

[Send comments](#) on this topic.

GetMaterial Method (IModelDocExtension)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDocExtension Interface](#) : GetMaterial Method (IModelDocExtension)

Gets the appearance for the specified appearance ID in the specified configuration in this model document

.NET Syntax

Visual Basic (Declaration)

```
Function GetMaterial( _  
    ByVal ID As System.Integer, _  
    ByVal Configuration As System.String _  
) As RenderMaterial
```

Visual Basic (Usage)



```
Dim instance As IModelDocExtension  
Dim ID As System.Integer  
Dim Configuration As System.String  
Dim value As RenderMaterial
```

```
value = instance.GetMaterial(ID, Configuration)
```

C#

```
RenderMaterial GetMaterial(  
    System.int ID,  
    System.string Configuration  
)
```

C++/CLI

```
RenderMaterial^ GetMaterial(  
& System.int ID,  
& System.String^ Configuration  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

ID
Appearance Id
Configuration
Name of the configuration where the appearance is applied

Return Value

[Appearance](#)

Visual Basic for Applications (VBA) Syntax

See [ModelDocExtension::GetMaterial](#).

See Also

[IModelDocExtension Interface](#)
[IModelDocExtension Members](#)

[IRenderMaterial Interface](#)
[IModelDocExtension::AddDefaultRenderMaterial Method](#)
[IModelDocExtension::AddRenderMaterial Method](#)
[IModelDocExtension::CreateRenderMaterial Method](#)
[IModelDocExtension::DeleteRenderMaterial Method](#)
[IModelDocExtension::GetRenderMaterials Method](#)
[IModelDocExtension::GetRenderMaterialsCount Method](#)
[IModelDocExtension::IGetRenderMaterials Method](#)
[IModelDocExtension::UpdateRenderMaterialsInSceneGraph Method](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

GetMaterialPropertyValues Method (IModelDocExtension)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDocExtension Interface](#) : GetMaterialPropertyValues Method (IModelDocExtension)

Gets the material properties for this model document.

.NET Syntax

Visual Basic (Declaration)

```
Function GetMaterialPropertyValues( _  
    ByVal Config\_opt As System.Integer, _  
    ByVal Config\_names As System.Object _  
) As System.Object
```

Visual Basic (Usage)



```
Dim instance As IModelDocExtension  
Dim Config_opt As System.Integer  
Dim Config_names As System.Object  
Dim value As System.Object  
  
value = instance.GetMaterialPropertyValues(Config_opt, Config_names)
```

C#

```
System.object GetMaterialPropertyValues(  
    System.int Config\_opt,  
    System.object Config\_names  
)
```

C++/CLI

```
System.Object^ GetMaterialPropertyValues(  
& System.int Config\_opt,  
& System.Object^ Config\_names  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Config_opt
Configuration options as defined by [swInConfigurationOpts_e](#)
Config_names
Array of configuration names for this component

Return Value

Array of material values for this component (see **Remarks**)

Visual Basic for Applications (VBA) Syntax

See [ModelDocExtension::GetMaterialPropertyValues](#).

Remarks

The material values returned include the face color (R,G,B values), reflectivity (ambient, diffuse, specular, shininess), transparency, and emission.

The format of material_values is an array of doubles:

[*R*, *G*, *B*, *Ambient*, *Diffuse*, *Specular*, *Shininess*, *Transparency*, *Emission*]

Valid values are from 0 to 1 for all variables. If material_values is all -1 values, then material property values were not assigned to the feature. Therefore, the feature will have the default properties in the user interface.

See Also

[IModelDocExtension Interface](#)
[IModelDocExtension Members](#)
[IModelDocExtension::GetMaterialPropertyValues Method](#)
[IModelDocExtension::RemoveMaterialProperty Method](#)
[IModelDocExtension::SetMaterialPropertyValues Method](#)
[IModelDocExtension::HasMaterialPropertyValues Method](#)

Availability

SOLIDWORKS 2004 FCS, Revision Number 12.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

GetMBD3DPdfData Method (IModelDocExtension)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDocExtension Interface](#) : GetMBD3DPdfData Method (IModelDocExtension)

Gets the SOLIDWORKS MBD 3D PDF data object.

.NET Syntax

Visual Basic (Declaration)

```
Function GetMBD3DPdfData() As System.Object
```

Visual Basic (Usage)



```
Dim instance As IModelDocExtension  
Dim value As System.Object  
  
value = instance.GetMBD3DPdfData()
```

C#

```
System.object GetMBD3DPdfData()
```

C++/CLI

```
System.Object^ GetMBD3DPdfData();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Return Value

[IMBD3DPdfData](#) object

Visual Basic for Applications (VBA) Syntax

See [ModelDocExtension::GetMBD3DPdfData](#).

Example

[Publish Text and Custom Properties from Theme to MBD 3D PDF \(C#\)](#)
[Publish Text and Custom Properties from Theme to MBD 3D PDF \(VB.NET\)](#)
[Publish Text and Custom Properties from Theme to MBD 3D PDF \(VBA\)](#)

Remarks

SOLIDWORKS Model Based Definition (MBD) is an integrated drawingless manufacturing solution for SOLIDWORKS.

This method requires that the SOLIDWORKS MBD add-in be loaded. ([ISldWorks::LoadAddIn](#))

Typical steps for generating a SOLIDWORKS MBD 3D PDF using the SOLIDWORKS API are:

1. Get the MBD3DPdfData object using this method.
2. Set the path and file name of the SOLIDWORKS MBD 3D PDF theme using [IMBD3DPdfData::ThemeName](#).
3. Get standard and custom views using [IMBD3DPdfData::GetStandardViews](#) and [IMBD3DPdfData::GetMoreViews](#).

4. Set standard and custom views using [IMBD3DPdfData::SetStandardViews](#) and [IMBD3DPdfData::SetMoreViews](#).
5. Get and set text and custom properties in the theme using [IMBD3DPdfData::GetTextAndCustomProperties](#) and [ITextAndCustomProperty](#).
6. Set the path for the SOLIDWORKS MBD 3D PDF using [IMBD3DPdfData::FilePath](#).
7. Generate the SOLIDWORKS MBD 3D PDF using [IModelDocExtension::PublishTo3DPDF](#).
See the SOLIDWORKS Help for details about MBD.

See Also

[IModelDocExtension Interface](#)
[IModelDocExtension Members](#)
[IView3D Interface](#)

Availability

SOLIDWORKS 2016 FCS, Revision Number 24.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

GetMBDSTEP242Data Method (IModelDocExtension)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDocExtension Interface](#) : GetMBDSTEP242Data Method (IModelDocExtension)

Gets the SOLIDWORKS MBD STEP 242 data object.

.NET Syntax

Visual Basic (Declaration)

```
Function GetMBDSTEP242Data() As System.Object
```

Visual Basic (Usage)



```
Dim instance As IModelDocExtension  
Dim value As System.Object  
  
value = instance.GetMBDSTEP242Data()
```

C#

```
System.object GetMBDSTEP242Data()
```

C++/CLI

```
System.Object^ GetMBDSTEP242Data();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Return Value

[IMBDSTEP242Data](#)

Visual Basic for Applications (VBA) Syntax

See [ModelDocExtension::GetMBDSTEP242Data](#).

Example

See the IMBDSTEP242DATA example.

Remarks

SOLIDWORKS Model Based Definition (MBD) is an integrated drawingless manufacturing solution for SOLIDWORKS.

This method requires that the SOLDWORKS MBD add-in be loaded. ([ISldWorks::LoadAddIn](#))

See the SOLIDWORKS Help for details about MBD.

See Also

Availability

SOLIDWORKS 2025 SP03, Revision Number 33.3

SOLIDWORKS API Help

[Send comments](#) on this topic.

GetModelBreakViewNames Method (IModelDocExtension)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDocExtension Interface](#) : GetModelBreakViewNames Method (IModelDocExtension)

Gets the names and number of the Model Break Views in the current configuration of the active model.

.NET Syntax

Visual Basic (Declaration)

```
Function GetModelBreakViewNames( _  
    ByRef Views As System.Object _  
) As System.Integer
```

Visual Basic (Usage)



```
Dim instance As IModelDocExtension  
Dim Views As System.Object  
Dim value As System.Integer  
  
value = instance.GetModelBreakViewNames(Views)
```

C#

```
System.int GetModelBreakViewNames(  
    out System.object Views  
)
```

C++/CLI

```
System.int GetModelBreakViewNames(  
& [Out] System.Object^ Views  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Views
Names of Model Break Views

Return Value

Number of Model Break Views

Visual Basic for Applications (VBA) Syntax

See [ModelDocExtension::GetModelBreakViewNames](#).

Example

[Get Names and Show Model Break Views \(C#\)](#)
[Get Names and Show Model Break Views \(VB.NET\)](#)
[Get Names and Show Model Break Views \(VBA\)](#)

See Also

[IModelDocExtension Interface](#)
[IModelDocExtension Members](#)
[IModelDocExtension::ShowModelBreakView Method \(\)](#)
[IView3D::ModelBreakViewName Property \(\)](#)

Availability

SOLIDWORKS 2015 FCS, Revision Number 23.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

GetModelViewCount Method (IModelDocExtension)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDocExtension Interface](#) : GetModelViewCount Method (IModelDocExtension)

Gets the number of model views in this document.

.NET Syntax

Visual Basic (Declaration)

```
Function GetModelViewCount() As System.Integer
```

Visual Basic (Usage)



```
Dim instance As IModelDocExtension  
Dim value As System.Integer  
  
value = instance.GetModelViewCount()
```

C#

```
System.int GetModelViewCount()
```

C++/CLI

```
System.int GetModelViewCount();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Return Value

Number of model views (see **Remarks**)

Visual Basic for Applications (VBA) Syntax

See [ModelDocExtension::GetModelViewCount](#).

Example

[Get Scale Factor of Each Model View \(C++\)](#)
[Get Scale Factor of Each Model View \(C#\)](#)
[Get Scale Factor of Each Model View \(VB.NET\)](#)
[Get Scale Factor of Each Model View \(VBA\)](#)

Remarks

Call this method before calling [IModelDocExtension::IGetModelViews](#) to determine the size of the array for that method.

This method returns the number of model views set using either **SOLIDWORKS menu > Window > Viewport** or [IModelViewManager::ViewportDisplay](#).

See Also

[IModelDocExtension Interface](#)
[IModelDocExtension Members](#)
[IModelDocExtension::GetModelViews Method](#)
[IModelDoc2::GetFirstModelView Method](#)
[IModelDoc2::IGetFirstModelView Method](#)
[IModelView::GetNext Method](#)
[IModelView::IGetNext Method](#)

Availability

SOLIDWORKS 2009 FCS, Revision Number 17.0