

SOLIDWORKS API (.NET, VBA, C#) — Reference (235/337): IRayTraceRenderOptions-IRefAxis

SOLIDWORKS API Documentation (converted from CHM)

IRayTraceRendererOptions (Type)

IRayTraceRendererOptions Interface

[See Also](#) [Members](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) : IRayTraceRendererOptions Interface

Allows access to a [ray-trace rendering engine's](#) options.

NOTE: Click the **Members** link, located near the top of the topic, to see this interface's methods and properties.

.NET Syntax

Visual Basic (Declaration)

```
Public Interface IRayTraceRendererOptions
```

Visual Basic (Usage)



```
Dim instance As IRayTraceRendererOptions
```

C#

```
public interface IRayTraceRendererOptions
```

C++/CLI

```
public interface class IRayTraceRendererOptions
```

Visual Basic for Applications (VBA) Syntax

See [RayTraceRendererOptions](#).

Example

[Render Model \(C#\)](#)
[Render Model \(VB.NET\)](#)
[Render Model \(VBA\)](#)
[Update Graphics Area After Changing Render Options \(C#\)](#)
[Update Graphics Area After Changing Render Options \(VB.NET\)](#)
[Update Graphics Area After Changing Render Options \(VBA\)](#)

Accessors

[IRayTraceRenderer::RayTraceRendererOptions](#)

Access Diagram

[RayTraceRendererOptions](#)

See Also

[IRayTraceRendererOptions Members](#)
[SolidWorks.Interop.sldworks Namespace](#)

IRayTraceRendererOptions Interface Members

[See Also](#) [Properties](#) [Methods](#)



[SolidWorks.Interop.sldworks Namespace](#) : IRayTraceRendererOptions Interface

The following tables list the members exposed by [IRayTraceRendererOptions](#).

Public Properties

Name	Description
 AlphaOutput	Gets or sets whether to render the model as alpha or final color output.

 BloomEnabled	Gets or sets whether to enable bloom effect.
 BloomRadius	Gets or sets the the distance bloom radiates from source.
 BloomThreshold	Gets or sets the level of brightness or emissiveness to which bloom effect is applied.
 CausticAmount	Gets or sets the maximum number of photons fired, which controls the amount of visible caustics.
 CausticQuality	Gets or sets the number of photons sampled at each pixel, which controls the quality of the caustics.
 ClientWorkload	Gets or sets how many buckets (sections of rendering) are sent to each client processor.
 ContourCartoonRenderingEnabled	Gets or sets whether to enable contour/cartoon rendering.
 ContourEnabled	Obsolete. Superseded by IRayTraceRendererOptions.ContourCartoonRenderingEnabled.
 ContourLineColor	Gets or sets the color of the contour lines.
 ContourLineThickness	Gets or sets the thickness of contour lines.
 CustomRenderSettings	Gets or sets whether to enable custom render settings.
 DefaultImagePath	Gets or sets the default path to which to save the image.
 DirectCaustics	Gets or sets whether to enable direct caustics in the final render .
 FinalRenderQuality	Gets or sets quality of the final render .
 Gamma	Gets or sets the value for midtones of the rendered image while preserving the extreme whites and blacks.
 HasCartoonEdges	Gets or sets whether to render with cartoon edges.
 HasCartoonShading	Gets or sets whether to render with cartoon shading.
 ImageFormat	Gets or sets the format of the image.
 ImageHeight	Gets or sets the height of the image.
 ImageWidth	Gets or sets the width of the image.
 IncludeAnnotationsInRendering	Gets or sets whether to include annotations and dimensions visible in the model when rendering to a file .
 NetworkRendering	Gets or sets whether to enable network rendering.
 NetworkSharedDirectory	Gets or sets the name of the shared network directory for network renders .
 NumberOfReflections	Gets or sets the number of reflections in the final render .
 NumberOfRefractions	Gets or sets the number of refractions in the final render .
 OffloadedRendering	Gets or sets whether to offload rendering to other networked machines.
 OutputAmbientOcclusion	Gets or sets whether to render with ambient occlusion.
 PreviewRenderQuality	Gets or sets the quality of the rendering in the preview window.
 RenderAnnotationsToSeparateImage	Gets or sets whether to render annotations and dimensions visible in the model to a separate image file.
 RenderType	Gets or sets whether to render with contour or cartoon lines.
 SendDataForNetworkJob	Gets or sets whether to send rendering data over the network.
 ShadedContour	Gets or sets whether to shade the contours lines.
 UseSceneBackgroundImageAspectRatio	Gets or sets whether to use the aspect ratio of the scene's background image for ray-trace rendering engine preview and final renders.
 UseSolidWorksViewAspectRatio	Gets or sets whether to use the aspect ratio of the SOLIDWORKS view for ray-trace rendering engine preview and final renders.

[Top](#)

Public Methods

Name	Description
 UpdateGraphics	Updates the graphics area.

[Top](#)

See Also

[IRayTraceRendererOptions Interface](#)
[SolidWorks.Interop.sldworks Namespace](#)

IRayTraceRendererOptions Interface Methods

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) : IRayTraceRendererOptions Interface

For a list of all members of this type, see [IRayTraceRendererOptions members](#).

Public Methods

Name	Description
 UpdateGraphics	Updates the graphics area.

[Top](#)

See Also

[IRayTraceRendererOptions Interface](#)
[SolidWorks.Interop.sldworks Namespace](#)

IRayTraceRendererOptions Interface Properties

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) : IRayTraceRendererOptions Interface

For a list of all members of this type, see [IRayTraceRendererOptions members](#).

Public Properties

Name	Description
 AlphaOutput	Gets or sets whether to render the model as alpha or final color output.
 BloomEnabled	Gets or sets whether to enable bloom effect.
 BloomRadius	Gets or sets the the distance bloom radiates from source.
 BloomThreshold	Gets or sets the level of brightness or emissiveness to which bloom effect is applied.
 CausticAmount	Gets or sets the maximum number of photons fired, which controls the amount of visible caustics.
 CausticQuality	Gets or sets the number of photons sampled at each pixel, which controls the quality of the caustics.
 ClientWorkload	Gets or sets how many buckets (sections of rendering) are sent to each client processor.
 ContourCartoonRenderingEnabled	Gets or sets whether to enable contour/cartoon rendering.
 ContourEnabled	Obsolete. Superseded by IRayTraceRendererOptions.ContourCartoonRenderingEnabled .
 ContourLineColor	Gets or sets the color of the contour lines.
 ContourLineThickness	Gets or sets the thickness of contour lines.
 CustomRenderSettings	Gets or sets whether to enable custom render settings.
 DefaultImagePath	Gets or sets the default path to which to save the image.
 DirectCaustics	Gets or sets whether to enable direct caustics in the final render .
 FinalRenderQuality	Gets or sets quality of the final render .
 Gamma	Gets or sets the value for midtones of the rendered image while preserving the extreme whites and blacks.
 HasCartoonEdges	Gets or sets whether to render with cartoon edges.
 HasCartoonShading	Gets or sets whether to render with cartoon shading.
 ImageFormat	Gets or sets the format of the image.
 ImageHeight	Gets or sets the height of the image.
 ImageWidth	Gets or sets the width of the image.
 IncludeAnnotationsInRendering	Gets or sets whether to include annotations and dimensions visible in the model when rendering to a file .
 NetworkRendering	Gets or sets whether to enable network rendering.
 NetworkSharedDirectory	Gets or sets the name of the shared network directory for network renders .

	NumberOfReflections	Gets or sets the number of reflections in the final render .
	NumberOfRefractions	Gets or sets the number of refractions in the final render .
	OffloadedRendering	Gets or sets whether to offload rendering to other networked machines.
	OutputAmbientOcclusion	Gets or sets whether to render with ambient occlusion.
	PreviewRenderQuality	Gets or sets the quality of the rendering in the preview window.
	RenderAnnotationsToSeparateImage	Gets or sets whether to render annotations and dimensions visible in the model to a separate image file.
	RenderType	Gets or sets whether to render with contour or cartoon lines.
	SendDataForNetworkJob	Gets or sets whether to send rendering data over the network.
	ShadedContour	Gets or sets whether to shade the contours lines.
	UseSceneBackgroundImageAspectRatio	Gets or sets whether to use the aspect ratio of the scene's background image for ray-trace rendering engine preview and final renders.
	UseSolidWorksViewAspectRatio	Gets or sets whether to use the aspect ratio of the SOLIDWORKS view for ray-trace rendering engine preview and final renders.

[Top](#)

See Also

[IRayTraceRendererOptions Interface](#)
[SolidWorks.Interop.sldworks Namespace](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

AlphaOutput Property (IRayTraceRendererOptions)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IRayTraceRendererOptions Interface](#) : AlphaOutput Property (IRayTraceRendererOptions)

Gets or sets whether to [render](#) the model as alpha or final color output.

.NET Syntax

Visual Basic (Declaration)

Property AlphaOutput As System.Boolean

Visual Basic (Usage)



```
Dim instance As IRayTraceRendererOptions
Dim value As System.Boolean

instance.AlphaOutput = value

value = instance.AlphaOutput
```

C#

```
System.bool AlphaOutput {get; set;}
```

C++/CLI

```
property System.bool AlphaOutput {
    System.bool get();
    void set ( & System.bool value);
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

True for alpha output, false for final color output

Visual Basic for Applications (VBA) Syntax

See [RayTraceRendererOptions::AlphaOutput](#).

Example

[Render Model \(C#\)](#)
[Render Model \(VB.NET\)](#)
[Render Model \(VBA\)](#)

See Also

[IRayTraceRendererOptions Interface](#)
[IRayTraceRendererOptions Members](#)

Availability

SOLIDWORKS 2016 FCS, Revision Number 24.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

BloomEnabled Property (IRayTraceRendererOptions)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IRayTraceRendererOptions Interface](#) : BloomEnabled Property (IRayTraceRendererOptions)

Gets or sets whether to enable bloom effect.

.NET Syntax

Visual Basic (Declaration)

Property BloomEnabled As System.Boolean

Visual Basic (Usage)



```
Dim instance As IRayTraceRendererOptions  
Dim value As System.Boolean
```

```
instance.BloomEnabled = value
```

```
value = instance.BloomEnabled
```

C#

```
System.bool BloomEnabled {get; set;}
```

C++/CLI

```
property System.bool BloomEnabled {  
    System.bool get();  
    void set ( & System.bool value);  
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

True if bloom effect is enabled, false if not

Visual Basic for Applications (VBA) Syntax

See [RayTraceRendererOptions::BloomEnabled](#).

Example

[Render Model \(C#\)](#)
[Render Model \(VB.NET\)](#)
[Render Model \(VBA\)](#)

Remarks

Bloom effect is visible in the [final rendering](#) only, not in the [preview](#). See the SOLIDWORKS Help for details about bloom effect.

See Also

[IRayTraceRendererOptions Interface](#)
[IRayTraceRendererOptions Members](#)
[IRayTraceRendererOptions::BloomRadius Property](#)
[IRayTraceRendererOptions::BloomThreshold Property](#)

Availability

SOLIDWORKS 2011 FCS, Revision Number 19.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

BloomRadius Property (IRayTraceRendererOptions)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IRayTraceRendererOptions Interface](#) : BloomRadius Property (IRayTraceRendererOptions)

Gets or sets the the distance bloom radiates from source.

.NET Syntax

Visual Basic (Declaration)

```
Property BloomRadius As System.Integer
```

Visual Basic (Usage)



```
Dim instance As IRayTraceRendererOptions  
Dim value As System.Integer  
  
instance.BloomRadius = value  
  
value = instance.BloomRadius
```

C#

```
System.int BloomRadius {get; set;}
```

C++/CLI

```
property System.int BloomRadius {  
    System.int get();  
    void set ( & System.int value);  
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

Distance bloom radiates from source

Visual Basic for Applications (VBA) Syntax

See [RayTraceRendererOptions::BloomRadius](#).

Example

[Render Model \(C#\)](#)
[Render Model \(VB.NET\)](#)
[Render Model \(VBA\)](#)

Remarks

Bloom effect is visible in the [final rendering](#) only, not in the [preview](#). See the SOLIDWORKS Help for details about bloom effect.

See Also

[IRayTraceRendererOptions Interface](#)
[IRayTraceRendererOptions Members](#)
[IRayTraceRendererOptions::BloomEnabled Property](#)
[IRayTraceRendererOptions::BloomThreshold Property](#)

Availability

SOLIDWORKS 2011 FCS, Revision Number 19.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

BloomThreshold Property (IRayTraceRendererOptions)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IRayTraceRendererOptions Interface](#) : BloomThreshold Property (IRayTraceRendererOptions)

Gets or sets the level of brightness or emissiveness to which bloom effect is applied.

Visual Basic Syntax

Visual Basic (Declaration)

Property BloomThreshold As System.Integer

Visual Basic (Usage)



```
Dim instance As IRayTraceRendererOptions  
Dim value As System.Integer
```

```
instance.BloomThreshold = value
```

```
value = instance.BloomThreshold
```

C#

```
System.int BloomThreshold {get; set;}
```

C++/CLI

```
property System.int BloomThreshold {  
    System.int get();  
    void set ( & System.int value);  
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

Brightness or emissiveness to which bloom effect is applied

Visual Basic for Applications (VBA) Syntax

See [RayTraceRendererOptions::BloomThreshold](#).

Example

[Render Model \(C#\)](#)
[Render Model \(VB.NET\)](#)
[Render Model \(VBA\)](#)

Remarks

Bloom effect is visible in the [final rendering](#) only, not in the [preview](#). See the SOLIDWORKS Help for details about bloom effect.

See Also

[IRayTraceRendererOptions Interface](#)
[IRayTraceRendererOptions Members](#)
[IRayTraceRendererOptions::BloomEnabled Property](#)
[IRayTraceRendererOptions::BloomRadius Property](#)

Availability

SOLIDWORKS 2011 FCS, Revision Number 19.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

CausticAmount Property (IRayTraceRendererOptions)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IRayTraceRendererOptions Interface](#) : CausticAmount Property (IRayTraceRendererOptions)

Gets or sets the maximum number of photons fired, which controls the amount of visible caustics.

.NET Syntax

Visual Basic (Declaration)

```
Property CausticAmount As System.Integer
```

Visual Basic (Usage)



```
Dim instance As IRayTraceRendererOptions  
Dim value As System.Integer
```

```
instance.CausticAmount = value
```

```
value = instance.CausticAmount
```

C#

```
System.int CausticAmount {get; set;}
```

C++/CLI

```
property System.int CausticAmount {  
    System.int get();  
    void set ( & System.int value);  
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

Maximum number of photons fired

Visual Basic for Applications (VBA) Syntax

See [RayTraceRendererOptions::CausticAmount](#).

Remarks

Increasing the amount of photons fired creates sharper and clearer caustics but increases rendering time.

See Also

[IRayTraceRendererOptions Interface](#)
[IRayTraceRendererOptions Members](#)
[IRayTraceRendererOptions::CausticQuality Property \(\)](#)
[IRayTraceRendererOptions::DirectCaustics Property \(\)](#)

Availability

SOLIDWORKS 2016 FCS, Revision Number 24.0

SOLIDWORKS API Help

[Send comments](#) on this topic.

CausticQuality Property (IRayTraceRendererOptions)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IRayTraceRendererOptions Interface](#) : CausticQuality Property (IRayTraceRendererOptions)

Gets or sets the number of photons sampled at each pixel, which controls the quality of the caustics.

.NET Syntax

Visual Basic (Declaration)

Property CausticQuality As System.Integer

Visual Basic (Usage)



```
Dim instance As IRayTraceRendererOptions  
Dim value As System.Integer  
  
instance.CausticQuality = value  
value = instance.CausticQuality
```

C#

```
System.int CausticQuality {get; set;}
```

C++/CLI

```
property System.int CausticQuality {  
    System.int get();  
    void set ( & System.int value);  
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

Number of photons sampled at each pixel

Visual Basic for Applications (VBA) Syntax

See [RayTraceRendererOptions::CausticQuality](#).

Remarks

Increasing the number of photons sampled at each pixel creates a smoother caustic effect at the expense of detail. Decreasing the number of photons results in a sharper caustic effect with increasing graininess.

See Also

[IRayTraceRendererOptions Interface](#)
[IRayTraceRendererOptions Members](#)
[IRayTraceRendererOptions::CausticAmount Property \(\)](#)
[IRayTraceRendererOptions::DirectCaustics Property \(\)](#)

Availability

SOLIDWORKS 2016 FCS, Revision Number 24.0

SOLIDWORKS API Help

[Send comments](#) on this topic.

ClientWorkload Property (IRayTraceRendererOptions)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IRayTraceRendererOptions Interface](#) : ClientWorkload Property (IRayTraceRendererOptions)

Gets or sets how many buckets (sections of rendering) are sent to each client processor.

.NET Syntax

Visual Basic (Declaration)

```
Property ClientWorkload As System.Integer
```

Visual Basic (Usage)



```
Dim instance As IRayTraceRendererOptions  
Dim value As System.Integer  
  
instance.ClientWorkload = value
```

```
value = instance.ClientWorkload
```

C#

```
System.int ClientWorkload {get; set;}
```

C++/CLI

```
property System.int ClientWorkload {  
    System.int get();  
    void set ( & System.int value);  
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

Number of buckets sent to each client processor (see **Remarks**)

Visual Basic for Applications (VBA) Syntax

See [RayTraceRendererOptions::ClientWorkload](#).

Remarks

A high client workload setting is appropriate if the client machines are more powerful than the coordinator machine.

Using a [shared network directory](#) for [network renders](#):

- can be faster when using many client machines.
- avoids having to [send scene asset data to each node on the network](#).

NOTE: Only SOLIDWORKS Subscription Services customers can share the effort of rendering across multiple computers.

See Also

[IRayTraceRendererOptions Interface](#)
[IRayTraceRendererOptions Members](#)
[IRayTraceRendererOptions::OffloadedRendering_Property\(\)](#)

Availability

SOLIDWORKS 2016 FCS, Revision Number 24.0

SOLIDWORKS API Help

[Send comments](#) on this topic.

ContourCartoonRenderingEnabled Property (IRayTraceRendererOptions)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IRayTraceRendererOptions Interface](#) : ContourCartoonRenderingEnabled Property (IRayTraceRendererOptions)

Gets or sets whether to enable contour/cartoon rendering.

.NET Syntax

Visual Basic (Declaration)

```
Property ContourCartoonRenderingEnabled As System.Boolean
```

Visual Basic (Usage)



```
Dim instance As IRayTraceRendererOptions  
Dim value As System.Boolean  
  
instance.ContourCartoonRenderingEnabled = value  
  
value = instance.ContourCartoonRenderingEnabled
```

C#

```
System.bool ContourCartoonRenderingEnabled {get; set;}
```

C++/CLI

```
property System.bool ContourCartoonRenderingEnabled {
    System.bool get();
    void set ( & System.bool value);
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

True to enable contour/cartoon rendering, false to not

Visual Basic for Applications (VBA) Syntax

See [RayTraceRendererOptions::ContourCartoonRenderingEnabled](#).

Example

[Render Model \(C#\)](#)
[Render Model \(VB.NET\)](#)
[Render Model \(VBA\)](#)
[Update Graphics Area After Changing Render Options \(C#\)](#)
[Update Graphics Area After Changing Render Options \(VB.NET\)](#)
[Update Graphics Area After Changing Render Options \(VBA\)](#)

Remarks

After setting this property, call [IRayTraceRendererOptions::RenderType](#) to set rendering to either contour or cartoon.

See Also

[IRayTraceRendererOptions Interface](#)
[IRayTraceRendererOptions Members](#)
[IRayTraceRendererOptions::ContourLineColor Property \(\)](#)
[IRayTraceRendererOptions::ContourLineThickness Property \(\)](#)

Availability

SOLIDWORKS 2016 FCS, Revision Number 24.0

SOLIDWORKS API Help

[Send comments](#) on this topic.

ContourEnabled Property (IRayTraceRendererOptions)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IRayTraceRendererOptions Interface](#) : ContourEnabled Property (IRayTraceRendererOptions)

Obsolete. Superseded by [IRayTraceRendererOptions::ContourCartoonRenderingEnabled](#).

.NET Syntax

Visual Basic (Declaration)

Property ContourEnabled As System.Boolean

Visual Basic (Usage)



```
Dim instance As IRayTraceRendererOptions
Dim value As System.Boolean
```

```
instance.ContourEnabled = value
```

```
value = instance.ContourEnabled
```

C#

```
System.bool ContourEnabled {get; set;}
```

C++/CLI

```
property System.bool ContourEnabled {
    System.bool get();
```

```
void set ( & System.bool value);  
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

True to render with contour lines, false to not

Visual Basic for Applications (VBA) Syntax

See [RayTraceRendererOptions::ContourEnabled](#).

See Also

[IRayTraceRendererOptions Interface](#)
[IRayTraceRendererOptions Members](#)

Availability

SOLIDWORKS 2011 FCS, Revision Number 19.0

SOLIDWORKS API Help

[Send comments](#) on this topic.

ContourLineColor Property (IRayTraceRendererOptions)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IRayTraceRendererOptions Interface](#) : ContourLineColor Property (IRayTraceRendererOptions)

Gets or sets the color of the contour lines.

.NET Syntax

Visual Basic (Declaration)

```
Property ContourLineColor As System.Integer
```

Visual Basic (Usage)



```
Dim instance As IRayTraceRendererOptions  
Dim value As System.Integer
```

```
instance.ContourLineColor = value
```

```
value = instance.ContourLineColor
```

C#

```
System.int ContourLineColor {get; set;}
```

C++/CLI

```
property System.int ContourLineColor {  
    System.int get();  
    void set ( & System.int value);  
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

RGB value for color of contour lines

Visual Basic for Applications (VBA) Syntax

See [RayTraceRendererOptions::ContourLineColor](#).

Example

[Render Model \(C#\)](#)
[Render Model \(VB.NET\)](#)
[Render Model \(VBA\)](#)

Remarks

This property is only available when [IRayTraceRendererOptions::ContourCartoonRenderingEnabled](#) is true.

See Also

[IRayTraceRendererOptions Interface](#)
[IRayTraceRendererOptions Members](#)
[IRayTraceRendererOptions::ContourLineThickness Property](#)

Availability

SOLIDWORKS 2011 FCS, Revision Number 19.0

[SOLIDWORKS API Help](#)

[Send comments on this topic.](#)

ContourLineThickness Property (IRayTraceRendererOptions)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IRayTraceRendererOptions Interface](#) : ContourLineThickness Property (IRayTraceRendererOptions)

Gets or sets the thickness of contour lines.

.NET Syntax

Visual Basic (Declaration)

```
Property ContourLineThickness As System.Integer
```

Visual Basic (Usage)



```
Dim instance As IRayTraceRendererOptions  
Dim value As System.Integer  
  
instance.ContourLineThickness = value  
  
value = instance.ContourLineThickness
```

C#

```
System.int ContourLineThickness {get; set;}
```

C++/CLI

```
property System.int ContourLineThickness {  
    System.int get();  
    void set ( & System.int value);  
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

Thickness, in pixels, of contour lines

Visual Basic for Applications (VBA) Syntax

See [RayTraceRendererOptions::ContourLineThickness](#).

Example

[Render Model \(C#\)](#)
[Render Model \(VB.NET\)](#)
[Render Model \(VBA\)](#)

Remarks

This property is only available when [IRayTraceRendererOptions::ContourCartoonRenderingEnabled](#) is true.

See Also

[IRayTraceRendererOptions Interface](#)
[IRayTraceRendererOptions Members](#)
[IRayTraceRendererOptions::ContourLineColor Property](#)

Availability

SOLIDWORKS 2011 FCS, Revision Number 19.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

CustomRenderSettings Property (IRayTraceRendererOptions)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IRayTraceRendererOptions Interface](#) : CustomRenderSettings Property (IRayTraceRendererOptions)

Gets or sets whether to enable custom render settings.

.NET Syntax

Visual Basic (Declaration)

Property CustomRenderSettings As System.Boolean

Visual Basic (Usage)



```
Dim instance As IRayTraceRendererOptions  
Dim value As System.Boolean
```

```
instance.CustomRenderSettings = value
```

```
value = instance.CustomRenderSettings
```

C#

```
System.bool CustomRenderSettings {get; set;}
```

C++/CLI

```
property System.bool CustomRenderSettings {  
    System.bool get();  
    void set ( & System.bool value);  
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

True to enable custom render settings, false to not

Visual Basic for Applications (VBA) Syntax

See [RayTraceRendererOptions::CustomRenderSettings](#).

Remarks

Enabling custom render settings allows access to the number of:

- [reflections](#)
- [refractions](#)

in the [final render](#).

See Also

[IRayTraceRendererOptions Interface](#)
[IRayTraceRendererOptions Members](#)

Availability

SOLIDWORKS 2016 FCS, Revision Number 24.0

DefaultImagePath Property (IRayTraceRendererOptions)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IRayTraceRendererOptions Interface](#) : DefaultImagePath Property (IRayTraceRendererOptions)

Gets or sets the default path to which to save the image.

.NET Syntax

Visual Basic (Declaration)

Property DefaultImagePath As System.String

Visual Basic (Usage)



```
Dim instance As IRayTraceRendererOptions
Dim value As System.String

instance.DefaultImagePath = value

value = instance.DefaultImagePath
```

C#

```
System.string DefaultImagePath {get; set;}
```

C++/CLI

```
property System.String^ DefaultImagePath {
    System.String^ get();
    void set ( & System.String^ value);
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

Path to which to save the image

Visual Basic for Applications (VBA) Syntax

See [RayTraceRendererOptions.DefaultImagePath](#).

See Also

[IRayTraceRendererOptions Interface](#)
[IRayTraceRendererOptions Members](#)
[IRayTraceRendererOptions::ImageFormat Property](#)
[IRayTraceRendererOptions::ImageHeight Property](#)
[IRayTraceRendererOptions::ImageWidth Property](#)

Availability

SOLIDWORKS 2011 FCS, Revision Number 19.0

DirectCaustics Property (IRayTraceRendererOptions)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IRayTraceRendererOptions Interface](#) : DirectCaustics Property (IRayTraceRendererOptions)

Gets or sets whether to enable direct caustics in the [final render](#).

.NET Syntax

Visual Basic (Declaration)

Property DirectCaustics As System.Boolean

Visual Basic (Usage)



```
Dim instance As IRayTraceRendererOptions
Dim value As System.Boolean

instance.DirectCaustics = value

value = instance.DirectCaustics
```

C#

```
System.bool DirectCaustics {get; set;}
```

C++/CLI

```
property System.bool DirectCaustics {
    System.bool get();
    void set ( & System.bool value);
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

True to enable direct caustics in the final render, false to not

Visual Basic for Applications (VBA) Syntax

See [RayTraceRendererOptions.DirectCaustics](#).

Remarks

Direct caustics are only visible in the final render and only when reflected off a floor appearance or physical geometry using a spot or point light. The light bounces off or filters through the model creating a bright pattern on the floor.

See Also

[IRayTraceRendererOptions Interface](#)
[IRayTraceRendererOptions Members](#)
[IRayTraceRendererOptions::CausticAmount Property \(\)](#)
[IRayTraceRendererOptions::CausticQuality Property \(\)](#)
[IRayTraceRendererOptions::FinalRenderQuality Property \(\)](#)
[IRayTraceRendererOptions::PreviewRenderQuality Property \(\)](#)

Availability

SOLIDWORKS 2016 FCS, Revision Number 24.0

SOLIDWORKS API Help

[Send comments](#) on this topic.

FinalRenderQuality Property (IRayTraceRendererOptions)

See Also [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IRayTraceRendererOptions Interface](#) : FinalRenderQuality Property (IRayTraceRendererOptions)

Gets or sets quality of the [final render](#).

.NET Syntax

Visual Basic (Declaration)

```
Property FinalRenderQuality As System.Integer
```

Visual Basic (Usage)



```
Dim instance As IRayTraceRendererOptions
Dim value As System.Integer

instance.FinalRenderQuality = value

value = instance.FinalRenderQuality
```

C#

```
System.int FinalRenderQuality {get; set;}
```

C++/CLI

```
property System.int FinalRenderQuality {  
    System.int get();  
    void set ( & System.int value);  
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

Quality of final render as defined in [swRayTraceRenderQuality_e](#)

Visual Basic for Applications (VBA) Syntax

See [RayTraceRenderOptions::FinalRenderQuality](#).

Example

[Render Model \(C#\)](#)
[Render Model \(VB.NET\)](#)
[Render Model \(VBA\)](#)

See Also

[IRayTraceRenderOptions Interface](#)
[IRayTraceRenderOptions Members](#)
[IRayTraceRenderOptions::PreviewRenderQuality Property](#)
[IRayTraceRenderOptions::DirectCaustics Property](#)

Availability

SOLIDWORKS 2011 FCS, Revision Number 19.0

SOLIDWORKS API Help

[Send comments](#) on this topic.

Gamma Property (IRayTraceRenderOptions)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IRayTraceRenderOptions Interface](#) : Gamma Property (IRayTraceRenderOptions)

Gets or sets the value for midtones of the rendered image while preserving the extreme whites and blacks.

.NET Syntax

Visual Basic (Declaration)

```
Property Gamma As System.Double
```

Visual Basic (Usage)



```
Dim instance As IRayTraceRenderOptions  
Dim value As System.Double
```

```
instance.Gamma = value
```

```
value = instance.Gamma
```

C#

```
System.double Gamma {get; set;}
```

C++/CLI

```
property System.double Gamma {  
    System.double get();  
    void set ( & System.double value);  
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

Value for midtones of the rendered image

Visual Basic for Applications (VBA) Syntax

See [RayTraceRendererOptions::Gamma](#).

Remarks

Increasing the value for midtones lightens them; decreasing the value darkens them.

See Also

[IRayTraceRendererOptions Interface](#)
[IRayTraceRendererOptions Members](#)

Availability

SOLIDWORKS 2016 FCS, Revision Number 24.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

HasCartoonEdges Property (IRayTraceRendererOptions)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IRayTraceRendererOptions Interface](#) : HasCartoonEdges Property (IRayTraceRendererOptions)

Gets or sets whether to render with cartoon edges.

.NET Syntax

Visual Basic (Declaration)

Property HasCartoonEdges As System.Boolean

Visual Basic (Usage)



```
Dim instance As IRayTraceRendererOptions  
Dim value As System.Boolean
```

```
instance.HasCartoonEdges = value
```

```
value = instance.HasCartoonEdges
```

C#

```
System.bool HasCartoonEdges {get; set;}
```

C++/CLI

```
property System.bool HasCartoonEdges {  
    System.bool get();  
    void set ( & System.bool value);  
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

True to render with cartoon edges, false to not

Visual Basic for Applications (VBA) Syntax

See [RayTraceRendererOptions::HasCartoonEdges](#).

Example

[Update Graphics Area After Changing Render Options \(C#\)](#)
[Update Graphics Area After Changing Render Options \(VB.NET\)](#)
[Update Graphics Area After Changing Render Options \(VBA\)](#)

Remarks

This property is only available when [IRayTraceRendererOptions::ContourCartoonRenderingEnabled](#) is true and [IRayTraceRendererOptions::RenderType](#) is swRayTraceRenderingType_e.swRayTraceCartoon.

To set cartoon...	Set IRayTraceRendererOptions::HasCartoonEdges to...	Set IRayTraceRendererOptions::HasCartoonShading to...
Edges	True	False
Shading	False	True
Edges and shading	True	True

See Also

[IRayTraceRendererOptions Interface](#)
[IRayTraceRendererOptions Members](#)
[IRayTraceRendererOptions::ContourLineColor Property \(\)](#)
[IRayTraceRendererOptions::ContourLineThickness Property \(\)](#)

Availability

SOLIDWORKS 2016 FCS, Revision Number 24.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

HasCartoonShading Property (IRayTraceRendererOptions)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IRayTraceRendererOptions Interface](#) : HasCartoonShading Property (IRayTraceRendererOptions)

Gets or sets whether to render with cartoon shading.

.NET Syntax

Visual Basic (Declaration)

Property HasCartoonShading As System.Boolean

Visual Basic (Usage)



```
Dim instance As IRayTraceRendererOptions
Dim value As System.Boolean

instance.HasCartoonShading = value

value = instance.HasCartoonShading
```

C#

```
System.bool HasCartoonShading {get; set;}
```

C++/CLI

```
property System.bool HasCartoonShading {
    System.bool get();
    void set ( & System.bool value);
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

True to render with cartoon shading, false to not

Visual Basic for Applications (VBA) Syntax

See [RayTraceRendererOptions::HasCartoonShading](#).

Remarks

This property is only available when [IRayTraceRendererOptions::ContourCartoonRenderingEnabled](#) is true and [IRayTraceRendererOptions::RenderType](#) is `swRayTraceRenderingType_e.swRayTraceCartoon`.

To set cartoon...	Set IRayTraceRendererOptions::HasCartoonEdges to...	Set IRayTraceRendererOptions::HasCartoonShading to...
Edges	True	False
Shading	False	True
Edges and shading	True	True

 See Also

[IRayTraceRendererOptions Interface](#)
[IRayTraceRendererOptions Members](#)
[IRayTraceRendererOptions::ContourLineColor Property \(\)](#)
[IRayTraceRendererOptions::ContourLineThickness Property \(\)](#)

 Availability

SOLIDWORKS 2016 FCS, Revision Number 24.0

SOLIDWORKS API Help [Send comments on this topic.](#)

ImageFormat Property (IRayTraceRendererOptions)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IRayTraceRendererOptions Interface](#) : ImageFormat Property (IRayTraceRendererOptions)

Gets or sets the format of the image.

 .NET Syntax

Visual Basic (Declaration)

Property ImageFormat As System.Integer

Visual Basic (Usage)



```
Dim instance As IRayTraceRendererOptions  
Dim value As System.Integer  
  
instance.ImageFormat = value  
  
value = instance.ImageFormat
```

C#

```
System.int ImageFormat {get; set;}
```

C++/CLI

```
property System.int ImageFormat {  
    System.int get();  
    void set ( & System.int value);  
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

Format of the image as defined in [swRayTraceRenderImageFormat_e](#)

 Visual Basic for Applications (VBA) Syntax

See [RayTraceRendererOptions::ImageFormat](#).

 Example

[Render Model \(C#\)](#)
[Render Model \(VB.NET\)](#)
[Render Model \(VBA\)](#)

 See Also

[IRayTraceRendererOptions Interface](#)
[IRayTraceRendererOptions Members](#)
[IRayTraceRendererOptions::ImageHeight Property](#)
[IRayTraceRendererOptions::ImageWidth Property](#)
[IRayTraceRendererOptions::DefaultImagePath Property](#)

Availability

SOLIDWORKS 2011 FCS, Revision Number 19.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

ImageHeight Property (IRayTraceRendererOptions)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IRayTraceRendererOptions Interface](#) : ImageHeight Property (IRayTraceRendererOptions)

Gets or sets the height of the image.

.NET Syntax

Visual Basic (Declaration)

```
Property ImageHeight As System.Integer
```

Visual Basic (Usage)



```
Dim instance As IRayTraceRendererOptions  
Dim value As System.Integer  
  
instance.ImageHeight = value  
  
value = instance.ImageHeight
```

C#

```
System.int ImageHeight {get; set;}
```

C++/CLI

```
property System.int ImageHeight {  
    System.int get();  
    void set ( & System.int value);  
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

Height, in pixels, of the image

Visual Basic for Applications (VBA) Syntax

See [RayTraceRendererOptions::ImageHeight](#).

Example

[Render Model \(C#\)](#)
[Render Model \(VB.NET\)](#)
[Render Model \(VBA\)](#)

Remarks

You can override the values set in this property and [IRayTraceRendererOptions::ImageWidth](#) by specifying Width and Height in [IRayTraceRenderer::RenderToFile](#).

See Also

[IRayTraceRendererOptions Interface](#)
[IRayTraceRendererOptions Members](#)
[IRayTraceRendererOptions::ImageFormat Property](#)
[IRayTraceRendererOptions::DefaultImagePath Property](#)

Availability

SOLIDWORKS 2011 FCS, Revision Number 19.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

ImageWidth Property (IRayTraceRendererOptions)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IRayTraceRendererOptions Interface](#) : ImageWidth Property (IRayTraceRendererOptions)

Gets or sets the width of the image.

.NET Syntax

Visual Basic (Declaration)

Property ImageWidth As System.Integer

Visual Basic (Usage)



```
Dim instance As IRayTraceRendererOptions
Dim value As System.Integer

instance.ImageWidth = value
value = instance.ImageWidth
```

C#

```
System.int ImageWidth {get; set;}
```

C++/CLI

```
property System.int ImageWidth {
    System.int get();
    void set ( & System.int value);
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

Width, in pixels, of the image

Visual Basic for Applications (VBA) Syntax

See [RayTraceRendererOptions::ImageWidth](#).

Example

[Render Model \(C#\)](#)
[Render Model \(VB.NET\)](#)
[Render Model \(VBA\)](#)

Remarks

You can override the values set in this property and [IRayTraceRendererOptions::ImageHeight](#) by specifying Width and Height in [IRayTraceRenderer::RenderToFile](#).

See Also

[IRayTraceRendererOptions Interface](#)
[IRayTraceRendererOptions Members](#)
[IRayTraceRendererOptions::ImageFormat Property](#)
[IRayTraceRendererOptions::DefaultImagePath Property](#)

Availability

SOLIDWORKS 2011 FCS, Revision Number 19.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

IncludeAnnotationsInRendering Property (IRayTraceRendererOptions)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IRayTraceRendererOptions Interface](#) : IncludeAnnotationsInRendering Property (IRayTraceRendererOptions)

Gets or sets whether to include annotations and dimensions visible in the model when [rendering to a file](#).

.NET Syntax

Visual Basic (Declaration)

```
Property IncludeAnnotationsInRendering As System.Boolean
```

Visual Basic (Usage)



```
Dim instance As IRayTraceRendererOptions
Dim value As System.Boolean

instance.IncludeAnnotationsInRendering = value

value = instance.IncludeAnnotationsInRendering
```

C#

```
System.bool IncludeAnnotationsInRendering {get; set;}
```

C++/CLI

```
property System.bool IncludeAnnotationsInRendering {
    System.bool get();
    void set ( & System.bool value);
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

True to include annotations and dimensions visible in the model when rendering to a file, false to not

Visual Basic for Applications (VBA) Syntax

See [RayTraceRendererOptions::IncludeAnnotationsInRendering](#).

Example

[Include Note in Render File \(C#\)](#)
[Include Note in Render File \(VB.NET\)](#)
[Include Note in Render File \(VBA\)](#)

Remarks

This property is only available when rendering to a file; this property is not available when only [invoking the final render window](#).

To render the annotations and dimensions visible in the model to a separate image file, call [IRayTraceRendererOptions::RenderAnnotationsToSeparateImage](#).

See Also

[IRayTraceRendererOptions Interface](#)
[IRayTraceRendererOptions Members](#)

Availability

SOLIDWORKS 2016 FCS, Revision Number 24.0

SOLIDWORKS API Help

[Send comments](#) on this topic.

NetworkRendering Property (IRayTraceRendererOptions)

[See Also](#)



Gets or sets whether to enable network rendering.

.NET Syntax

Visual Basic (Declaration)

Property NetworkRendering As System.Boolean

Visual Basic (Usage)



```
Dim instance As IRayTraceRendererOptions
Dim value As System.Boolean

instance.NetworkRendering = value

value = instance.NetworkRendering
```

C#

```
System.bool NetworkRendering {get; set;}
```

C++/CLI

```
property System.bool NetworkRendering {
    System.bool get();
    void set ( & System.bool value);
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

True to enable network rendering, false to not

Visual Basic for Applications (VBA) Syntax

See [RayTraceRendererOptions::NetworkRendering](#).

Remarks

Only SOLIDWORKS Subscription Services customers can share the effort of rendering across multiple computers.

See Also

[IRayTraceRendererOptions Interface](#)
[IRayTraceRendererOptions Members](#)
[IRayTraceRendererOptions::ClientWorkload Property\(\)](#)
[IRayTraceRendererOptions::NetworkSharedDirectory Property\(\)](#)
[IRayTraceRendererOptions::SendDataForNetworkJob Property\(\)](#)
[IRayTraceRendererOptions::OffloadedRendering Property\(\)](#)

Availability

SOLIDWORKS 2016 FCS, Revision Number 24.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

NetworkSharedDirectory Property (IRayTraceRendererOptions)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IRayTraceRendererOptions Interface](#) : NetworkSharedDirectory Property (IRayTraceRendererOptions)

Gets or sets the name of the shared network directory for [network renders](#).

.NET Syntax

Visual Basic (Declaration)

Property NetworkSharedDirectory As System.String

Visual Basic (Usage)

```
Dim instance As IRayTraceRendererOptions  
Dim value As System.String  
  
instance.NetworkSharedDirectory = value  
value = instance.NetworkSharedDirectory
```

C#

```
System.string NetworkSharedDirectory {get; set;}
```

C++/CLI

```
property System.String^ NetworkSharedDirectory {  
    System.String^ get();  
    void set ( &    System.String^ value);  
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

Name of the shared network directory for network renders

Visual Basic for Applications (VBA) Syntax

See [RayTraceRendererOptions.NetworkSharedDirectory](#).

Remarks

Using a shared network directory for network renders:

- avoids having to [send scene asset data to each node on the network](#).
- can be faster when using many [client machines](#).

NOTE: Only SOLIDWORKS Subscription Services customers can share the effort of rendering across multiple computers.

See Also

[IRayTraceRendererOptions Interface](#)
[IRayTraceRendererOptions Members](#)
[IRayTraceRendererOptions.OffloadedRendering Property \(\)](#)

Availability

SOLIDWORKS 2016 FCS, Revision Number 24.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

NumberOfReflections Property (IRayTraceRendererOptions)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IRayTraceRendererOptions Interface](#) : NumberOfReflections Property (IRayTraceRendererOptions)

Gets or sets the number of reflections in the [final render](#).

.NET Syntax

Visual Basic (Declaration)

```
Property NumberOfReflections As System.Integer
```

Visual Basic (Usage)

```
Dim instance As IRayTraceRendererOptions  
Dim value As System.Integer  
  
instance.NumberOfReflections = value  
value = instance.NumberOfReflections
```

C#

```
System.int NumberOfReflections {get; set;}
```

C++/CLI

```
property System.int NumberOfReflections {  
    System.int get();  
    void set ( & System.int value);  
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

0 <= Number of reflections <= 32

Visual Basic for Applications (VBA) Syntax

See [RayTraceRendererOptions::NumberOfReflections](#).

Remarks

This property is only available when [IRayTraceRendererOptions::CustomRenderSettings](#) is true.

The number of reflections impacts rendering performance, so only use a high number of reflections to correctly see objects in the rendering.

See Also

[IRayTraceRendererOptions Interface](#)
[IRayTraceRendererOptions Members](#)
[IRayTraceRendererOptions::NumberOfRefractions Property \(\)](#)

Availability

SOLIDWORKS 2016 FCS, Revision Number 24.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

NumberOfRefractions Property (IRayTraceRendererOptions)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IRayTraceRendererOptions Interface](#) : NumberOfRefractions Property (IRayTraceRendererOptions)

Gets or sets the number of refractions in the [final render](#).

.NET Syntax

Visual Basic (Declaration)

```
Property NumberOfRefractions As System.Integer
```

Visual Basic (Usage)



```
Dim instance As IRayTraceRendererOptions  
Dim value As System.Integer
```

```
instance.NumberOfRefractions = value
```

```
value = instance.NumberOfRefractions
```

C#

```
System.int NumberOfRefractions {get; set;}
```

C++/CLI

```
property System.int NumberOfRefractions {  
    System.int get();  
    void set ( & System.int value);  
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

0 <= Number of refractions <= 32

Visual Basic for Applications (VBA) Syntax

See [RayTraceRendererOptions::NumberOfRefractions](#).

Remarks

This property is only available when [IRayTraceRendererOptions::CustomRenderSettings](#) is true.

The number of refractions impacts rendering performance, so only use a high number of refractions to correctly see objects in the rendering.

See Also

[IRayTraceRendererOptions Interface](#)
[IRayTraceRendererOptions Members](#)
[IRayTraceRendererOptions::NumberOfRefractions Property \(\)](#)

Availability

SOLIDWORKS 2016 FCS, Revision Number 24.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

OffloadedRendering Property (IRayTraceRendererOptions)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IRayTraceRendererOptions Interface](#) : OffloadedRendering Property (IRayTraceRendererOptions)

Gets or sets whether to offload rendering to other networked machines.

.NET Syntax

Visual Basic (Declaration)

Property OffloadedRendering As System.Boolean

Visual Basic (Usage)



```
Dim instance As IRayTraceRendererOptions  
Dim value As System.Boolean
```

```
instance.OffloadedRendering = value
```

```
value = instance.OffloadedRendering
```

C#

```
System.bool OffloadedRendering {get; set;}
```

C++/CLI

```
property System.bool OffloadedRendering {  
    System.bool get();  
    void set ( & System.bool value);  
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

True to offload rendering, false to not

Visual Basic for Applications (VBA) Syntax

See [RayTraceRendererOptions::OffloadedRendering](#).

Remarks

NOTE: Only SOLIDWORKS Subscription Services customers can share the effort of rendering across multiple computers.

See Also

[IRayTraceRendererOptions Interface](#)
[IRayTraceRendererOptions Members](#)
[IRayTraceRendererOptions.ClientWorkload Property \(\)](#)
[IRayTraceRendererOptions.NetworkRendering Property \(\)](#)
[IRayTraceRendererOptions.NetworkSharedDirectory Property \(\)](#)
[IRayTraceRendererOptions.SendDataForNetworkJob Property \(\)](#)

Availability

SOLIDWORKS 2018 FCS, Revision Number 26.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

OutputAmbientOcclusion Property (IRayTraceRendererOptions)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IRayTraceRendererOptions Interface](#) : OutputAmbientOcclusion Property (IRayTraceRendererOptions)

Gets or sets whether to render with ambient occlusion.

.NET Syntax

Visual Basic (Declaration)

Property OutputAmbientOcclusion As System.Boolean

Visual Basic (Usage)



```
Dim instance As IRayTraceRendererOptions  
Dim value As System.Boolean
```

```
instance.OutputAmbientOcclusion = value
```

```
value = instance.OutputAmbientOcclusion
```

C#

```
System.bool OutputAmbientOcclusion {get; set;}
```

C++/CLI

```
property System.bool OutputAmbientOcclusion {  
    System.bool get();  
    void set ( & System.bool value);  
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

True to render with ambient occlusion, false to not

Visual Basic for Applications (VBA) Syntax

See [RayTraceRendererOptions::OutputAmbientOcclusion](#).

Remarks

Ambient occlusion is a global lighting method that adds realism to models by controlling the attenuation of ambient light due to occluded areas. Objects appear as they would on an overcast day

See Also

[IRayTraceRendererOptions Interface](#)
[IRayTraceRendererOptions Members](#)

Availability

SOLIDWORKS 2016 FCS, Revision Number 24.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

PreviewRenderQuality Property (IRayTraceRendererOptions)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IRayTraceRendererOptions Interface](#) : PreviewRenderQuality Property (IRayTraceRendererOptions)

Gets or sets the quality of the rendering in the preview window.

.NET Syntax

Visual Basic (Declaration)

Property PreviewRenderQuality As System.Integer

Visual Basic (Usage)



```
Dim instance As IRayTraceRendererOptions  
Dim value As System.Integer
```

```
instance.PreviewRenderQuality = value
```

```
value = instance.PreviewRenderQuality
```

C#

```
System.int PreviewRenderQuality {get; set;}
```

C++/CLI

```
property System.int PreviewRenderQuality {  
    System.int get();  
    void set ( & System.int value);  
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

Quality of the rendering in the preview window as defined in [swRayTraceRenderQuality_e](#)

Visual Basic for Applications (VBA) Syntax

See [RayTraceRendererOptions::PreviewRenderQuality](#).

Example

[Render Model \(C#\)](#)
[Render Model \(VB.NET\)](#)
[Render Model \(VBA\)](#)

See Also

[IRayTraceRendererOptions Interface](#)
[IRayTraceRendererOptions Members](#)
[IRayTraceRenderer::DisplayPreviewWindow Method](#)

Availability

SOLIDWORKS 2011 FCS, Revision Number 19.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

RenderAnnotationsToSeparateImage Property (IRayTraceRendererOptions)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IRayTraceRendererOptions Interface](#) : RenderAnnotationsToSeparateImage Property (IRayTraceRendererOptions)

Gets or sets whether to render annotations and dimensions visible in the model to a separate image file.

Visual Basic Syntax

Visual Basic (Declaration)

Property RenderAnnotationsToSeparateImage As System.Boolean

Visual Basic (Usage)



```
Dim instance As IRayTraceRendererOptions
Dim value As System.Boolean

instance.RenderAnnotationsToSeparateImage = value
value = instance.RenderAnnotationsToSeparateImage
```

C#

```
System.bool RenderAnnotationsToSeparateImage {get; set;}
```

C++/CLI

```
property System.bool RenderAnnotationsToSeparateImage {
    System.bool get();
    void set ( & System.bool value);
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

True to render annotations and dimensions visible in the model to a separate image file, false to not

Visual Basic for Applications (VBA) Syntax

See [RayTraceRendererOptions::RenderAnnotationsToSeparateImage](#).

Example

[Render Annotations to Separate Image File \(C#\)](#)
[Render Annotations to Separate Image File \(VB.NET\)](#)
[Render Annotations to Separate Image File \(VBA\)](#)

Remarks

This property is only available when:

- [rendering to a file](#). This property is not available when only [invoking the final render window](#).
- [IRayTraceRendererOptions.IncludeAnnotationsInRendering](#) is set to true.

When this property is set to true, then SOLIDWORKS API appends **_1** to the name of the render file. For example, if you named the render file **abc.png**, then this property creates a file named **abc_1.png** that contains only the annotations and dimensions visible in the model.

See Also

[IRayTraceRendererOptions Interface](#)
[IRayTraceRendererOptions Members](#)

Availability

SOLIDWORKS 2016 FCS, Revision Number 24.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

RenderType Property (IRayTraceRendererOptions)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IRayTraceRendererOptions Interface](#) : RenderType Property (IRayTraceRendererOptions)

Gets or sets whether to render with contour or cartoon lines.

Visual Basic Syntax

```
Property RenderType As System.Integer
```



```
Dim instance As IRayTraceRendererOptions
Dim value As System.Integer

instance.RenderType = value

value = instance.RenderType
```

```
System.int RenderType {get; set;}
```

```
property System.int RenderType {
    System.int get();
    void set ( & System.int value);
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

Render type as defined by [swRayTraceRenderingType_e](#)

Visual Basic for Applications (VBA) Syntax

See [RayTraceRendererOptions::RenderType](#).

Example

[Render Model \(C#\)](#)
[Render Model \(VB.NET\)](#)
[Render Model \(VBA\)](#)
[Update Graphics Area After Changing Render Options \(C#\)](#)
[Update Graphics Area After Changing Render Options \(VB.NET\)](#)
[Update Graphics Area After Changing Render Options \(VBA\)](#)

Remarks

This property is only available when [IRayTraceRendererOptions::ContourCartoonRenderingEnabled](#) is true.

See Also

[IRayTraceRendererOptions Interface](#)
[IRayTraceRendererOptions Members](#)
[IRayTraceRendererOptions::HasCartoonEdges Property\(\)](#)
[IRayTraceRendererOptions::HasCartoonShading Property\(\)](#)
[IRayTraceRendererOptions::ShadedContour Property\(\)](#)

Availability

SOLIDWORKS 2016 FCS, Revision Number 24.0

SendDataForNetworkJob Property (IRayTraceRendererOptions)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IRayTraceRendererOptions Interface](#) : SendDataForNetworkJob Property (IRayTraceRendererOptions)

Gets or sets whether to send rendering data over the network.

.NET Syntax

Property SendDataForNetworkJob As System.Boolean

Visual Basic (Usage)



```
Dim instance As IRayTraceRendererOptions  
Dim value As System.Boolean
```

```
instance.SendDataForNetworkJob = value
```

```
value = instance.SendDataForNetworkJob
```

C#

```
System.bool SendDataForNetworkJob {get; set;}
```

C++/CLI

```
property System.bool SendDataForNetworkJob {  
    System.bool get();  
    void set ( & System.bool value);  
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

True to send rendering data over the network, false to not

Visual Basic for Applications (VBA) Syntax

See [RayTraceRendererOptions::SendDataForNetworkJob](#).

Remarks

Use this property to send rendering data over the network instead of using a [shared network directory](#).

Sending rendering data over the network avoids issues with permissions and cross-platform configurations that might occur when using a share network directory.

NOTE: Only SOLIDWORKS Subscription Services customers can share the effort of rendering across multiple computers.

See Also

[IRayTraceRendererOptions Interface](#)
[IRayTraceRendererOptions Members](#)
[IRayTraceRendererOptions::ClientWorkload Property \(\)](#)
[IRayTraceRendererOptions::NetworkRendering Property \(\)](#)
[IRayTraceRendererOptions::OffloadedRendering Property \(\)](#)

Availability

SOLIDWORKS 2016 FCS, Revision Number 24.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

ShadedContour Property (IRayTraceRendererOptions)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IRayTraceRendererOptions Interface](#) : ShadedContour Property (IRayTraceRendererOptions)

Gets or sets whether to shade the contours lines.

.NET Syntax

Visual Basic (Declaration)

```
Property ShadedContour As System.Boolean
```

Visual Basic (Usage)



```
Dim instance As IRayTraceRendererOptions
Dim value As System.Boolean

instance.ShadedContour = value

value = instance.ShadedContour
```

C#

```
System.bool ShadedContour {get; set;}
```

C++/CLI

```
property System.bool ShadedContour {
    System.bool get();
    void set ( & System.bool value);
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

True to shade the contour lines, false to not

Visual Basic for Applications (VBA) Syntax

See [RayTraceRendererOptions::ShadedContour](#).

Example

[Render Model \(C#\)](#)
[Render Model \(VB.NET\)](#)
[Render Model \(VBA\)](#)

Remarks

This property is only available when [IRayTraceRendererOptions::ContourCartoonRenderingEnabled](#) is true and [IRayTraceRendererOptions::RenderType](#) is `swRayTraceRenderingType_e.swRayTraceContour`.

See Also

[IRayTraceRendererOptions Interface](#)
[IRayTraceRendererOptions Members](#)
[IRayTraceRendererOptions::ContourLineColor Property](#)
[IRayTraceRendererOptions::ContourLineThickness Property](#)

Availability

SOLIDWORKS 2011 FCS, Revision Number 19.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

UpdateGraphics Method (IRayTraceRendererOptions)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IRayTraceRendererOptions Interface](#) : UpdateGraphics Method (IRayTraceRendererOptions)

Updates the graphics area.

.NET Syntax

Visual Basic (Declaration)

```
Sub UpdateGraphics()
```

Visual Basic (Usage)



```
Dim instance As IRayTraceRendererOptions

instance.UpdateGraphics()
```

C#

```
void UpdateGraphics()
```

C++/CLI

```
void UpdateGraphics();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Visual Basic for Applications (VBA) Syntax

See [RayTraceRendererOptions.UpdateGraphics](#).

Example

[Update Graphics Area After Changing Render Options \(C#\)](#)
[Update Graphics Area After Changing Render Options \(VB.NET\)](#)
[Update Graphics Area After Changing Render Options \(VBA\)](#)

Remarks

To visually verify your changes after changing a model's ray-trace rendering engine's options and before rendering the model, call this method.

See Also

[IRayTraceRendererOptions Interface](#)
[IRayTraceRendererOptions Members](#)
[IRayTraceRenderer.InvokeFinalRender Method \(\)](#)
[IRayTraceRenderer.RenderToFile Method \(\)](#)

Availability

SOLIDWORKS 2016 FCS, Revision Number 24.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

UseSceneBackgroundImageAspectRatio Property (IRayTraceRendererOptions)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IRayTraceRendererOptions Interface](#) : UseSceneBackgroundImageAspectRatio Property (IRayTraceRendererOptions)

Gets or sets whether to use the aspect ratio of the scene's background image for ray-trace rendering engine preview and final renders.

.NET Syntax

Visual Basic (Declaration)

```
Property UseSceneBackgroundImageAspectRatio As System.Boolean
```

Visual Basic (Usage)



```
Dim instance As IRayTraceRendererOptions  
Dim value As System.Boolean  
  
instance.UseSceneBackgroundImageAspectRatio = value  
  
value = instance.UseSceneBackgroundImageAspectRatio
```

C#

```
System.bool UseSceneBackgroundImageAspectRatio {get; set;}
```

C++/CLI

```
property System.bool UseSceneBackgroundImageAspectRatio {  
    System.bool get();  
    void set ( & System.bool value);  
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

True to use the aspect ratio of the scene's background image for ray-trace rendering engine preview and final renders, false to not

Visual Basic for Applications (VBA) Syntax

See [RayTraceRendererOptions::UseSceneBackgroundImageAspectRatio](#).

See Also

[IRayTraceRendererOptions Interface](#)
[IRayTraceRendererOptions Members](#)
[IRayTraceRendererOptions::UseSolidWorksViewAspectRatio Property \(\)](#)

Availability

SOLIDWORKS 2011 FCS, Revision Number 19.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

UseSolidWorksViewAspectRatio Property (IRayTraceRendererOptions)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IRayTraceRendererOptions Interface](#) : UseSolidWorksViewAspectRatio Property (IRayTraceRendererOptions)

Gets or sets whether to use the aspect ratio of the SOLIDWORKS view for ray-trace rendering engine preview and final renders.

.NET Syntax

Visual Basic (Declaration)

Property UseSolidWorksViewAspectRatio As System.Boolean

Visual Basic (Usage)



```
Dim instance As IRayTraceRendererOptions  
Dim value As System.Boolean  
  
instance.UseSolidWorksViewAspectRatio = value  
value = instance.UseSolidWorksViewAspectRatio
```

C#

```
System.bool UseSolidWorksViewAspectRatio {get; set;}
```

C++/CLI

```
property System.bool UseSolidWorksViewAspectRatio {  
    System.bool get();  
    void set ( & System.bool value);  
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

True to use the aspect ratio of the SOLIDWORKS view for ray-trace rendering engine preview and final renders, false to not

Visual Basic for Applications (VBA) Syntax

See [RayTraceRendererOptions::UseSolidWorksViewAspectRatio](#).

Example

See the [IRayTraceRendererOptions](#) examples.

See Also

[IRayTraceRendererOptions Interface](#)
[IRayTraceRendererOptions Members](#)

Availability

SOLIDWORKS 2015 FCS, Revision Number 23.0

IRefAxis (Type)

SOLIDWORKS API Help

[Send comments](#) on this topic.

IRefAxis Interface

[See Also](#) [Members](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) : IRefAxis Interface

Allows access to reference axis definitions.

NOTE: Click the **Members** link, located near the top of the topic, to see this interface's methods and properties.

.NET Syntax

Visual Basic (Declaration)

```
Public Interface IRefAxis
```

Visual Basic (Usage)



```
Dim instance As IRefAxis
```

C#

```
public interface IRefAxis
```

C++/CLI

```
public interface class IRefAxis
```

Visual Basic for Applications (VBA) Syntax

See [RefAxis](#).

Example

[Get Info on Plane-Axis \(C++\)](#)
[Get Parameters of Reference Axis \(VBA\)](#)
[Get Reference Axis Data \(VBA\)](#)
[Get Reference Axis Data \(VB.NET\)](#)
[Get Reference Axis Data \(C#\)](#)

Accessors

[IAngleMateFeatureData::EntitiesToMate](#)
[IAngleMateFeatureData::ReferenceEntity](#)
[IBoundaryBossFeatureData::GetDirectionVector](#)
[IChainPatternFeatureData::Group1PathLink1](#)
[IChainPatternFeatureData::Group1PathLink2](#)
[IChainPatternFeatureData::Group2PathLink1](#)
[IChainPatternFeatureData::Group2PathLink2](#)
[ICircularPatternFeatureData::Axis](#)
[ICoincidentMateFeatureData::EntitiesToMate](#)
[IConcentricMateFeatureData::EntitiesToMate](#)
[IDistanceMateFeatureData::EntitiesToMate](#)
[IExplodeStep::DivergeDirection](#)
[IFeature::GetSpecificFeature2](#)
[IGearMateFeatureData::EntitiesToMate](#)
[IHingeMateFeatureData::EntitiesToMate](#)
[ILinearPatternFeatureData::D1Axis](#)
[ILinearPatternFeatureData::D2Axis](#)

[ILocalCircularPatternFeatureData::Axis](#)
[ILocalLinearPatternFeatureData::D1Axis](#)
[ILocalLinearPatternFeatureData::D2Axis](#)
[ILocalLinearPatternFeatureData::RotationAxis](#)
[IMoveFaceFeatureData::GetDirectionReference](#)
[IPartExplodeStep::GetExplodeDirection](#)
[IPartingLineFeatureData::PullDirectionBase](#)
[IPartingSurfaceFeatureData::PullDirectionBase](#)
[IRackPinionMateFeatureData::EntitiesToMate](#)
[IRevolveFeatureData2::Axis](#)
[IScrewMateFeatureData::EntitiesToMate](#)
[ISlotMateFeatureData::EntitiesToMate](#)
[ISplitLineFeatureData::PullDirectionBase](#)
[IStructureSystemMemberProfile::ProfileAlignmentObject](#)
[ISweepFeatureData::EndDirectionVector](#)
[ISweepFeatureData::GetPathAlignmentDirectionVector](#)
[ISweepFeatureData::StartDirectionVector](#)
[ISymmetricMateFeatureData::EntitiesToMate](#)
[IWidthMateFeatureData::TabSelection](#)
[IWrapSketchFeatureData::PullDirection](#)

 Access Diagram

[RefAxis](#)

 See Also

[IRefAxis Members](#)
[SolidWorks.Interop.sldworks.Namespace](#)
[IRefAxisFeatureData Interface](#)

IRefAxis Interface Methods

[See Also](#)



[SolidWorks.Interop.sldworks.Namespace](#) : IRefAxis Interface

For a list of all members of this type, see [IRefAxis members](#).

 Public Methods

Name	Description
 GetRefAxisParams	Gets information for a reference axis.
 GetTempAxisReferenceFace	Gets the reference face for this temporary axis.
 IGetRefAxisParams	Gets information for a reference axis.
 IsTempAxis	Gets whether the reference axis is a temporary axis.

[Top](#)

 See Also

[IRefAxis Interface](#)
[SolidWorks.Interop.sldworks.Namespace](#)
[IRefAxisFeatureData Interface](#)

IRefAxis Interface Members

[See Also](#) [Methods](#)



[SolidWorks.Interop.sldworks.Namespace](#) : IRefAxis Interface

The following tables list the members exposed by [IRefAxis](#).

Public Methods		
Name	Description	
 GetRefAxisParams	Gets information for a reference axis.	
 GetTempAxisReferenceFace	Gets the reference face for this temporary axis.	
 IGetRefAxisParams	Gets information for a reference axis.	
 IsTempAxis	Gets whether the reference axis is a temporary axis.	

[Top](#)

See Also

[IRefAxis Interface](#)
[SolidWorks.Interop.sldworks Namespace](#)
[IRefAxisFeatureData Interface](#)

GetRefAxisParams Method (IRefAxis)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IRefAxis Interface](#) : GetRefAxisParams Method (IRefAxis)

Gets information for a reference axis.

.NET Syntax

Visual Basic (Declaration)

Function GetRefAxisParams() As System.Object

Visual Basic (Usage)



```
Dim instance As IRefAxis  
Dim value As System.Object  
  
value = instance.GetRefAxisParams()
```

C#

System.object GetRefAxisParams()

C++/CLI

System.Object^ GetRefAxisParams();

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Return Value

Array of doubles (see [Remarks](#))

Visual Basic for Applications (VBA) Syntax

See [RefAxis::GetRefAxisParams](#).

Example

[Get Parameters for Reference Axis \(VBA\)](#)

Remarks

The return value is the following array of doubles:

[StartPt[3], EndPt[3]]

where:

- *StartPt[3]* = array of three values describing the x,y,z start point of the reference axis.
- *EndPt[3]* = array of three values describing the x,y,z end point of the reference axis.

See Also

[IRefAxis Interface](#)
[IRefAxis Members](#)
[IRefAxis.IGetRefAxisParams Method](#)

SOLIDWORKS API Help

[Send comments on this topic.](#)

GetTempAxisReferenceFace Method (IRefAxis)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IRefAxis Interface](#) : GetTempAxisReferenceFace Method (IRefAxis)

Gets the reference face for this temporary axis.

.NET Syntax

Visual Basic (Declaration)

```
Function GetTempAxisReferenceFace() As System.Object
```

Visual Basic (Usage)



```
Dim instance As IRefAxis
Dim value As System.Object

value = instance.GetTempAxisReferenceFace()
```

C#

```
System.object GetTempAxisReferenceFace()
```

C++/CLI

```
System.Object^ GetTempAxisReferenceFace();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Return Value

Reference face for this temporary axis

Visual Basic for Applications (VBA) Syntax

See [RefAxis.GetTempAxisReferenceFace](#).

Example

[Get Temporary Axis and Its Reference Face \(C#\)](#)
[Get Temporary Axis and Its Reference Face \(VB.NET\)](#)
[Get Temporary Axis and Its Reference Face \(VBA\)](#)

See Also

[IRefAxis Interface](#)
[IRefAxis Members](#)
[IRefAxis.IsTempAxis Method \(\)](#)

Availability

SOLIDWORKS 2017 FCS, Revision Number 25.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

IGetRefAxisParams Method (IRefAxis)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IRefAxis Interface](#) : IGetRefAxisParams Method (IRefAxis)

Gets information for a reference axis.

.NET Syntax

Visual Basic (Declaration)

```
Function IGetRefAxisParams() As System.Double
```

Visual Basic (Usage)



```
Dim instance As IRefAxis
Dim value As System.Double

value = instance.IGetRefAxisParams()
```

C#

```
System.double IGetRefAxisParams()
```

C++/CLI

```
System.double IGetRefAxisParams();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Return Value

- in-process, unmanaged C++: Pointer to an array of doubles (see [Remarks](#))
 - VBA, VB.NET, C#, and C++/CLI: Not supported
- See [In-process Methods](#) for details about this type of method.

Example

[Get Info on Plane-Axis \(C++\)](#)

Remarks

The return value is the following array of doubles:

[*StartPt*[3], *EndPt*[3]]

where:

- *StartPt*[3] = array of three values describing the x,y,z start point of the reference axis.
- *EndPt*[3] = array of three values describing the x,y,z end point of the reference axis.

See Also

[IRefAxis Interface](#)
[IRefAxis Members](#)
[IRefAxis::GetRefAxisParams Method](#)

SOLIDWORKS API Help

[Send comments on this topic.](#)

IsTempAxis Method (IRefAxis)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IRefAxis Interface](#) : IsTempAxis Method (IRefAxis)

Gets whether the reference axis is a temporary axis.

.NET Syntax

Visual Basic (Declaration)

```
Function IsTempAxis() As System.Boolean
```

Visual Basic (Usage)



```
Dim instance As IRefAxis
Dim value As System.Boolean
```

```
value = instance.IsTempAxis()
```

C#

```
System.bool IsTempAxis()
```

C++/CLI

```
System.bool IsTempAxis();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Return Value

True if the reference axis is a temporary axis, false if not

Visual Basic for Applications (VBA) Syntax

See [RefAxis::IsTempAxis](#).

Example

[Get Temporary Axis and Its Reference Face \(C#\)](#)
[Get Temporary Axis and Its Reference Face \(VB.NET\)](#)
[Get Temporary Axis and Its Reference Face \(VBA\)](#)

See Also

[IRefAxis Interface](#)
[IRefAxis Members](#)
[IRefAxis::GetTempAxisReferenceFace](#)

Availability

SOLIDWORKS 2017 FCS, Revision Number 25.0