

SOLIDWORKS API (.NET VBA C#) — Reference

(266/337): ISketchArc

SOLIDWORKS API Documentation (converted from CHM)

ISketchArc (Type)

ISketchArc Interface

[See Also](#) [Members](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) : ISketchArc Interface

Provides access to properties and methods for sketched arc entities.

NOTE: Click the **Members** link, located near the top of the topic, to see this interface's methods and properties.

.NET Syntax

Visual Basic (Declaration)

```
Public Interface ISketchArc
```

Visual Basic (Usage)

```
Dim instance As ISketchArc
```

C#

```
public interface ISketchArc
```

C++/CLI

```
public interface class ISketchArc
```

Visual Basic for Applications (VBA) Syntax

See [SketchArc](#).

Example

[Get Sketch Arc Data \(VBA\)](#)
[Get Sketch Arc Data \(VB.NET\)](#)
[Get Sketch Arc Data \(C#\)](#)

Accessors

[IRackPinionMateFeatureData::EntitiesToMate](#)
[ISketchManager::CreateArc](#)
[ISketchManager::PerimeterCircle](#)
[ISweepFeatureData::GuideCurves](#)

Access Diagram

[SketchArc](#)

See Also

[ISketchArc Members](#)
[SolidWorks.Interop.sldworks Namespace](#)
[IModelDoc2::SketchArc Method](#)

ISketchArc Interface Members

[See Also](#) [Methods](#)



[SolidWorks.Interop.sldworks Namespace](#) : ISketchArc Interface

The following tables list the members exposed by [ISketchArc](#).

Public Methods

Name	Description
 GetCenterPoint	Obsolete. Superseded by ISketchArc.GetCenterPoint2 and ISketchArc.IGetCenterPoint2
 GetCenterPoint2	Gets the sketch point for the center point of the arc.
 GetEndPoint	Obsolete. Superseded by ISketchArc.GetEndPoint2 and ISketchArc.IGetEndPoint2
 GetEndPoint2	Gets the sketch point for the end point of the arc.
 GetNormalVector	Gets the normal to the arc.
 GetRadius	Gets the radius of the arc.
 GetRotationDir	Gets the rotation direction of this sketch arc.
 GetStartPoint	Obsolete. Superseded by ISketchArc.GetStartPoint2 and ISketchArc.IGetStartPoint2
 GetStartPoint2	Gets the sketch point for the start point of this arc.
 IGetCenterPoint	Obsolete. Superseded by ISketchArc.GetCenterPoint2 and ISketchArc.IGetCenterPoint2
 IGetCenterPoint2	Gets the sketch point for the center point of the arc.
 IGetEndPoint	Obsolete. Superseded by ISketchArc.GetEndPoint2 and ISketchArc.IGetEndPoint2
 IGetEndPoint2	Gets the sketch point for the end point of the arc.
 IGetNormalVector	Gets the normal to the arc.
 IGetStartPoint	Obsolete. Superseded by ISketchArc.GetStartPoint2 and ISketchArc.IGetStartPoint2
 IGetStartPoint2	Gets the sketch point for the start point of this arc.
 IsCircle	Gets whether the sketch arc is a complete circle or a partial arc.
 SetRadius	Sets the radius of the arc.

[Top](#)

 See Also

[ISketchArc Interface](#)
[SolidWorks.Interop.sldworks Namespace](#)
[IModelDoc2::SketchArc Method](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

ISketchArc Interface Methods

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) : ISketchArc Interface

For a list of all members of this type, see [ISketchArc members](#).

 Public Methods

Name	Description
 GetCenterPoint	Obsolete. Superseded by ISketchArc.GetCenterPoint2 and ISketchArc.IGetCenterPoint2
 GetCenterPoint2	Gets the sketch point for the center point of the arc.
 GetEndPoint	Obsolete. Superseded by ISketchArc.GetEndPoint2 and ISketchArc.IGetEndPoint2
 GetEndPoint2	Gets the sketch point for the end point of the arc.
 GetNormalVector	Gets the normal to the arc.
 GetRadius	Gets the radius of the arc.
 GetRotationDir	Gets the rotation direction of this sketch arc.
 GetStartPoint	Obsolete. Superseded by ISketchArc.GetStartPoint2 and ISketchArc.IGetStartPoint2
 GetStartPoint2	Gets the sketch point for the start point of this arc.
 IGetCenterPoint	Obsolete. Superseded by ISketchArc.GetCenterPoint2 and ISketchArc.IGetCenterPoint2
 IGetCenterPoint2	Gets the sketch point for the center point of the arc.
 IGetEndPoint	Obsolete. Superseded by ISketchArc.GetEndPoint2 and ISketchArc.IGetEndPoint2
 IGetEndPoint2	Gets the sketch point for the end point of the arc.



[IGetNormalVector](#)

Gets the normal to the arc.



[IGetStartPoint](#)

Obsolete. Superseded by [ISketchArc.GetStartPoint2](#) and [ISketchArc.IGetStartPoint2](#)



[IGetStartPoint2](#)

Gets the sketch point for the start point of this arc.



[IsCircle](#)

Gets whether the sketch arc is a complete circle or a partial arc.



[SetRadius](#)

Sets the radius of the arc.

[Top](#)

See Also

[ISketchArc Interface](#)

[SolidWorks.Interop.sldworks Namespace](#)

[IModelDoc2::SketchArc Method](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

GetCenterPoint Method (ISketchArc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISketchArc Interface](#) : GetCenterPoint Method (ISketchArc)

Obsolete. Superseded by [ISketchArc::GetCenterPoint2](#) and [ISketchArc.IGetCenterPoint2](#).

.NET Syntax

Visual Basic (Declaration)

```
Function GetCenterPoint() As System.Object
```

Visual Basic (Usage)



```
Dim instance As ISketchArc  
Dim value As System.Object
```

```
value = instance.GetCenterPoint()
```

C#

```
System.object GetCenterPoint()
```

C++/CLI

```
System.Object^ GetCenterPoint();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Visual Basic for Applications (VBA) Syntax

See [SketchArc::GetCenterPoint](#).

See Also

[ISketchArc Interface](#)

[ISketchArc Members](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

GetCenterPoint2 Method (ISketchArc)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISketchArc Interface](#) : GetCenterPoint2 Method (ISketchArc)

Gets the sketch point for the center point of the arc.

.NET Syntax

Visual Basic (Declaration)

```
Function GetCenterPoint2() As System.Object
```

Visual Basic (Usage)



```
Dim instance As ISketchArc
Dim value As System.Object

value = instance.GetCenterPoint2()
```

C#

```
System.object GetCenterPoint2()
```

C++/CLI

```
System.Object^ GetCenterPoint2();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Return Value

[Sketch point](#)

Visual Basic for Applications (VBA) Syntax

See [SketchArc::GetCenterPoint2](#).

Example

See the [ISketchArc](#) examples.

Example

[Create Imported Surface Body From Sketch \(C#\)](#)
[Get All Elements of Sketch \(VBA\)](#)

See Also

[ISketchArc Interface](#)
[ISketchArc Members](#)
[ISketchArc::IGetCenterPoint2 Method](#)
[ISketchArc::GetEndPoint2 Method](#)
[ISketchArc::IGetEndPoint2 Method](#)
[ISketchArc::GetStartPoint2 Method](#)
[ISketchArc::IGetStartPoint2 Method](#)

Availability

SOLIDWORKS 2000 FCS, Revision Number 8.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

GetEndPoint Method (ISketchArc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISketchArc Interface](#) : GetEndPoint Method (ISketchArc)

Obsolete. Superseded by [ISketchArc::GetEndPoint2](#) and [ISketchArc::IGetEndPoint2](#).

.NET Syntax

Visual Basic (Declaration)

```
Function GetEndPoint() As System.Object
```

Visual Basic (Usage)



```
Dim instance As ISketchArc
Dim value As System.Object
```

```
value = instance.GetEndPoint()
```

C#

```
System.Object GetEndPoint()
```

C++/CLI

```
System.Object^ GetEndPoint();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Visual Basic for Applications (VBA) Syntax

See [SketchArc::GetEndPoint](#).

See Also

[ISketchArc Interface](#)
[ISketchArc Members](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

GetEndPoint2 Method (ISketchArc)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISketchArc Interface](#) : GetEndPoint2 Method (ISketchArc)

Gets the sketch point for the end point of the arc.

.NET Syntax

Visual Basic (Declaration)

```
Function GetEndPoint2() As System.Object
```

Visual Basic (Usage)



```
Dim instance As ISketchArc  
Dim value As System.Object  
  
value = instance.GetEndPoint2()
```

C#

```
System.Object GetEndPoint2()
```

C++/CLI

```
System.Object^ GetEndPoint2();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Return Value

[Sketch point](#)

Visual Basic for Applications (VBA) Syntax

See [SketchArc::GetEndPoint2](#).

Example

See the [ISketchArc](#) examples.

Example

[Create Imported Surface Body From Sketch \(C#\)](#)
[Get All Elements of Sketch \(VBA\)](#)

See Also

[ISketchArc Interface](#)
[ISketchArc Members](#)
[ISketchArc::IGetEndPoint2 Method](#)
[ISketchArc::GetCenterPoint2 Method](#)
[ISketchArc::GetStartPoint2 Method](#)
[ISketchArc::IGetCenterPoint2 Method](#)
[ISketchArc::IGetStartPoint2 Method](#)

Availability

SOLIDWORKS 2000 FCS, Revision Number 8.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

GetNormalVector Method (ISketchArc)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISketchArc Interface](#) : GetNormalVector Method (ISketchArc)

Gets the normal to the arc.

.NET Syntax

Visual Basic (Declaration)

```
Function GetNormalVector() As System.Object
```

Visual Basic (Usage)



```
Dim instance As ISketchArc  
Dim value As System.Object
```

```
value = instance.GetNormalVector()
```

C#

```
System.object GetNormalVector()
```

C++/CLI

```
System.Object^ GetNormalVector();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Return Value

Array of 3 doubles (x,y,z), which represents the unit vector normal to the arc

Visual Basic for Applications (VBA) Syntax

See [SketchArc::GetNormalVector](#).

Example

See the [ISketchArc](#) examples.

Example

[Create Imported Surface Body From Sketch \(C#\)](#)
[Get All Elements of Sketch \(VBA\)](#)

See Also

[ISketchArc Interface](#)
[ISketchArc Members](#)
[ISketchArc::GetNormalVector Method](#)

Availability

GetRadius Method (ISketchArc)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISketchArc Interface](#) : GetRadius Method (ISketchArc)

Gets the radius of the arc.

.NET Syntax

Visual Basic (Declaration)

```
Function GetRadius() As System.Double
```

Visual Basic (Usage)



```
Dim instance As ISketchArc  
Dim value As System.Double  
  
value = instance.GetRadius()
```

C#

```
System.double GetRadius()
```

C++/CLI

```
System.double GetRadius();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Return Value

Radius in meters of the arc

Visual Basic for Applications (VBA) Syntax

See [SketchArc::GetRadius](#).

Example

See the [ISketchArc](#) examples.

Example

[Create Imported Surface Body From Sketch \(C#\)](#)
[Get All Elements of Sketch \(VBA\)](#)

See Also

[ISketchArc Interface](#)
[ISketchArc Members](#)
[ISketchArc::SetRadius Method](#)

Availability

SOLIDWORKS 2000 FCS, Revision Number 8.0

GetRotationDir Method (ISketchArc)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISketchArc Interface](#) : GetRotationDir Method (ISketchArc)

Gets the rotation direction of this sketch arc.

.NET Syntax

```
Function GetRotationDir() As System.Integer
```



```
Dim instance As ISketchArc
Dim value As System.Integer

value = instance.GetRotationDir()
```

```
System.int GetRotationDir()
```

```
System.int GetRotationDir();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Return Value

Rotation direction with respect to the normal of the arc's sketch plane (counterclockwise = 1, clockwise = -1) (see **Remarks**)

Visual Basic for Applications (VBA) Syntax

See [SketchArc::GetRotationDir](#).

Example

See the [ISketchArc](#) examples.

Example

[Get All Elements in Sketch \(VBA\)](#)

Remarks

This method determines the direction that the sketch proceeds around this arc, beginning at the arc's start point and ending at the arc's end point. The direction is with respect to the normal of the arc's sketch plane and not with respect to the viewer.

If the normal to the arc's sketch plane is...	And the normal to the arc is...	And this method returns...	It means that...
(0, 0, -1)	(0, 0, 1)	1 (counterclockwise)	With respect to its sketch plane's normal (from behind the screen), the arc travels counterclockwise from its start point to its end point. Note that from the perspective of the viewer (in front of the screen), the arc travels clockwise from its start point to its end point.

See Also

[ISketchArc Interface](#)
[ISketchArc Members](#)

Availability

SOLIDWORKS 99, datecode 1999207

GetStartPoint Method (ISketchArc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISketchArc Interface](#) : GetStartPoint Method (ISketchArc)

Obsolete. Superseded by [ISketchArc::GetStartPoint2](#) and [ISketchArc::IGetStartPoint2](#).

.NET Syntax

Visual Basic (Declaration)

```
Function GetStartPoint() As System.Object
```

Visual Basic (Usage)



```
Dim instance As ISketchArc  
Dim value As System.Object  
  
value = instance.GetStartPoint()
```

C#

```
System.object GetStartPoint()
```

C++/CLI

```
System.Object^ GetStartPoint();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Visual Basic for Applications (VBA) Syntax

See [SketchArc::GetStartPoint](#).

See Also

[ISketchArc Interface](#)
[ISketchArc Members](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

GetStartPoint2 Method (ISketchArc)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISketchArc Interface](#) : GetStartPoint2 Method (ISketchArc)

Gets the sketch point for the start point of this arc.

.NET Syntax

Visual Basic (Declaration)

```
Function GetStartPoint2() As System.Object
```

Visual Basic (Usage)



```
Dim instance As ISketchArc  
Dim value As System.Object  
  
value = instance.GetStartPoint2()
```

C#

```
System.object GetStartPoint2()
```

C++/CLI

```
System.Object^ GetStartPoint2();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Return Value

[Sketch point](#)

Visual Basic for Applications (VBA) Syntax

See [SketchArc::GetStartPoint2](#).

Example

See the [ISketchArc](#) examples.

Example

[Create Imported Surface Body from Sketch \(C#\)](#)
[Get All Elements of Sketch \(VBA\)](#)

See Also

[ISketchArc Interface](#)
[ISketchArc Members](#)
[ISketchArc::IGetStartPoint2 Method](#)
[ISketchArc::GetEndPoint2 Method](#)
[ISketchArc::GetCenterPoint2 Method](#)
[ISketchArc::IGetCenterPoint2 Method](#)
[ISketchArc::IGetEndPoint2 Method](#)

Availability

SOLIDWORKS 2000 FCS, Revision Number 8.0

SOLIDWORKS API Help

[Send comments](#) on this topic.

IGetCenterPoint Method (ISketchArc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISketchArc Interface](#) : IGetCenterPoint Method (ISketchArc)

Obsolete. Superseded by [ISketchArc::GetCenterPoint2](#) and [ISketchArc::IGetCenterPoint2](#).

.NET Syntax

Visual Basic (Declaration)

```
Function IGetCenterPoint() As System.Double
```

Visual Basic (Usage)



```
Dim instance As ISketchArc  
Dim value As System.Double  
  
value = instance.IGetCenterPoint()
```

C#

```
System.double IGetCenterPoint()
```

C++/CLI

```
System.double IGetCenterPoint();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Visual Basic for Applications (VBA) Syntax

See [SketchArc::IGetCenterPoint](#).

See Also

[ISketchArc Interface](#)
[ISketchArc Members](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

IGetCenterPoint2 Method (ISketchArc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISketchArc Interface](#) : IGetCenterPoint2 Method (ISketchArc)

Gets the sketch point for the center point of the arc.

 .NET Syntax

Visual Basic (Declaration)

```
Function IGetCenterPoint2() As SketchPoint
```

Visual Basic (Usage)  Copy Code

```
Dim instance As ISketchArc
Dim value As SketchPoint

value = instance.IGetCenterPoint2()
```

C#

```
SketchPoint IGetCenterPoint2()
```

C++/CLI

```
SketchPoint^ IGetCenterPoint2();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Return Value

[Sketch point](#)

 Visual Basic for Applications (VBA) Syntax

See [SketchArc.IGetCenterPoint2](#).

 See Also

- [ISketchArc Interface](#)
- [ISketchArc Members](#)
- [ISketchArc::GetCenterPoint2 Method](#)
- [ISketchArc::GetEndPoint2 Method](#)
- [ISketchArc::GetStartPoint2 Method](#)
- [ISketchArc::IGetEndPoint2 Method](#)
- [ISketchArc::IGetStartPoint2 Method](#)

 Availability

SOLIDWORKS 2000 FCS, Revision Number 8.0

SOLIDWORKS API Help [Send comments on this topic.](#)

IGetEndPoint Method (ISketchArc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISketchArc Interface](#) : IGetEndPoint Method (ISketchArc)

Obsolete. Superseded by [ISketchArc::GetEndPoint2](#) and [ISketchArc::IGetEndPoint2](#).

 .NET Syntax

Visual Basic (Declaration)

```
Function IGetEndPoint() As System.Double
```

Visual Basic (Usage)  Copy Code

```
Dim instance As ISketchArc
Dim value As System.Double

value = instance.IGetEndPoint()
```

C#

```
System.double IGetEndPoint()
```

C++/CLI

```
System.double IGetEndPoint();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Visual Basic for Applications (VBA) Syntax

See [SketchArc::IGetEndPoint](#).

See Also

[ISketchArc Interface](#)
[ISketchArc Members](#)

SOLIDWORKS API Help

[Send comments on this topic.](#)

IGetEndPoint2 Method (ISketchArc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISketchArc Interface](#) : IGetEndPoint2 Method (ISketchArc)

Gets the sketch point for the end point of the arc.

.NET Syntax

Visual Basic (Declaration)

```
Function IGetEndPoint2() As SketchPoint
```

Visual Basic (Usage)



```
Dim instance As ISketchArc  
Dim value As SketchPoint  
  
value = instance.IGetEndPoint2()
```

C#

```
SketchPoint IGetEndPoint2()
```

C++/CLI

```
SketchPoint^ IGetEndPoint2();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Return Value

[Sketch point](#)

Visual Basic for Applications (VBA) Syntax

See [SketchArc::IGetEndPoint2](#).

See Also

[ISketchArc Interface](#)
[ISketchArc Members](#)
[GetEndPoint2 Method](#)
[ISketchArc::GetCenterPoint2 Method](#)
[ISketchArc::GetStartPoint2 Method](#)
[ISketchArc::IGetCenterPoint2 Method](#)
[ISketchArc::IGetStartPoint2 Method](#)

Availability

SOLIDWORKS 2000 FCS, Revision Number 8.0

IGetNormalVector Method (ISketchArc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISketchArc Interface](#) : IGetNormalVector Method (ISketchArc)

Gets the normal to the arc.

.NET Syntax

Visual Basic (Declaration)

```
Function IGetNormalVector() As System.Double
```

Visual Basic (Usage)



```
Dim instance As ISketchArc  
Dim value As System.Double
```

```
value = instance.IGetNormalVector()
```

C#

```
System.double IGetNormalVector()
```

C++/CLI

```
System.double IGetNormalVector();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Return Value

- in-process, unmanaged C++: Pointer to an array of 3 doubles (x,y,z), which represents the unit vector normal to the arc
 - VBA, VB.NET, C#, and C++/CLI: Not supported
- See [In-process Methods](#) for details about this type of method.

See Also

[ISketchArc Interface](#)
[ISketchArc Members](#)
[ISketchArc::GetNormalVector Method](#)

Availability

SOLIDWORKS 2000 FCS, Revision Number 8.0

IGetStartPoint Method (ISketchArc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISketchArc Interface](#) : IGetStartPoint Method (ISketchArc)

Obsolete. Superseded by [ISketchArc::GetStartPoint2](#) and [ISketchArc::IGetStartPoint2](#).

.NET Syntax

Visual Basic (Declaration)

```
Function IGetStartPoint() As System.Double
```

Visual Basic (Usage)



```
Dim instance As ISketchArc  
Dim value As System.Double
```

```
value = instance.IGetStartPoint()
```

C#

```
System.double IGetStartPoint()
```

C++/CLI

```
System.double IGetStartPoint();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Visual Basic for Applications (VBA) Syntax

See [SketchArc::IGetStartPoint](#).

See Also

[ISketchArc Interface](#)
[ISketchArc Members](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

IGetStartPoint2 Method (ISketchArc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISketchArc Interface](#) : IGetStartPoint2 Method (ISketchArc)

Gets the sketch point for the start point of this arc.

.NET Syntax

Visual Basic (Declaration)

```
Function IGetStartPoint2() As SketchPoint
```

Visual Basic (Usage)



```
Dim instance As ISketchArc  
Dim value As SketchPoint
```

```
value = instance.IGetStartPoint2()
```

C#

```
SketchPoint IGetStartPoint2()
```

C++/CLI

```
SketchPoint^ IGetStartPoint2();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Return Value

[Sketch point](#)

Visual Basic for Applications (VBA) Syntax

See [SketchArc::IGetStartPoint2](#).

See Also

[ISketchArc Interface](#)
[ISketchArc Members](#)
[ISketchArc::GetStartPoint2 Method](#)
[ISketchArc::GetCenterPoint2 Method](#)
[ISketchArc::GetEndPoint2 Method](#)
[ISketchArc::IGetCenterPoint2 Method](#)
[ISketchArc::IGetEndPoint2 Method](#)

Availability

SOLIDWORKS 2000 FCS, Revision Number 8.0

IsCircle Method (ISketchArc)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISketchArc Interface](#) : IsCircle Method (ISketchArc)

Gets whether the sketch arc is a complete circle or a partial arc.

.NET Syntax

Visual Basic (Declaration)

```
Function IsCircle() As System.Integer
```

Visual Basic (Usage)



```
Dim instance As ISketchArc  
Dim value As System.Integer  
  
value = instance.IsCircle()
```

C#

```
System.int IsCircle()
```

C++/CLI

```
System.int IsCircle();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Return Value

1 if a complete circle, 0 if a partial arc

Visual Basic for Applications (VBA) Syntax

See [SketchArc::IsCircle](#).

Example

See the [ISketchArc](#) examples.

Example

[Get All Elements of Sketch \(VBA\)](#)

See Also

[ISketchArc Interface](#)
[ISketchArc Members](#)

Availability

SOLIDWORKS 99, datecode 1999207

SetRadius Method (ISketchArc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISketchArc Interface](#) : SetRadius Method (ISketchArc)

Sets the radius of the arc.

.NET Syntax

Visual Basic (Declaration)

```
Function SetRadius( _  
    ByVal Radius As System.Double _  
    ) As System.Boolean
```

Visual Basic (Usage)



```
Dim instance As ISketchArc  
Dim Radius As System.Double  
Dim value As System.Boolean  
  
value = instance.SetRadius(Radius)
```

C#

```
System.bool SetRadius(  
    System.double Radius  
)
```

C++/CLI

```
System.bool SetRadius(  
&    System.double Radius  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Radius

Radius in meters of the arc

Return Value

True if successful, false if not

Visual Basic for Applications (VBA) Syntax

See [SketchArc::SetRadius](#).

See Also

[ISketchArc Interface](#)
[ISketchArc Members](#)
[ISketchArc::GetRadius Method](#)

Availability

SOLIDWORKS 2000 FCS, Revision Number 8.0