

SOLIDWORKS API (NET VBA C#) — Reference

(280/337): ISketchText

SOLIDWORKS API Documentation (converted from CHM)

ISketchText (Type)

ISketchText Interface

[See Also](#) [Members](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) : ISketchText Interface

Provides access to sketched text entities.

NOTE: Click the **Members** link, located near the top of the topic, to see this interface's methods and properties.

.NET Syntax

Visual Basic (Declaration)

```
Public Interface ISketchText
```

Visual Basic (Usage)



```
Dim instance As ISketchText
```

C#

```
public interface ISketchText
```

C++/CLI

```
public interface class ISketchText
```

Visual Basic for Applications (VBA) Syntax

See [SketchText](#).

Example

[Get All Elements of Sketch \(VBA\)](#)
[Insert Sketch Text and Hole \(VBA\)](#)
[Insert Sketch Text and Hole \(VB.NET\)](#)
[Insert Sketch Text and Hole \(C#\)](#)

Accessors

[IModelDoc2::InsertSketchText](#) and [IModelDoc2::InsertSketchText](#)

Access Diagram

[SketchText](#)

See Also

[ISketchText Members](#)
[SolidWorks.Interop.sldworks Namespace](#)
[ITextFormat Interface](#)

ISketchText Interface Methods

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) : ISketchText Interface

For a list of all members of this type, see [ISketchText members](#).

Public Methods

Name	Description
EnumEdges	Gets the edges in this sketch text.
GetCoordinates	Gets the position of this sketch text.

		
	GetEdges	Obsolete. Superseded by ISketchText.GetEdges2
	GetEdges2	Gets the edges for this sketch text.
	GetTextFormat	Gets the text format for this sketch text.
	GetUseDocTextFormat	Gets whether default model text format is in use in this sketch text.
	IGetCoordinates	Gets the position of this sketch text.
	IGetTextFormat	Gets the text format for this sketch text.
	ISetTextFormat	Sets the text format for this sketch text.
	SetCoordinates	Sets the position of this sketch text.
	SetTextFormat	Sets the text format for this sketch text.

[Top](#)

See Also

[ISketchText Interface](#)
[SolidWorks.Interop.sldworks Namespace](#)
[ITextFormat Interface](#)

SOLIDWORKS API Help

[Send comments on this topic.](#)

ISketchText Interface Members

[See Also](#) [Properties](#) [Methods](#)



[SolidWorks.Interop.sldworks Namespace](#) : ISketchText Interface

The following tables list the members exposed by [ISketchText](#).

Public Properties

Name	Description
 Text	Gets or sets the text that makes up this sketch text.

[Top](#)

Public Methods

Name	Description
 EnumEdges	Gets the edges in this sketch text.
 GetCoordinates	Gets the position of this sketch text.
 GetEdges	Obsolete. Superseded by ISketchText.GetEdges2
 GetEdges2	Gets the edges for this sketch text.
 GetTextFormat	Gets the text format for this sketch text.
 GetUseDocTextFormat	Gets whether default model text format is in use in this sketch text.
 IGetCoordinates	Gets the position of this sketch text.
 IGetTextFormat	Gets the text format for this sketch text.
 ISetTextFormat	Sets the text format for this sketch text.
 SetCoordinates	Sets the position of this sketch text.
 SetTextFormat	Sets the text format for this sketch text.

[Top](#)

See Also

[ISketchText Interface](#)
[SolidWorks.Interop.sldworks Namespace](#)
[ITextFormat Interface](#)

SOLIDWORKS API Help

[Send comments on this topic.](#)

ISketchText Interface Properties

[See Also](#)

	SolidWorks.Interop.sldworks Namespace : ISketchText Interface
---	---

For a list of all members of this type, see [ISketchText members](#).

Public Properties

Name	Description
 Text	Gets or sets the text that makes up this sketch text.

[Top](#)

See Also

[ISketchText Interface](#)
[SolidWorks.Interop.sldworks Namespace](#)
[ITextFormat Interface](#)

EnumEdges Method (ISketchText)

[See Also](#)

	
SolidWorks.Interop.sldworks Namespace > ISketchText Interface : EnumEdges Method (ISketchText)	

Gets the edges in this sketch text.

.NET Syntax

Visual Basic (Declaration)

```
Function EnumEdges() As EnumEdges
```

Visual Basic (Usage)



```
Dim instance As ISketchText  
Dim value As EnumEdges  
  
value = instance.EnumEdges()
```

C#

```
EnumEdges EnumEdges()
```

C++/CLI

```
EnumEdges^ EnumEdges();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Return Value

[Edges enumeration](#)

Visual Basic for Applications (VBA) Syntax

See [SketchText::EnumEdges](#).

Remarks

The edges returned by this method are transient and should be regarded as read only. They can be used to obtain the underlying [ICurve](#) objects but should not be used for manipulation or to obtain any other objects through them. These pointers should not be saved; if they are needed again, they should be obtained at that time.

See Also

[ISketchText Interface](#)
[ISketchText Members](#)
[ISketchText::GetEdges Method](#)

Availability

SOLIDWORKS 2000 FCS, Revision Number 8.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

GetCoordinates Method (ISketchText)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISketchText Interface](#) : GetCoordinates Method (ISketchText)

Gets the position of this sketch text.

.NET Syntax

Visual Basic (Declaration)

```
Function GetCoordinates() As System.Object
```

Visual Basic (Usage)



```
Dim instance As ISketchText  
Dim value As System.Object  
  
value = instance.GetCoordinates()
```

C#

```
System.Object GetCoordinates()
```

C++/CLI

```
System.Object^ GetCoordinates();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Return Value

Array of 3 double values, the x,y,z coordinate of the sketch text

Visual Basic for Applications (VBA) Syntax

See [SketchText::GetCoordinates](#).

Example

See the [ISketchText](#) examples.

Remarks

To set the position of this sketch text, use [ISketchText::SetCoordinates](#).

See Also

[ISketchText Interface](#)
[ISketchText Members](#)
[ISketchText::IGetCoordinates Method](#)

Availability

SOLIDWORKS 2001Plus FCS, Revision Number 10.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

GetEdges Method (ISketchText)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISketchText Interface](#) : GetEdges Method (ISketchText)

Obsolete. Superseded by [ISketchText::GetEdges2](#).

.NET Syntax

Visual Basic (Declaration)

```
Function GetEdges() As System.Object
```

Visual Basic (Usage)



```
Dim instance As ISketchText  
Dim value As System.Object  
  
value = instance.GetEdges()
```

C#

```
System.Object GetEdges()
```

C++/CLI

```
System.Object^ GetEdges();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Return Value

Array of [edges](#)

Visual Basic for Applications (VBA) Syntax

See [SketchText::GetEdges](#).

Remarks

The edges returned by this method are transient and should be regarded as read only. They can be used to obtain the underlying [ICurve](#) objects but should not be used for manipulation or to obtain any other objects through them. These pointers should not be saved; if they are needed again, they should be obtained at that time.

See Also

[ISketchText Interface](#)
[ISketchText Members](#)
[ISketchText::EnumEdges Method](#)

Availability

SOLIDWORKS 2000 FCS, Revision Number 8.0

SOLIDWORKS API Help

[Send comments](#) on this topic.

GetEdges2 Method (ISketchText)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISketchText Interface](#) : GetEdges2 Method (ISketchText)

Gets the edges for this sketch text.

.NET Syntax

Visual Basic (Declaration)

```
Function GetEdges2() As System.Object
```

Visual Basic (Usage)



```
Dim instance As ISketchText  
Dim value As System.Object  
  
value = instance.GetEdges2()
```

C#

```
System.Object GetEdges2()
```

C++/CLI

```
System.Object^ GetEdges2();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Return Value

Array of [edges](#)

Visual Basic for Applications (VBA) Syntax

See [SketchText::GetEdges2](#).

Remarks

The difference between this method and the now obsolete ISketchText::GetEdges is this method also gets the edges of sketch text rendered with "stick" or single line fonts such as OLF SimpleSansOC.

The edges returned by this method are transient and should be regarded as read only. They can be used to obtain the underlying [ICurve](#) objects but should not be used for manipulation or to obtain any other objects. These pointers should not be saved; if they are needed again, they should be obtained at that time.

See Also

[ISketchText Interface](#)
[ISketchText Members](#)
[ISketchText::EnumEdges Method \(\)](#)

Availability

SOLIDWORKS 2019 FCS, Revision Number 27.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

GetTextFormat Method (ISketchText)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISketchText Interface](#) : GetTextFormat Method (ISketchText)

Gets the text format for this sketch text.

.NET Syntax

Visual Basic (Declaration)

```
Function GetTextFormat() As System.Object
```

Visual Basic (Usage)



```
Dim instance As ISketchText  
Dim value As System.Object  
  
value = instance.GetTextFormat()
```

C#

```
System.Object GetTextFormat()
```

C++/CLI

```
System.Object^ GetTextFormat();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Return Value

[Text format](#)

Visual Basic for Applications (VBA) Syntax

See [SketchText::GetTextFormat](#).

Example

[Get All Elements \(VBA\)](#)

Remarks

To change the text format of an existing sketch text, get the [ITextFormat](#) object using this method, next use its APIs to set the text format properties to what you want the sketch text to look like. Then use [ISketchText::SetTextFormat](#) or [ISketchText::ISetTextFormat](#) to change how the sketch text looks. To make the sketch text use the default model text format, use [ISketchText::SetTextFormat](#) and [ISketchText::ISetTextFormat](#) with the UseDoc argument set to True.

See Also

[ISketchText Interface](#)
[ISketchText Members](#)
[ISketchText::GetUseDocTextFormat Method](#)
[ISketchText::ISetTextFormat Method](#)
[ISketchText::Text Property](#)

Availability

SOLIDWORKS 2001Plus FCS, Revision Number 10.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

GetUseDocTextFormat Method (ISketchText)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISketchText Interface](#) : GetUseDocTextFormat Method (ISketchText)

Gets whether default model text format is in use in this sketch text.

.NET Syntax

Visual Basic (Declaration)

```
Function GetUseDocTextFormat() As System.Boolean
```

Visual Basic (Usage)



```
Dim instance As ISketchText  
Dim value As System.Boolean  
  
value = instance.GetUseDocTextFormat()
```

C#

```
System.bool GetUseDocTextFormat()
```

C++/CLI

```
System.bool GetUseDocTextFormat();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Return Value

True if the default model text format is used, false if not

Visual Basic for Applications (VBA) Syntax

See [SketchText::GetUseDocTextFormat](#).

Example

Remarks

To change the text format of an existing sketch text, get the [ITextFormat](#) object using [ISketchText::GetTextFormat](#) or [ISketchText::IGetTextFormat](#), next use the ITextFormat APIs to set the text format properties to what you want the sketch text to look like. Then, use [ISketchText::SetTextFormat](#) or [ISketchText::!SetTextFormat](#) to change how the sketch text looks. To make the sketch text use the default model text format, use [ISketchText::SetTextFormat](#) and [ISketchText::!SetTextFormat](#) with the UseDoc argument set to True.

See Also

[ISketchText Interface](#)
[ISketchText Members](#)
[ISketchText::Text Property](#)

Availability

SOLIDWORKS 2001Plus FCS, Revision Number 10.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

IGetCoordinates Method (ISketchText)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISketchText Interface](#) : IGetCoordinates Method (ISketchText)

Gets the position of this sketch text.

.NET Syntax

Visual Basic (Declaration)

```
Function IGetCoordinates() As System.Double
```

Visual Basic (Usage)



```
Dim instance As ISketchText  
Dim value As System.Double
```

```
value = instance.IGetCoordinates()
```

C#

```
System.double IGetCoordinates()
```

C++/CLI

```
System.double IGetCoordinates();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Return Value

- in-process, unmanaged C++: Pointer to an array of 3 double values, the x,y,z coordinate of the sketch text
 - VBA, VB.NET, C#, and C++/CLI: Not supported
- See [In-process Methods](#) for details about this type of method.

Remarks

To set the position of this sketch text, use [ISketchText::SetCoordinates](#).

See Also

[ISketchText Interface](#)
[ISketchText Members](#)
[ISketchText::GetCoordinates Method](#)

Availability

SOLIDWORKS 2001Plus FCS, Revision Number 10.0

IGetTextFormat Method (ISketchText)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISketchText Interface](#) : IGetTextFormat Method (ISketchText)

Gets the text format for this sketch text.

.NET Syntax

Visual Basic (Declaration)

```
Function IGetTextFormat() As TextFormat
```

Visual Basic (Usage)



```
Dim instance As ISketchText  
Dim value As TextFormat  
  
value = instance.IGetTextFormat()
```

C#

```
TextFormat IGetTextFormat()
```

C++/CLI

```
TextFormat^ IGetTextFormat();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Return Value

[Text format](#)

Visual Basic for Applications (VBA) Syntax

See [SketchText::IGetTextFormat](#).

Remarks

To change the text format of an existing sketch text, get the [ITextFormat](#) object using this method, next use its APIs to set the text format properties to what you want the sketch text to look like. Then use [ISketchText::SetTextFormat](#) or [ISketchText::ISetTextFormat](#) to change how the sketch text looks. To make the sketch text use the default model text format, use [ISketchText::SetTextFormat](#) and [ISketchText::ISetTextFormat](#) with the UseDoc argument set to True.

See Also

[ISketchText Interface](#)
[ISketchText Members](#)
[ISketchText::GetTextFormat Method](#)
[ISketchText::GetUseDocTextFormat Method](#)
[ISketchText::Text Property](#)

Availability

SOLIDWORKS 2001Plus FCS, Revision Number 10.0

ISetTextFormat Method (ISketchText)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISketchText Interface](#) : ISetTextFormat Method (ISketchText)

Sets the text format for this sketch text.

.NET Syntax

Visual Basic (Declaration)

```
Function ISetTextFormat(  
    ByVal UseDoc As System.Boolean, _
```

```
ByVal TextFormat As TextFormat _  
) As System.Boolean
```

Visual Basic (Usage)



```
Dim instance As ISketchText  
Dim UseDoc As System.Boolean  
Dim TextFormat As TextFormat  
Dim value As System.Boolean  
  
value = instance.ISetTextFormat(UseDoc, TextFormat)
```

C#

```
System.bool ISetTextFormat(  
    System.bool UseDoc,  
    TextFormat TextFormat  
)
```

C++/CLI

```
System.bool ISetTextFormat(  
& System.bool UseDoc,  
& TextFormat^ TextFormat  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

UseDoc

True to use the default model text format, false to use a local text format

TextFormat

Local [text format](#) to use if UseDoc is false

Return Value

True if the text format was successfully set, false if not

Visual Basic for Applications (VBA) Syntax

See [SketchText::ISetTextFormat](#).

Remarks

To set the text format, you must be editing the sketch. See [IModelDoc2::EditSketch](#) or [ISketchManager::InsertSketch](#).

To change the text format of an existing sketch text, get the [ITextFormat](#) object using [ISketchText::GetTextFormat](#) or [ISketchText::IGetTextFormat](#), next use the various ITextFormat APIs to set the text format properties to what you want the sketch text to look like. Then use this method to change how the sketch text looks. To make the sketch text use the default model text format, use this method with the useDoc argument set to True.

To determine if this sketch text is using the default model text format or not, use [ISketchText::GetUseDocTextFormat](#).

See Also

[ISketchText Interface](#)
[ISketchText Members](#)
[ISketchText::SetTextFormat Method](#)
[ISketchText::Text Property](#)

Availability

SOLIDWORKS 2001Plus FCS, Revision Number 10.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

SetCoordinates Method (ISketchText)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISketchText Interface](#) : SetCoordinates Method (ISketchText)

Sets the position of this sketch text.

.NET Syntax

Visual Basic (Declaration)

```
Function SetCoordinates( _  
    ByVal X As System.Double, _  
    ByVal Y As System.Double, _  
    ByVal Z As System.Double _  
) As System.Boolean
```

Visual Basic (Usage)



```
Dim instance As ISketchText  
Dim X As System.Double  
Dim Y As System.Double  
Dim Z As System.Double  
Dim value As System.Boolean  
  
value = instance.SetCoordinates(X, Y, Z)
```

C#

```
System.bool SetCoordinates(  
    System.double X,  
    System.double Y,  
    System.double Z  
)
```

C++/CLI

```
System.bool SetCoordinates(  
& System.double X,  
& System.double Y,  
& System.double Z  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

[X](#)
X coordinate of the sketch text position

[Y](#)
Y coordinate of the sketch text position

[Z](#)
Z coordinate of the sketch text position

Return Value

True if the sketch text position is successfully set, false if not

Visual Basic for Applications (VBA) Syntax

See [SketchText::SetCoordinates](#).

Remarks

To set the sketch text position, you must be editing the sketch. See [IModelDoc2::EditSketch](#) or [ISketchManager::InsertSketch](#).
To get the position of this sketch text, use [ISketchText::GetCoordinates](#) and [ISketchText::IGetCoordinates](#).

See Also

[ISketchText Interface](#)
[ISketchText Members](#)

Availability

SetTextFormat Method (ISketchText)

[See Also](#)[SolidWorks.Interop.sldworks Namespace](#) > [ISketchText Interface](#) : SetTextFormat Method (ISketchText)

Sets the text format for this sketch text.

.NET Syntax

Visual Basic (Declaration)

```
Function SetTextFormat( _
    ByVal UseDoc As System.Boolean, _
    ByVal TextFormat As System.Object _
) As System.Boolean
```

Visual Basic (Usage)



```
Dim instance As ISketchText
Dim UseDoc As System.Boolean
Dim TextFormat As System.Object
Dim value As System.Boolean

value = instance.SetTextFormat(UseDoc, TextFormat)
```

C#

```
System.bool SetTextFormat(
    System.bool UseDoc,
    System.object TextFormat
)
```

C++/CLI

```
System.bool SetTextFormat(
    & System.bool UseDoc,
    & System.Object^ TextFormat
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

UseDoc

True to use the default model text format, false to use a local text format

*TextFormat*Local [text format](#) to use if UseDoc is false

Return Value

True if the text format was successfully set, false if not

Visual Basic for Applications (VBA) Syntax

See [SketchText::SetTextFormat](#).

Remarks

To set the text format, you must be editing the sketch. See [IModelDoc2::EditSketch](#) or [ISketchManager::InsertSketch](#).To change the text format of an existing sketch text, get the [ITextFormat](#) object using [ISketchText::GetTextFormat](#) or [ISketchText::IGetTextFormat](#), next use the various ITextFormat APIs to set the text format properties to what you want the sketch text to look like. Then use this method to change how the sketch text looks. To make the sketch text use the default model text format, use this method with the useDoc argument set to True.To determine if this sketch text is using the default model text format or not, use [ISketchText::GetUseDocTextFormat](#).

See Also

[ISketchText Interface](#)
[ISketchText Members](#)
[ISketchText::ISetTextFormat Method](#)
[ISketchText::Text Property](#)

Availability

SOLIDWORKS 2001Plus FCS, Revision Number 10.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

Text Property (ISketchText)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISketchText Interface](#) : Text Property (ISketchText)

Gets or sets the text that makes up this sketch text.

.NET Syntax

Visual Basic (Declaration)

Property Text As System.String

Visual Basic (Usage)



```
Dim instance As ISketchText  
Dim value As System.String
```

```
instance.Text = value
```

```
value = instance.Text
```

C#

```
System.string Text {get; set;}
```

C++/CLI

```
property System.String^ Text {  
    System.String^ get();  
    void set ( & System.String^ value);  
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

Text that makes up this sketch text

Visual Basic for Applications (VBA) Syntax

See [SketchText::Text](#).

Example

[Get All Elements of Sketch \(VBA\)](#)
[Get Sketch Entities \(VBA\)](#)
[Replace Sketch Text \(VBA\)](#)

Remarks

To set the text format, you must be editing the sketch. See [IModelDoc2::EditSketch](#) or [ISketchManager::InsertSketch](#). You can only change text in visible documents.

See Also

[ISketchText Interface](#)
[ISketchText Members](#)
[ISketchText::GetTextFormat Method](#)
[ISketchText::GetUseDocTextFormat Method](#)
[ISketchText::IGetTextFormat Method](#)
[ISketchText::ISetTextFormat Method](#)
[ISketchText::SetTextFormat Method](#)

