

SOLIDWORKS API (.NET VBA C#) — Reference

(316/337) | TitleBlockTableFeature-
TriadManipulator

SOLIDWORKS API Documentation (converted from CHM)

ITitleBlockTableFeature (Type)

ITitleBlockTableFeature Interface

[See Also](#) [Members](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) : ITitleBlockTableFeature Interface

Provides access to title block table features.
NOTE: Click the **Members** link, located near the top of the topic, to see this interface's methods and properties.

.NET Syntax

Visual Basic (Declaration)

```
Public Interface ITitleBlockTableFeature
```

Visual Basic (Usage)

```
Dim instance As ITitleBlockTableFeature
```

C#

```
public interface ITitleBlockTableFeature
```

C++/CLI

```
public interface class ITitleBlockTableFeature
```

Visual Basic for Applications (VBA) Syntax

See [TitleBlockTableFeature](#).

Example

[Get Title Block Tables \(VBA\)](#)
[Get Title Block Tables \(VB.NET\)](#)
[Get Title Block Tables \(C#\)](#)

Accessors

[ITitleBlockTableAnnotation::TitleBlockTableFeature](#)

Access Diagram

[TitleBlockTableFeature](#)

See Also

[ITitleBlockTableFeature Members](#)
[SolidWorks.Interop.sldworks Namespace](#)

ITitleBlockTableFeature Interface Members

[See Also](#) [Methods](#)



[SolidWorks.Interop.sldworks Namespace](#) : ITitleBlockTableFeature Interface

The following tables list the members exposed by [ITitleBlockTableFeature](#).

Public Methods

Name	Description
 GetFeature	Provides access to the feature associated with this title block table.
 GetTableAnnotationCount	Gets the number of title block table annotations in this title block table feature.

 GetTableAnnotations	Gets all of the title block table annotations in this title block table feature.
 IGetTableAnnotations	Gets all of the title block table annotations in this title block table feature.

[Top](#)

 See Also

[ITitleBlockTableFeature Interface](#)
[SolidWorks.Interop.sldworks Namespace](#)

SOLIDWORKS API Help

[Send comments on this topic.](#)

ITitleBlockTableFeature Interface Methods

[See Also](#)


SolidWorks.Interop.sldworks Namespace : ITitleBlockTableFeature Interface

For a list of all members of this type, see [ITitleBlockTableFeature members](#).

 Public Methods

Name	Description
 GetFeature	Provides access to the feature associated with this title block table.
 GetTableAnnotationCount	Gets the number of title block table annotations in this title block table feature.
 GetTableAnnotations	Gets all of the title block table annotations in this title block table feature.
 IGetTableAnnotations	Gets all of the title block table annotations in this title block table feature.

[Top](#)

 See Also

[ITitleBlockTableFeature Interface](#)
[SolidWorks.Interop.sldworks Namespace](#)

SOLIDWORKS API Help

[Send comments on this topic.](#)

GetFeature Method (ITitleBlockTableFeature)

[See Also](#) [Example](#)

 
SolidWorks.Interop.sldworks Namespace > ITitleBlockTableFeature Interface : GetFeature Method (ITitleBlockTableFeature)

Provides access to the feature associated with this title block table.

 .NET Syntax

Visual Basic (Declaration)

Function GetFeature() As Feature

Visual Basic (Usage)



```
Dim instance As ITitleBlockTableFeature  
Dim value As Feature  
  
value = instance.GetFeature()
```

C#

Feature GetFeature()

C++/CLI

Feature^ GetFeature();

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Return Value

[Feature](#)

Visual Basic for Applications (VBA) Syntax

See [TitleBlockTableFeature::GetFeature](#).

Example

[Get Title Block Tables \(VBA\)](#)
[Get Title Block Tables \(VB.NET\)](#)
[Get Title Block Tables \(C#\)](#)

See Also

[ITitleBlockTableFeature Interface](#)
[ITitleBlockTableFeature Members](#)

Availability

SOLIDWORKS 2010 FCS, Revision Number 18.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

GetTableAnnotationCount Method (ITitleBlockTableFeature)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ITitleBlockTableFeature Interface](#) : GetTableAnnotationCount Method (ITitleBlockTableFeature)

Gets the number of title block table annotations in this title block table feature.

.NET Syntax

Visual Basic (Declaration)

```
Function GetTableAnnotationCount() As System.Integer
```

Visual Basic (Usage)



```
Dim instance As ITitleBlockTableFeature  
Dim value As System.Integer  
  
value = instance.GetTableAnnotationCount()
```

C#

```
System.int GetTableAnnotationCount()
```

C++/CLI

```
System.int GetTableAnnotationCount();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Return Value

Number of title block table annotations in this title block feature

Visual Basic for Applications (VBA) Syntax

See [TitleBlockTableFeature::GetTableAnnotationCount](#).

Example

[Get Title Block Tables \(VBA\)](#)
[Get Title Block Tables \(VB.NET\)](#)
[Get Title Block Tables \(C#\)](#)

See Also

[ITitleBlockTableFeature Interface](#)
[ITitleBlockTableFeature Members](#)

Availability

SOLIDWORKS 2010 FCS, Revision Number 18.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

GetTableAnnotations Method (ITitleBlockTableFeature)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ITitleBlockTableFeature Interface](#) : GetTableAnnotations Method (ITitleBlockTableFeature)

Gets all of the title block table annotations in this title block table feature.

.NET Syntax

Visual Basic (Declaration)

```
Function GetTableAnnotations() As System.Object
```

Visual Basic (Usage)



```
Dim instance As ITitleBlockTableFeature
Dim value As System.Object

value = instance.GetTableAnnotations()
```

C#

```
System.Object GetTableAnnotations()
```

C++/CLI

```
System.Object^ GetTableAnnotations();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Return Value

Array of [table annotations](#) in this title block table feature

Visual Basic for Applications (VBA) Syntax

See [TitleBlockTableFeature::GetTableAnnotations](#).

Example

[Get Title Block Tables \(VBA\)](#)
[Get Title Block Tables \(VB.NET\)](#)
[Get Title Block Tables \(C#\)](#)

See Also

[ITitleBlockTableFeature Interface](#)
[ITitleBlockTableFeature Members](#)

Availability

SOLIDWORKS 2010 FCS, Revision Number 18.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

IGetTableAnnotations Method (ITitleBlockTableFeature)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ITitleBlockTableFeature Interface](#) : IGetTableAnnotations Method (ITitleBlockTableFeature)

Gets all of the title block table annotations in this title block table feature.

.NET Syntax

Visual Basic (Declaration)

```
Function IGetTableAnnotations( _  
    ByVal Count As System.Integer _  
    ) As TitleBlockTableAnnotation
```

Visual Basic (Usage)



```
Dim instance As ITitleBlockTableFeature  
Dim Count As System.Integer  
Dim value As TitleBlockTableAnnotation  
  
value = instance.IGetTableAnnotations(Count)
```

C#

```
TitleBlockTableAnnotation IGetTableAnnotations(  
    System.int Count  
)
```

C++/CLI

```
TitleBlockTableAnnotation^ IGetTableAnnotations(  
& System.int Count  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Count

Number of annotations in this title block feature

Return Value

- in-process, unmanaged C++: Pointer to an array of [title block table annotations](#)
- VBA, VB.NET, C#, and C++/CLI: Not supported

See [In-process Methods](#) for details about this type of method.

Remarks

Before calling this method, call [ITitleBlockTableFeature::GetTableAnnotationCount](#) to get the value for Count.

See Also

[ITitleBlockTableFeature Interface](#)
[ITitleBlockTableFeature Members](#)

Availability

SOLIDWORKS 2010 FCS, Revision Number 18.0

IToolingSplitFeatureData (Type)

IToolingSplitFeatureData Interface

[See Also](#) [Members](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) : IToolingSplitFeatureData Interface

Allows access to a tooling-split feature.

NOTE: Click the **Members** link, located near the top of the topic, to see this interface's methods and properties.

.NET Syntax

Visual Basic (Declaration)

```
Public Interface IToolingSplitFeatureData
```

Visual Basic (Usage)



```
Dim instance As IToolingSplitFeatureData
```

C#

```
public interface IToolingSplitFeatureData
```

C++/CLI

```
public interface class IToolingSplitFeatureData
```

Visual Basic for Applications (VBA) Syntax

See [ToolingSplitFeatureData](#).

Example

[Get Tooling Split Feature Data \(VBA\)](#)
[Get Tooling Split Feature Data \(VB.NET\)](#)
[Get Tooling Split Feature Data \(C#\)](#)

Accessors

[IFeature::GetDefinition](#) and [IFeature::!GetDefinition](#)

Access Diagram

[ToolingSplitFeatureData](#)

See Also

[IToolingSplitFeatureData Members](#)
[SolidWorks.Interop.sldworks Namespace](#)

IToolingSplitFeatureData Interface Members

[See Also](#) [Properties](#) [Methods](#)



[SolidWorks.Interop.sldworks Namespace](#) : IToolingSplitFeatureData Interface

The following tables list the members exposed by [IToolingSplitFeatureData](#).

Public Properties

Name	Description
 Angle	Gets or sets the draft angle for this tooling split feature if an interlock surface exists.
 CavitySurfaces	Gets or sets the cavity surface bodies for this tooling split feature.

 CoreSurfaces	Gets or sets the core surface bodies for this tooling split feature.
 Depth	Gets or sets the depth of the block in the specified direction for this tooling split feature.
 InterlockSurface	Gets or sets whether to create an interlock surface for this tooling split feature.
 PartingSurfaces	Gets or sets the parting surface bodies for this tooling split feature.

[Top](#)

Public Methods

Name	Description
 AccessSelections	Gains access to the selections that define this tooling split feature.
 GetCavitySurfacesCount	Gets the number of cavity surface bodies in this tooling split feature.
 GetCoreSurfacesCount	Gets the number of core surface bodies in this tooling split feature.
 GetPartingSurfacesCount	Gets the number of parting surface bodies in this tooling split feature.
 IGetCavitySurfaces	Gets the cavity surface bodies in this tooling split feature.
 IGetCoreSurfaces	Gets the core surface bodies in this tooling split feature.
 IGetPartingSurfaces	Gets the parting surface bodies in this tooling split feature.
 ISetCavitySurfaces	Sets the cavity surface bodies for this tooling split feature.
 ISetCoreSurfaces	Sets the core surface bodies for this tooling split feature.
 ISetPartingSurfaces	Sets the parting surface bodies for this tooling split feature.
 ReleaseSelectionAccess	Releases access to the selections that define this tooling split feature.

[Top](#)

See Also

[IToolingSplitFeatureData Interface](#)
[SolidWorks.Interop.sldworks Namespace](#)

SOLIDWORKS API Help

[Send comments on this topic.](#)

IToolingSplitFeatureData Interface Methods

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) : IToolingSplitFeatureData Interface

For a list of all members of this type, see [IToolingSplitFeatureData members](#).

Public Methods

Name	Description
 AccessSelections	Gains access to the selections that define this tooling split feature.
 GetCavitySurfacesCount	Gets the number of cavity surface bodies in this tooling split feature.
 GetCoreSurfacesCount	Gets the number of core surface bodies in this tooling split feature.
 GetPartingSurfacesCount	Gets the number of parting surface bodies in this tooling split feature.
 IGetCavitySurfaces	Gets the cavity surface bodies in this tooling split feature.
 IGetCoreSurfaces	Gets the core surface bodies in this tooling split feature.
 IGetPartingSurfaces	Gets the parting surface bodies in this tooling split feature.
 ISetCavitySurfaces	Sets the cavity surface bodies for this tooling split feature.
 ISetCoreSurfaces	Sets the core surface bodies for this tooling split feature.
 ISetPartingSurfaces	Sets the parting surface bodies for this tooling split feature.
 ReleaseSelectionAccess	Releases access to the selections that define this tooling split feature.

[Top](#)

See Also

[IToolingSplitFeatureData Interface](#)
[SolidWorks.Interop.sldworks Namespace](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

IToolingSplitFeatureData Interface Properties

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) : IToolingSplitFeatureData Interface

For a list of all members of this type, see [IToolingSplitFeatureData members](#).

Public Properties

Name	Description
 Angle	Gets or sets the draft angle for this tooling split feature if an interlock surface exists.
 CavitySurfaces	Gets or sets the cavity surface bodies for this tooling split feature.
 CoreSurfaces	Gets or sets the core surface bodies for this tooling split feature.
 Depth	Gets or sets the depth of the block in the specified direction for this tooling split feature.
 InterlockSurface	Gets or sets whether to create an interlock surface for this tooling split feature.
 PartingSurfaces	Gets or sets the parting surface bodies for this tooling split feature.

[Top](#)

See Also

[IToolingSplitFeatureData Interface](#)
[SolidWorks.Interop.sldworks Namespace](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

AccessSelections Method (IToolingSplitFeatureData)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IToolingSplitFeatureData Interface](#) : AccessSelections Method (IToolingSplitFeatureData)

Gains access to the selections that define this tooling split feature.

.NET Syntax

Visual Basic (Declaration)

```
Function AccessSelections(  
    ByVal TopDoc As ModelDoc2, _  
    ByVal Component As Component2 _  
) As System.Boolean
```

Visual Basic (Usage)



```
Dim instance As IToolingSplitFeatureData  
Dim TopDoc As ModelDoc2  
Dim Component As Component2  
Dim value As System.Boolean  
  
value = instance.AccessSelections(TopDoc, Component)
```

C#

```
System.bool AccessSelections(  
    ModelDoc2 TopDoc,  
    Component2 Component  
)
```

C++/CLI

```
System.bool AccessSelections(  
& ModelDoc2^ TopDoc,
```

& Component2^ [Component](#)
)

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

TopDoc

Top-level document

Component

Component to which this feature is to be applied

Return Value

True if access is successful, false if not

Visual Basic for Applications (VBA) Syntax

See [ToolingSplitFeatureData::AccessSelections](#).

Example

See the [IToolingSplitFeatureData](#) examples.

Remarks

To modify a feature in a...	Then...
Part	- TopDoc argument is the IModelDoc2 for the part - Component argument is NULL
Assembly	- TopDoc is the IModelDoc2 object for the assembly - Component argument is the IComponent2 object in which the feature is to be modified

This method puts the model into a rollback state to allow access to the selections that define this feature. You must use either of the following methods to restore the rollback state:

- [IFeature::ModifyDefinition](#) or [IFeature::IModifyDefinition2](#) if you modified the feature
- [IToolingSplitFeatureData::ReleaseSelectionAccess](#) if you did not

See Also

[IToolingSplitFeatureData Interface](#)

[IToolingSplitFeatureData Members](#)

Availability

SOLIDWORKS 2005 FCS, Revision Number 13.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

Angle Property (IToolingSplitFeatureData)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IToolingSplitFeatureData Interface](#) : Angle Property (IToolingSplitFeatureData)

Gets or sets the draft angle for this tooling split feature if an [interlock surface](#) exists.

.NET Syntax

Visual Basic (Declaration)

Property Angle As System.Double

Visual Basic (Usage)



```
Dim instance As IToolingSplitFeatureData  
Dim value As System.Double
```

```
instance.Angle = value
```

```
value = instance.Angle
```

C#

```
System.double Angle {get; set;}
```

C++/CLI

```
property System.double Angle {  
    System.double get();  
    void set ( & System.double value);  
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

Angle in radians

Visual Basic for Applications (VBA) Syntax

See [ToolingSplitFeatureData::Angle](#).

Example

See the [IToolingSplitFeatureData](#) examples.

Remarks

See [Accessing Selections that Define Features](#) for additional details.

See Also

[IToolingSplitFeatureData Interface](#)
[IToolingSplitFeatureData Members](#)

Availability

SOLIDWORKS 2005 FCS, Revision Number 13.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

CavitySurfaces Property (IToolingSplitFeatureData)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IToolingSplitFeatureData Interface](#) : CavitySurfaces Property (IToolingSplitFeatureData)

Gets or sets the cavity surface bodies for this tooling split feature.

.NET Syntax

Visual Basic (Declaration)

```
Property CavitySurfaces As System.Object
```

Visual Basic (Usage)



```
Dim instance As IToolingSplitFeatureData  
Dim value As System.Object
```

```
instance.CavitySurfaces = value
```

```
value = instance.CavitySurfaces
```

C#

```
System.object CavitySurfaces {get; set;}
```

C++/CLI

```
property System.Object^ CavitySurfaces {  
    System.Object^ get();  
    void set ( & System.Object^ value);  
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

Array of cavity surface [bodies](#)

Visual Basic for Applications (VBA) Syntax

See [ToolingSplitFeatureData::CavitySurfaces](#).

Example

See the [IToolingSplitFeatureData](#) examples.

Remarks

See [Accessing Selections that Define Features](#) for additional details.

See Also

[IToolingSplitFeatureData Interface](#)
[IToolingSplitFeatureData Members](#)
[IToolingSplitFeatureData::GetCavitySurfacesCount Method](#)
[IToolingSplitFeatureData::!GetCavitySurfaces Method](#)
[IToolingSplitFeatureData::!SetCavitySurfaces Method](#)

Availability

SOLIDWORKS 2005 FCS, Revision Number 13.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

CoreSurfaces Property (IToolingSplitFeatureData)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IToolingSplitFeatureData Interface](#) : CoreSurfaces Property (IToolingSplitFeatureData)

Gets or sets the core surface bodies for this tooling split feature.

.NET Syntax

Visual Basic (Declaration)

```
Property CoreSurfaces As System.Object
```

Visual Basic (Usage)



```
Dim instance As IToolingSplitFeatureData  
Dim value As System.Object
```

```
instance.CoreSurfaces = value
```

```
value = instance.CoreSurfaces
```

C#

```
System.Object CoreSurfaces {get; set;}
```

C++/CLI

```
property System.Object^ CoreSurfaces {  
    System.Object^ get();  
    void set ( & System.Object^ value);  
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

Array of core surface [bodies](#)

Visual Basic for Applications (VBA) Syntax

See [ToolingSplitFeatureData::CoreSurfaces](#).

Example

See the [IToolingSplitFeatureData](#) examples.

Remarks

See [Accessing Selections that Define Features](#) for additional details.

See Also

[IToolingSplitFeatureData Interface](#)
[IToolingSplitFeatureData Members](#)
[IToolingSplitFeatureData::GetCoreSurfacesCount Method](#)
[IToolingSplitFeatureData::!GetCoreSurfaces Method](#)
[IToolingSplitFeatureData::!SetCoreSurfaces Method](#)

Availability

SOLIDWORKS 2005 FCS, Revision Number 13.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

Depth Property (IToolingSplitFeatureData)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IToolingSplitFeatureData Interface](#) : Depth Property (IToolingSplitFeatureData)

Gets or sets the depth of the block in the specified direction for this tooling split feature.

.NET Syntax

Visual Basic (Declaration)

```
Property Depth( _  
    ByVal Dir As System.Integer _  
) As System.Double
```

Visual Basic (Usage)



```
Dim instance As IToolingSplitFeatureData  
Dim Dir As System.Integer  
Dim value As System.Double  
  
instance.Depth(Dir) = value  
  
value = instance.Depth(Dir)
```

C#

```
System.double Depth(  
    System.int Dir  
) {get; set;}
```

C++/CLI

```
property System.double Depth {  
    System.double get(System.int Dir);  
    void set (System.int Dir, System.double value);  
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Dir

- 0 = Depth in Direction 1
- 1 = Depth in Direction 2

Property Value

Depth

Visual Basic for Applications (VBA) Syntax

See [ToolingSplitFeatureData::Depth](#).

Example

See the [IToolingSplitFeatureData](#) examples.

Remarks

See [Accessing Selections that Define Features](#) for additional details.

See Also

[IToolingSplitFeatureData Interface](#)
[IToolingSplitFeatureData Members](#)

Availability

SOLIDWORKS 2005 FCS, Revision Number 13.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

GetCavitySurfacesCount Method (IToolingSplitFeatureData)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IToolingSplitFeatureData Interface](#) : GetCavitySurfacesCount Method (IToolingSplitFeatureData)

Gets the number of cavity surface bodies in this tooling split feature.

.NET Syntax

Visual Basic (Declaration)

```
Function GetCavitySurfacesCount() As System.Integer
```

Visual Basic (Usage)



```
Dim instance As IToolingSplitFeatureData  
Dim value As System.Integer  
  
value = instance.GetCavitySurfacesCount()
```

C#

```
System.int GetCavitySurfacesCount()
```

C++/CLI

```
System.int GetCavitySurfacesCount();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Return Value

Number of cavity surface bodies

Visual Basic for Applications (VBA) Syntax

See [ToolingSplitFeatureData::GetCavitySurfacesCount](#).

Example

See the [IToolingSplitFeatureData](#) examples.

Remarks

Call this method before calling [IToolingSplitFeatureData::!GetCavitySurfaces](#) to get the size of the array for that method.

See Also

[IToolingSplitFeatureData Interface](#)
[IToolingSplitFeatureData Members](#)
[IToolingSplitFeatureData::CavitySurfaces Property](#)
[IToolingSplitFeatureData::!SetCavitySurfaces Method](#)

Availability

SOLIDWORKS 2005 FCS, Revision Number 13.0

SOLIDWORKS API Help

[Send comments](#) on this topic.

GetCoreSurfacesCount Method (IToolingSplitFeatureData)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IToolingSplitFeatureData Interface](#) : GetCoreSurfacesCount Method (IToolingSplitFeatureData)

Gets the number of core surface bodies in this tooling split feature.

.NET Syntax

Visual Basic (Declaration)

```
Function GetCoreSurfacesCount() As System.Integer
```

Visual Basic (Usage)



```
Dim instance As IToolingSplitFeatureData  
Dim value As System.Integer
```

```
value = instance.GetCoreSurfacesCount()
```

C#

```
System.int GetCoreSurfacesCount()
```

C++/CLI

```
System.int GetCoreSurfacesCount();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Return Value

Number of core surface bodies

Visual Basic for Applications (VBA) Syntax

See [ToolingSplitFeatureData::GetCoreSurfacesCount](#).

Example

See the [IToolingSplitFeatureData](#) examples.

Remarks

Call this method before calling [IToolingSplitFeatureData::!GetCoreSurfaces](#) to get the size of the array for that method.

See Also

[IToolingSplitFeatureData Interface](#)
[IToolingSplitFeatureData Members](#)
[IToolingSplitFeatureData::!SetCoreSurfaces Method](#)
[IToolingSplitFeatureData::CoreSurfaces Property](#)

Availability

GetPartingSurfacesCount Method (IToolingSplitFeatureData)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IToolingSplitFeatureData Interface](#) : GetPartingSurfacesCount Method (IToolingSplitFeatureData)

Gets the number of parting surface bodies in this tooling split feature.

.NET Syntax

Visual Basic (Declaration)

```
Function GetPartingSurfacesCount() As System.Integer
```

Visual Basic (Usage)



```
Dim instance As IToolingSplitFeatureData  
Dim value As System.Integer  
  
value = instance.GetPartingSurfacesCount()
```

C#

```
System.int GetPartingSurfacesCount()
```

C++/CLI

```
System.int GetPartingSurfacesCount();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Return Value

Number of parting surface bodies

Visual Basic for Applications (VBA) Syntax

See [ToolingSplitFeatureData::GetPartingSurfacesCount](#).

Example

See the [IToolingSplitFeatureData](#) examples.

Remarks

Call this method before calling [IToolingSplitFeatureData::!GetPartingSurfaces](#) to get the size of the array for that method.

See Also

[IToolingSplitFeatureData Interface](#)
[IToolingSplitFeatureData Members](#)
[IToolingSplitFeatureData::!GetPartingSurfaces Method](#)
[IToolingSplitFeatureData::PartingSurfaces Property](#)

Availability

SOLIDWORKS 2005 FCS, Revision Number 13.0

IGetCavitySurfaces Method (IToolingSplitFeatureData)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IToolingSplitFeatureData Interface](#) : IGetCavitySurfaces Method (IToolingSplitFeatureData)

Gets the cavity surface bodies in this tooling split feature.

.NET Syntax

Visual Basic (Declaration)

```
Function IGetCavitySurfaces( _  
    ByVal Count As System.Integer _  
) As Body2
```

Visual Basic (Usage)



```
Dim instance As IToolingSplitFeatureData  
Dim Count As System.Integer  
Dim value As Body2  
  
value = instance.IGetCavitySurfaces(Count)
```

C#

```
Body2 IGetCavitySurfaces(  
    System.int Count  
)
```

C++/CLI

```
Body2^ IGetCavitySurfaces(  
& System.int Count  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Count
Number of cavity surface bodies

Return Value

- in-process, unmanaged C++: Pointer to an array of cavity surface [bodies](#)
 - VBA, VB.NET, C#, and C++/CLI: Not supported
- See [In-process Methods](#) for details about this type of method.

Remarks

Call [IToolingSplitFeatureData::GetCavitySurfacesCount](#) before calling this method to get Count.

See Also

[IToolingSplitFeatureData Interface](#)
[IToolingSplitFeatureData Members](#)
[IToolingSplitFeatureData::ISetCavitySurfaces Method](#)
[IToolingSplitFeatureData::CavitySurfaces Property](#)

Availability

SOLIDWORKS 2005 FCS, Revision Number 13.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

IGetCoreSurfaces Method (IToolingSplitFeatureData)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IToolingSplitFeatureData Interface](#) : IGetCoreSurfaces Method (IToolingSplitFeatureData)

Gets the core surface bodies in this tooling split feature.

.NET Syntax

Visual Basic (Declaration)

```
Function IGetCoreSurfaces( _  
    ByVal Count As System.Integer _  
) As Body2
```

Visual Basic (Usage)



```
Dim instance As IToolingSplitFeatureData
Dim Count As System.Integer
Dim value As Body2

value = instance.IGetCoreSurfaces(Count)
```

C#

```
Body2 IGetCoreSurfaces(
    System.int Count
)
```

C++/CLI

```
Body2^ IGetCoreSurfaces(
    & System.int Count
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Count
Number of core surface bodies

Return Value

- in-process, unmanaged C++: Pointer to an array of core surface [bodies](#)
 - VBA, VB.NET, C#, and C++/CLI: Not supported
- See [In-process Methods](#) for details about this type of method.

Remarks

Call [IToolingSplitFeatureData::GetCoreSurfacesCount](#) before calling this method to get Count.

See Also

[IToolingSplitFeatureData Interface](#)
[IToolingSplitFeatureData Members](#)
[IToolingSplitFeatureData::CoreSurfaces Property](#)
[IToolingSplitFeatureData::ISetCoreSurfaces Method](#)

Availability

SOLIDWORKS 2005 FCS, Revision Number 13.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

IGetPartingSurfaces Method (IToolingSplitFeatureData)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IToolingSplitFeatureData Interface](#) : IGetPartingSurfaces Method (IToolingSplitFeatureData)

Gets the parting surface bodies in this tooling split feature.

.NET Syntax

Visual Basic (Declaration)

```
Function IGetPartingSurfaces( _
    ByVal Count As System.Integer _
) As Body2
```

Visual Basic (Usage)



```
Dim instance As IToolingSplitFeatureData
Dim Count As System.Integer
Dim value As Body2

value = instance.IGetPartingSurfaces(Count)
```

C#

```
Body2 IGetPartingSurfaces(  
    System.int Count  
)
```

C++/CLI

```
Body2^ IGetPartingSurfaces(  
&    System.int Count  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Count
Number of parting surface bodies

Return Value

- in-process, unmanaged C++: Pointer to an array of parting surface [bodies](#)
- VBA, VB.NET, C#, and C++/CLI: Not supported

See [In-process Methods](#) for details about this type of method.

Remarks

Call [IToolingSplitFeatureData::GetPartingSurfacesCount](#) before calling this method to get Count.

See Also

[IToolingSplitFeatureData Interface](#)
[IToolingSplitFeatureData Members](#)
[IToolingSplitFeatureData::iSetPartingSurfaces Method](#)
[IToolingSplitFeatureData::PartingSurfaces Property](#)

Availability

SOLIDWORKS 2005 FCS, Revision Number 13.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

InterlockSurface Property (IToolingSplitFeatureData)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IToolingSplitFeatureData Interface](#) : InterlockSurface Property (IToolingSplitFeatureData)

Gets or sets whether to create an interlock surface for this tooling split feature.

.NET Syntax

Visual Basic (Declaration)

```
Property InterlockSurface As System.Boolean
```

Visual Basic (Usage)



```
Dim instance As IToolingSplitFeatureData  
Dim value As System.Boolean
```

```
instance.InterlockSurface = value
```

```
value = instance.InterlockSurface
```

C#

```
System.bool InterlockSurface {get; set;}
```

C++/CLI

```
property System.bool InterlockSurface {
    System.bool get();
    void set ( & System.bool value);
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

True to create an interlock surface, false to not

Visual Basic for Applications (VBA) Syntax

See [ToolingSplitFeatureData::InterlockSurface](#).

Example

See the [IToolingSplitFeatureData](#) examples.

Remarks

If this property is set to true, then you can specify a [draft angle](#) for the interlock surface.

See [Accessing Selections that Define Features](#) for additional details.

See Also

[IToolingSplitFeatureData Interface](#)
[IToolingSplitFeatureData Members](#)

Availability

SOLIDWORKS 2005 FCS, Revision Number 13.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

ISetCavitySurfaces Method (IToolingSplitFeatureData)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IToolingSplitFeatureData Interface](#) : ISetCavitySurfaces Method (IToolingSplitFeatureData)

Sets the cavity surface bodies for this tooling split feature.

.NET Syntax

Visual Basic (Declaration)

```
Sub ISetCavitySurfaces( _
    ByVal Count As System.Integer, _
    ByRef BodyArr As Body2 _
)
```

Visual Basic (Usage)

```
Dim instance As IToolingSplitFeatureData
Dim Count As System.Integer
Dim BodyArr As Body2

instance.ISetCavitySurfaces(Count, BodyArr)
```

C#

```
void ISetCavitySurfaces(
    System.int Count,
    ref Body2 BodyArr
)
```

C++/CLI



```
void ISetCavitySurfaces(  
& System.int Count,  
& Body2^% BodyArr  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Count

Number of cavity surface bodies

BodyArr

- in-process, unmanaged C++: Pointer to an array of cavity surface [bodies](#)
- VBA, VB.NET, C#, and C++/CLI: Not supported

See [In-process Methods](#) for details about this type of method.

Remarks

See [Accessing Selections that Define Features](#) for additional details.

See Also

[IToolingSplitFeatureData Interface](#)

[IToolingSplitFeatureData Members](#)

[IToolingSplitFeatureData::GetCavitySurfacesCount Method](#)

[IToolingSplitFeatureData::ISetCavitySurfaces Method](#)

[IToolingSplitFeatureData::CavitySurfaces Property](#)

Availability

SOLIDWORKS 2005 FCS, Revision Number 13.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

ISetCoreSurfaces Method (IToolingSplitFeatureData)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IToolingSplitFeatureData Interface](#) : ISetCoreSurfaces Method (IToolingSplitFeatureData)

Sets the core surface bodies for this tooling split feature.

.NET Syntax

Visual Basic (Declaration)

```
Sub ISetCoreSurfaces( _  
    ByVal Count As System.Integer, _  
    ByRef BodyArr As Body2 _  
)
```

Visual Basic (Usage)



```
Dim instance As IToolingSplitFeatureData  
Dim Count As System.Integer  
Dim BodyArr As Body2
```

```
instance.ISetCoreSurfaces(Count, BodyArr)
```

C#

```
void ISetCoreSurfaces(  
    System.int Count,  
    ref Body2 BodyArr  
)
```

C++/CLI

```
void ISetCoreSurfaces(  
& System.int Count,  
& Body2^% BodyArr  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Count

Number of core surface bodies

BodyArr

- in-process, unmanaged C++: Pointer to an array of core surface [bodies](#)

- VBA, VB.NET, C#, and C++/CLI: Not supported

See [In-process Methods](#) for details about this type of method.

Remarks

See [Accessing Selections that Define Features](#) for additional details.

See Also

[IToolingSplitFeatureData Interface](#)

[IToolingSplitFeatureData Members](#)

[IToolingSplitFeatureData::GetCoreSurfacesCount Method](#)

[IToolingSplitFeatureData::IGetCoreSurfaces Method](#)

[IToolingSplitFeatureData::CoreSurfaces Property](#)

Availability

SOLIDWORKS 2005 FCS, Revision Number 13.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

ISetPartingSurfaces Method (IToolingSplitFeatureData)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IToolingSplitFeatureData Interface](#) : ISetPartingSurfaces Method (IToolingSplitFeatureData)

Sets the parting surface bodies for this tooling split feature.

.NET Syntax

Visual Basic (Declaration)

```
Sub ISetPartingSurfaces( _  
    ByVal Count As System.Integer, _  
    ByRef BodyArr As Body2 _  
)
```

Visual Basic (Usage)



```
Dim instance As IToolingSplitFeatureData  
Dim Count As System.Integer  
Dim BodyArr As Body2  
  
instance.ISetPartingSurfaces(Count, BodyArr)
```

C#

```
void ISetPartingSurfaces(  
    System.int Count,  
    ref Body2 BodyArr  
)
```

C++/CLI

```
void ISetPartingSurfaces(  
& System.int Count,  
& Body2^% BodyArr  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Count

Number of parting surface bodies

BodyArr

- in-process, unmanaged C++: Pointer to an array of parting surface [bodies](#)

• VBA, VB.NET, C#, and C++/CLI: Not supported
See [In-process Methods](#) for details about this type of method.

Remarks

See [Accessing Selections that Define Features](#) for additional details.

See Also

[IToolingSplitFeatureData Interface](#)
[IToolingSplitFeatureData Members](#)
[IToolingSplitFeatureData::GetPartingSurfacesCount Method](#)
[IToolingSplitFeatureData::GetPartingSurfaces Method](#)
[IToolingSplitFeatureData::PartingSurfaces Property](#)

Availability

SOLIDWORKS 2005 FCS, Revision Number 13.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

PartingSurfaces Property (IToolingSplitFeatureData)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IToolingSplitFeatureData Interface](#) : PartingSurfaces Property (IToolingSplitFeatureData)

Gets or sets the parting surface bodies for this tooling split feature.

.NET Syntax

Visual Basic (Declaration)

Property PartingSurfaces As System.Object

Visual Basic (Usage)



```
Dim instance As IToolingSplitFeatureData  
Dim value As System.Object
```

```
instance.PartingSurfaces = value
```

```
value = instance.PartingSurfaces
```

C#

```
System.Object PartingSurfaces {get; set;}
```

C++/CLI

```
property System.Object^ PartingSurfaces {  
    System.Object^ get();  
    void set ( & System.Object^ value);  
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

Array of parting surface [bodies](#)

Visual Basic for Applications (VBA) Syntax

See [ToolingSplitFeatureData::PartingSurfaces](#).

Example

See the [IToolingSplitFeatureData](#) examples.

Remarks

See [Accessing Selections that Define Features](#) for additional details.

See Also

[IToolingSplitFeatureData Interface](#)
[IToolingSplitFeatureData Members](#)
[IToolingSplitFeatureData::GetPartingSurfacesCount Method](#)
[IToolingSplitFeatureData::IGetPartingSurfaces Method](#)
[IToolingSplitFeatureData::ISetPartingSurfaces Method](#)

Availability

SOLIDWORKS 2005 FCS, Revision Number 13.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

ReleaseSelectionAccess Method (IToolingSplitFeatureData)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IToolingSplitFeatureData Interface](#) : ReleaseSelectionAccess Method (IToolingSplitFeatureData)

Releases access to the selections that define this tooling split feature.

.NET Syntax

Visual Basic (Declaration)

```
Sub ReleaseSelectionAccess()
```

Visual Basic (Usage)



```
Dim instance As IToolingSplitFeatureData  
instance.ReleaseSelectionAccess()
```

C#

```
void ReleaseSelectionAccess()
```

C++/CLI

```
void ReleaseSelectionAccess();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Visual Basic for Applications (VBA) Syntax

See [ToolingSplitFeatureData::ReleaseSelectionAccess](#).

Example

See the [IToolingSplitFeatureData](#) examples.

Remarks

[IToolingSplitFeatureData::AccessSelections](#) puts the model in a rollback state to allow access to the selections that define the feature.

Use this method to restore the rollback state if you did not modify the feature, or use [IFeature::ModifyDefinition](#) or [IFeature::IModifyDefinition2](#) if you did modify the feature.

See Also

[IToolingSplitFeatureData Interface](#)
[IToolingSplitFeatureData Members](#)

Availability

SOLIDWORKS 2005 FCS, Revision Number 13.0

ITreeControlItem (Type)

ITreeControlItem Interface

[See Also](#) [Members](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) : ITreeControlItem Interface

Allows you to traverse items in the FeatureManager design tree exactly as they appear in the FeatureManager design tree.

NOTE: Click the **Members** link, located near the top of the topic, to see this interface's methods and properties.

.NET Syntax

Visual Basic (Declaration)

```
Public Interface ITreeControlItem
```

Visual Basic (Usage)

```
Dim instance As ITreeControlItem
```

C#

```
public interface ITreeControlItem
```

C++/CLI

```
public interface class ITreeControlItem
```

Visual Basic for Applications (VBA) Syntax

See [TreeControlItem](#).

Example

[Traverse FeatureManager Design Tree \(VBA\)](#)
[Expand or Collapse FeatureManager Design Tree Nodes \(VBA\)](#)
[Expand or Collapse FeatureManager Design Tree Nodes \(VB.NET\)](#)
[Expand or Collapse FeatureManager Design Tree Nodes \(C#\)](#)

Remarks

ITreeControlItem objects are released whenever the FeatureManager design tree is rebuilt (e.g., add or remove features, rebuild the model, etc.).

Accessors

[IFeatureManager::GetFeatureTreeRootItem](#)
[ITreeControlItem::GetFirstChild](#)
[ITreeControlItem::GetNext](#)
[ITreeControlItem::GetParent](#)
[ITreeControlItem::GetPrevious](#)
[ITreeControlItem::GetRoot](#)

Access Diagram

[TreeControlItem](#)

See Also

[ITreeControlItem Members](#)
[SolidWorks.Interop.sldworks Namespace](#)

[See Also](#) [Properties](#) [Methods](#)

[SolidWorks.Interop.sldworks Namespace](#) : ITreeControlItem Interface

The following tables list the members exposed by [ITreeControlItem](#).

 Public Properties

Name	Description
 Expanded	Gets or sets whether to expand this item in the FeatureManager design tree.
 IsRoot	Gets whether this item is the root item of the FeatureManager design tree.
 Object	Gets the SOLIDWORKS object associated with this item in the FeatureManager design tree.
 ObjectType	Gets the type of SOLIDWORKS object for this item in the FeatureManager design tree.
 Text	Gets the text for this item in the FeatureManager design tree.

[Top](#)

 Public Methods

Name	Description
 GetFirstChild	Gets the first child of this item in the FeatureManager design tree.
 GetNext	Gets the next sibling of this item in the FeatureManager design tree.
 GetParent	Gets the parent of this item in the FeatureManager design tree.
 GetPrevious	Gets the previous sibling of this item in the FeatureManager design tree.
 GetRoot	Gets the root item of the FeatureManager design tree.

[Top](#)

 See Also

[ITreeControlItem Interface](#)
[SolidWorks.Interop.sldworks Namespace](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

ITreeControlItem Interface Methods

[See Also](#)

[SolidWorks.Interop.sldworks Namespace](#) : ITreeControlItem Interface

For a list of all members of this type, see [ITreeControlItem members](#).

 Public Methods

Name	Description
 GetFirstChild	Gets the first child of this item in the FeatureManager design tree.
 GetNext	Gets the next sibling of this item in the FeatureManager design tree.
 GetParent	Gets the parent of this item in the FeatureManager design tree.
 GetPrevious	Gets the previous sibling of this item in the FeatureManager design tree.
 GetRoot	Gets the root item of the FeatureManager design tree.

[Top](#)

 See Also

[ITreeControlItem Interface](#)
[SolidWorks.Interop.sldworks Namespace](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

ITreeControlItem Interface Properties

[See Also](#)

[SolidWorks.Interop.sldworks Namespace](#) : ITreeControlItem Interface

For a list of all members of this type, see [ITreeControlItem members](#).

Public Properties

Name	Description
 Expanded	Gets or sets whether to expand this item in the FeatureManager design tree.
 IsRoot	Gets whether this item is the root item of the FeatureManager design tree.
 Object	Gets the SOLIDWORKS object associated with this item in the FeatureManager design tree.
 ObjectType	Gets the type of SOLIDWORKS object for this item in the FeatureManager design tree.
 Text	Gets the text for this item in the FeatureManager design tree.

[Top](#)

See Also

[ITreeControlItem Interface](#)
[SolidWorks.Interop.sldworks Namespace](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

Expanded Property (ITreeControlItem)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ITreeControlItem Interface](#) : Expanded Property (ITreeControlItem)

Gets or sets whether to expand this item in the FeatureManager design tree.

.NET Syntax

Visual Basic (Declaration)

Property Expanded As System.Boolean

Visual Basic (Usage)



```
Dim instance As ITreeControlItem
Dim value As System.Boolean
```

```
instance.Expanded = value
```

```
value = instance.Expanded
```

C#

```
System.bool Expanded {get; set;}
```

C++/CLI

```
property System.bool Expanded {
    System.bool get();
    void set ( & System.bool value);
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

True to expand, false to collapse

Visual Basic for Applications (VBA) Syntax

See [TreeControlItem::Expanded](#).

Example

[Expand or Collapse FeatureManager Design Tree Nodes \(VBA\)](#)
[Expand or Collapse FeatureManager Design Tree Nodes \(VB.NET\)](#)
[Expand or Collapse FeatureManager Design Tree Nodes \(C#\)](#)

See Also

[ITreeControlItem Interface](#)
[ITreeControlItem Members](#)
[IFeatureManager::ExpandFeature Method \(\)](#)

Availability

SOLIDWORKS 2012 SP04, Revision 20.4

SOLIDWORKS API Help

[Send comments on this topic.](#)

GetFirstChild Method (ITreeControlItem)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ITreeControlItem Interface](#) : GetFirstChild Method (ITreeControlItem)

Gets the first child of this item in the FeatureManager design tree.

.NET Syntax

Visual Basic (Declaration)

```
Function GetFirstChild() As TreeControlItem
```

Visual Basic (Usage)



```
Dim instance As ITreeControlItem  
Dim value As TreeControlItem
```

```
value = instance.GetFirstChild()
```

C#

```
TreeControlItem GetFirstChild()
```

C++/CLI

```
TreeControlItem^ GetFirstChild();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Return Value

[First child of this item in the FeatureManager design tree](#)

Visual Basic for Applications (VBA) Syntax

See [TreeControlItem::GetFirstChild](#).

Example

[Traverse FeatureManager Design Tree \(VBA\)](#)
[Expand or Collapse FeatureManager Design Tree Nodes \(VBA\)](#)
[Expand or Collapse FeatureManager Design Tree Nodes \(VB.NET\)](#)
[Expand or Collapse FeatureManager Design Tree Nodes \(C#\)](#)

See Also

[ITreeControlItem Interface](#)
[ITreeControlItem Members](#)

Availability

SOLIDWORKS 2008 SP2, Revision Number 16.2

SOLIDWORKS API Help

[Send comments on this topic.](#)

GetNext Method (ITreeControlItem)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ITreeControlItem Interface](#) : GetNext Method (ITreeControlItem)

Gets the next sibling of this item in the FeatureManager design tree.

.NET Syntax

Visual Basic (Declaration)

```
Function GetNext() As TreeControlItem
```

Visual Basic (Usage)



```
Dim instance As ITreeControlItem  
Dim value As TreeControlItem  
  
value = instance.GetNext()
```

C#

```
TreeControlItem GetNext()
```

C++/CLI

```
TreeControlItem^ GetNext();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Return Value

[Next sibling of this item in the FeatureManager design tree](#)

Visual Basic for Applications (VBA) Syntax

See [TreeControlItem::GetNext](#).

Example

[Traverse FeatureManager Design Tree \(VBA\)](#)
[Expand or Collapse FeatureManager Design Tree Nodes \(VBA\)](#)
[Expand or Collapse FeatureManager Design Tree Nodes \(VB.NET\)](#)
[Expand or Collapse FeatureManager Design Tree Nodes \(C#\)](#)

Remarks

Use [ITreeControlItem::GetPrevious](#) to get the previous sibling of this item in the FeatureManager design tree.

See Also

[ITreeControlItem Interface](#)
[ITreeControlItem Members](#)

Availability

SOLIDWORKS 2008 SP2, Revision Number 16.2

SOLIDWORKS API Help

[Send comments](#) on this topic.

GetParent Method (ITreeControlItem)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ITreeControlItem Interface](#) : GetParent Method (ITreeControlItem)

Gets the parent of this item in the FeatureManager design tree.

.NET Syntax

Visual Basic (Declaration)

```
Function GetParent() As TreeControlItem
```

Visual Basic (Usage)



```
Dim instance As ITreeControlItem
Dim value As TreeControlItem

value = instance.GetParent()
```

C#

```
TreeControlItem GetParent()
```

C++/CLI

```
TreeControlItem^ GetParent();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Return Value

[Parent of this item in the FeatureManager design tree](#)

Visual Basic for Applications (VBA) Syntax

See [TreeControlItem::GetParent](#).

See Also

[ITreeControlItem Interface](#)
[ITreeControlItem Members](#)

Availability

SOLIDWORKS 2008 SP2, Revision Number 16.2

SOLIDWORKS API Help

[Send comments on this topic.](#)

GetPrevious Method (ITreeControlItem)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ITreeControlItem Interface](#) : GetPrevious Method (ITreeControlItem)

Gets the previous sibling of this item in the FeatureManager design tree.

.NET Syntax

Visual Basic (Declaration)

```
Function GetPrevious() As TreeControlItem
```

Visual Basic (Usage)



```
Dim instance As ITreeControlItem
Dim value As TreeControlItem

value = instance.GetPrevious()
```

C#

```
TreeControlItem GetPrevious()
```

C++/CLI

```
TreeControlItem^ GetPrevious();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Return Value

[Previous sibling of this item in the FeatureManager design tree](#)

Visual Basic for Applications (VBA) Syntax

See [ITreeControlItem::GetPrevious](#).

Remarks

Use [ITreeControlItem::GetNext](#) to get the next sibling of this item in the FeatureManager design tree.

See Also

[ITreeControlItem Interface](#)
[ITreeControlItem Members](#)

Availability

SOLIDWORKS 2008 SP2, Revision Number 16.2

SOLIDWORKS API Help

[Send comments on this topic.](#)

GetRoot Method (ITreeControlItem)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ITreeControlItem Interface](#) : GetRoot Method (ITreeControlItem)

Gets the root item of the FeatureManager design tree.

.NET Syntax

Visual Basic (Declaration)

```
Function GetRoot() As TreeControlItem
```

Visual Basic (Usage)



```
Dim instance As ITreeControlItem  
Dim value As TreeControlItem  
  
value = instance.GetRoot()
```

C#

```
TreeControlItem GetRoot()
```

C++/CLI

```
TreeControlItem^ GetRoot();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Return Value

[Root item of the FeatureManager design tree](#)

Visual Basic for Applications (VBA) Syntax

See [TreeControlItem::GetRoot](#).

Remarks

Use [ITreeControlItem::IsRoot](#) to get whether an item is the root item of the FeatureManager design tree.

See Also

[ITreeControlItem Interface](#)
[ITreeControlItem Members](#)

Availability

SOLIDWORKS 2008 SP2, Revision Number 16.2

IsRoot Property (ITreeControlItem)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ITreeControlItem Interface](#) : IsRoot Property (ITreeControlItem)

Gets whether this item is the root item of the FeatureManager design tree.

.NET Syntax

Visual Basic (Declaration)

```
ReadOnly Property IsRoot As System.Boolean
```

Visual Basic (Usage)



```
Dim instance As ITreeControlItem  
Dim value As System.Boolean  
  
value = instance.IsRoot
```

C#

```
System.bool IsRoot {get;}
```

C++/CLI

```
property System.bool IsRoot {  
    System.bool get();  
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

True if this item is the root item of the FeatureManager design tree, false if not

Visual Basic for Applications (VBA) Syntax

See [TreeControlItem::IsRoot](#).

Remarks

Use [ITreeControlItem::GetRoot](#) to get the root item of the FeatureManager design tree.

See Also

[ITreeControlItem Interface](#)
[ITreeControlItem Members](#)

Availability

SOLIDWORKS 2008 SP2, Revision Number 16.2

Object Property (ITreeControlItem)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ITreeControlItem Interface](#) : Object Property (ITreeControlItem)

Gets the SOLIDWORKS object associated with this item in the FeatureManager design tree.

.NET Syntax

Visual Basic (Declaration)

```
ReadOnly Property Object As System.Object
```

Visual Basic (Usage)



```
Dim instance As ITreeControlItem
Dim value As System.Object

value = instance.Object
```

C#

```
System.Object Object {get;}
```

C++/CLI

```
property System.Object^ Object {
    System.Object^ get();
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

SOLIDWORKS object associated with this item in the FeatureManager design tree (see **Remarks**)

Visual Basic for Applications (VBA) Syntax

See [TreeControlItem::Object](#).

Example

[Traverse FeatureManager Design Tree \(VBA\)](#)
[Expand or Collapse FeatureManager Design Tree Nodes \(VBA\)](#)
[Expand or Collapse FeatureManager Design Tree Nodes \(VB.NET\)](#)
[Expand or Collapse FeatureManager Design Tree Nodes \(C#\)](#)

Remarks

Currently only [features](#) and [components](#) are supported. Null is returned for sub-components of an assembly loaded hidden with a selective oper

Use [ITreeControlItem::ObjectType](#) to determine the SOLIDWORKS object type.

See Also

[ITreeControlItem Interface](#)
[ITreeControlItem Members](#)

Availability

SOLIDWORKS 2008 SP2, Revision Number 16.2

SOLIDWORKS API Help

[Send comments on this topic.](#)

ObjectType Property (ITreeControlItem)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ITreeControlItem Interface](#) : ObjectType Property (ITreeControlItem)

Gets the type of SOLIDWORKS object for this item in the FeatureManager design tree.

.NET Syntax

Visual Basic (Declaration)

```
ReadOnly Property ObjectType As System.Integer
```

Visual Basic (Usage)



```
Dim instance As ITreeControlItem
Dim value As System.Integer

value = instance.ObjectType
```

C#

```
System.int ObjectType {get;}
```

C++/CLI

```
property System.int ObjectType {  
    System.int get();  
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

Type of SOLIDWORKS object for this item in the FeatureManager design tree as defined by [swTreeControlItemType_e](#)

Visual Basic for Applications (VBA) Syntax

See [TreeControlItem::ObjectType](#).

Example

[Traverse FeatureManager Design Tree \(VBA\)](#)
[Expand or Collapse FeatureManager Design Tree Nodes \(VBA\)](#)
[Expand or Collapse FeatureManager Design Tree Nodes \(VB.NET\)](#)
[Expand or Collapse FeatureManager Design Tree Nodes \(C#\)](#)

Remarks

Currently only [features](#) and [components](#) are supported. Null is returned for sub-components of an assembly loaded hidden with a selective oper
Use [ITreeControlItem::Object](#) to get the SOLIDWORKS object associated with this item.

See Also

[ITreeControlItem Interface](#)
[ITreeControlItem Members](#)

Availability

SOLIDWORKS 2008 SP2, Revision Number 16.2

SOLIDWORKS API Help

[Send comments](#) on this topic.

Text Property (ITreeControlItem)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ITreeControlItem Interface](#) : Text Property (ITreeControlItem)

Gets the text for this item in the FeatureManager design tree.

.NET Syntax

Visual Basic (Declaration)

```
ReadOnly Property Text As System.String
```

Visual Basic (Usage)



```
Dim instance As ITreeControlItem  
Dim value As System.String  
  
value = instance.Text
```

C#

```
System.string Text {get;}
```

C++/CLI

```
property System.String^ Text {  
    System.String^ get();  
}
```

}

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

Text for this item in the FeatureManager design tree

Visual Basic for Applications (VBA) Syntax

See [TreeControlItem::Text](#).

Example

[Traverse FeatureManager Design Tree \(VBA\)](#)
[Expand or Collapse FeatureManager Design Tree Nodes \(VBA\)](#)
[Expand or Collapse FeatureManager Design Tree Nodes \(VB.NET\)](#)
[Expand or Collapse FeatureManager Design Tree Nodes \(C#\)](#)

See Also

[ITreeControlItem Interface](#)
[ITreeControlItem Members](#)

Availability

SOLIDWORKS 2008 SP2, Revision Number 16.2

ITriadManipulator (Type)

ITriadManipulator Interface

[See Also](#) [Members](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) : ITriadManipulator Interface

Allows access to triad manipulators, which are:

- Similar to the SOLIDWORKS triad.
- Used to move and rotate assembly components, move/copy bodies, and so on.

NOTE: Click the **Members** link, located near the top of the topic, to see this interface's methods and properties.

.NET Syntax

Visual Basic (Declaration)

```
Public Interface ITriadManipulator
```

Visual Basic (Usage)



```
Dim instance As ITriadManipulator
```

C#

```
public interface ITriadManipulator
```

C++/CLI

```
public interface class ITriadManipulator
```

Visual Basic for Applications (VBA) Syntax

See [TriadManipulator](#).

Example

[Create Triad Manipulator \(VBA\)](#)
[Create Triad Manipulator \(VB.NET\)](#)
[Create Triad Manipulator \(C#\)](#)

Accessors

[IManipulator::GetSpecificManipulator](#)

Access Diagram

[TriadManipulator](#)

See Also

[ITriadManipulator Members](#)
[SolidWorks.Interop.sldworks Namespace](#)
[IManipulator Interface](#)
[IDragArrowManipulator Interface](#)

ITriadManipulator Interface Methods

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) : ITriadManipulator Interface

For a list of all members of this type, see [ITriadManipulator members](#).

Public Methods

Name	Description
------	-------------

	SetColorRefAtIndex	Sets the colors of the controls of a triad manipulator.
	UpdatePosition	Updates the position of this triad manipulator.
	UpdateScale	Sets scale for the triad manipulator's x,y,z axes.

[Top](#)

See Also

[ITriadManipulator Interface](#)
[SolidWorks.Interop.sldworks Namespace](#)
[IManipulator Interface](#)
[IDragArrowManipulator Interface](#)

SOLIDWORKS API Help

[Send comments on this topic.](#)

ITriadManipulator Interface Members

[See Also](#) [Properties](#) [Methods](#)



[SolidWorks.Interop.sldworks Namespace](#) : ITriadManipulator Interface

The following tables list the members exposed by [ITriadManipulator](#).

Public Properties

Name	Description
 Cursor	Sets the cursor to use when the pointer is over the triad manipulator.
 DoNotShow	Specifies which triad manipulator's control points to not show.
 Origin	Gets or sets the origin for this triad manipulator.
 PreviousDragPoint	Gets the previous drag position of the triad manipulator.
 XAxis	Gets or sets the x axis for this triad manipulator.
 YAxis	Gets or sets the y axis for this triad manipulator.
 ZAxis	Gets or sets the z axis for this triad manipulator.

[Top](#)

Public Methods

Name	Description
 SetColorRefAtIndex	Sets the colors of the controls of a triad manipulator.
 UpdatePosition	Updates the position of this triad manipulator.
 UpdateScale	Sets scale for the triad manipulator's x,y,z axes.

[Top](#)

See Also

[ITriadManipulator Interface](#)
[SolidWorks.Interop.sldworks Namespace](#)
[IManipulator Interface](#)
[IDragArrowManipulator Interface](#)

SOLIDWORKS API Help

[Send comments on this topic.](#)

ITriadManipulator Interface Properties

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) : ITriadManipulator Interface

For a list of all members of this type, see [ITriadManipulator members](#).

Public Properties

Name	Description
 Cursor	Sets the cursor to use when the pointer is over the triad manipulator.
 DoNotShow	Specifies which triad manipulator's control points to not show.
 Origin	Gets or sets the origin for this triad manipulator.



[PreviousDragPoint](#)

Gets the previous drag position of the triad manipulator.



[XAxis](#)

Gets or sets the x axis for this triad manipulator.



[YAxis](#)

Gets or sets the y axis for this triad manipulator.



[ZAxis](#)

Gets or sets the z axis for this triad manipulator.

[Top](#)

See Also

[ITriadManipulator Interface](#)
[SolidWorks.Interop.sldworks Namespace](#)
[IManipulator Interface](#)
[IDragArrowManipulator Interface](#)

SOLIDWORKS API Help

[Send comments on this topic.](#)

Cursor Property (ITriadManipulator)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ITriadManipulator Interface](#) : Cursor Property (ITriadManipulator)

Sets the cursor to use when the pointer is over the triad manipulator.

.NET Syntax

Visual Basic (Declaration)

WriteOnly Property Cursor As System.Integer

Visual Basic (Usage)



Dim instance As [ITriadManipulator](#)

instance.Cursor = value

C#

System.int Cursor {set;}

C++/CLI

```
property System.int Cursor {
    void set ( & System.int value);
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

Cursor to use as defined by [swManipulatorCursor_e](#)

Visual Basic for Applications (VBA) Syntax

See [TriadManipulator::Cursor](#).

See Also

[ITriadManipulator Interface](#)
[ITriadManipulator Members](#)

Availability

SOLIDWORKS 2005 FCS, Revision Number 13.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

DoNotShow Property (ITriadManipulator)

[See Also](#)



Specifies which triad manipulator's control points to not show.

.NET Syntax

Visual Basic (Declaration)

Property DoNotShow As System.Integer

Visual Basic (Usage)



```
Dim instance As ITriadManipulator
Dim value As System.Integer

instance.DoNotShow = value

value = instance.DoNotShow
```

C#

```
System.int DoNotShow {get; set;}
```

C++/CLI

```
property System.int DoNotShow {
    System.int get();
    void set ( & System.int value);
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

Control points to not show as defined in [swTriadManipulatorDoNotShow_e](#)

Visual Basic for Applications (VBA) Syntax

See [TriadManipulator::DoNotShow](#).

See Also

[ITriadManipulator Interface](#)
[ITriadManipulator Members](#)

Availability

SOLIDWORKS 2005 FCS, Revision Number 13.0

SOLIDWORKS API Help

[Send comments](#) on this topic.

Origin Property (ITriadManipulator)

[See Also](#)



SolidWorks.Interop.sldworks Namespace > [ITriadManipulator Interface](#) : Origin Property (ITriadManipulator)

Gets or sets the origin for this triad manipulator.

.NET Syntax

Visual Basic (Declaration)

Property Origin As MathPoint

Visual Basic (Usage)



```
Dim instance As ITriadManipulator
Dim value As MathPoint

instance.Origin = value
```

```
value = instance.Origin
```

C#

```
MathPoint Origin {get; set;}
```

C++/CLI

```
property MathPoint^ Origin {  
    MathPoint^ get();  
    void set ( & MathPoint^ value);  
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

[IMathPoint](#)

Visual Basic for Applications (VBA) Syntax

See [TriadManipulator::Origin](#).

Example

See the [ITriadManipulator](#) examples.

Remarks

To update the position of the manipulator, call [ITriadManipulator::UpdatePosition](#). Moving the triad manipulator to the location set by this property is done by the [handler](#).

See Also

[ITriadManipulator Interface](#)
[ITriadManipulator Members](#)
[ITriadManipulator::UpdatePosition Method](#)
[ITriadManipulator::XAxis Property](#)
[ITriadManipulator::YAxis Property](#)
[ITriadManipulator::ZAxis Property](#)

Availability

SOLIDWORKS 2005 FCS, Revision Number 13.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

PreviousDragPoint Property (ITriadManipulator)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ITriadManipulator Interface](#) : PreviousDragPoint Property (ITriadManipulator)

Gets the previous drag position of the triad manipulator.

.NET Syntax

Visual Basic (Declaration)

```
ReadOnly Property PreviousDragPoint As MathPoint
```

Visual Basic (Usage)



```
Dim instance As ITriadManipulator  
Dim value As MathPoint
```

```
value = instance.PreviousDragPoint
```

C#

```
MathPoint PreviousDragPoint {get;}
```

C++/CLI

```
property MathPoint^ PreviousDragPoint {  
    MathPoint^ get();  
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

[IMathPoint](#)

Visual Basic for Applications (VBA) Syntax

See [TriadManipulator::PreviousDragPoint](#).

See Also

[ITriadManipulator Interface](#)
[ITriadManipulator Members](#)

Availability

SOLIDWORKS 2007 FCS, Revision Number 15.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

SetColorRefAtIndex Method (ITriadManipulator)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ITriadManipulator Interface](#) : SetColorRefAtIndex Method (ITriadManipulator)

Sets the colors of the controls of a triad manipulator.

.NET Syntax

Visual Basic (Declaration)

```
Sub SetColorRefAtIndex( _  
    ByVal Index As System.Integer, _  
    ByVal ColorRef As System.Integer _  
)
```

Visual Basic (Usage)



```
Dim instance As ITriadManipulator  
Dim Index As System.Integer  
Dim ColorRef As System.Integer  
  
instance.SetColorRefAtIndex(Index, ColorRef)
```

C#

```
void SetColorRefAtIndex(  
    System.int Index,  
    System.int ColorRef  
)
```

C++/CLI

```
void SetColorRefAtIndex(  
& System.int Index,  
& System.int ColorRef  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Index

Control whose color to set as defined in [swTriadManipulatorControlPoints](#) [e](#)

ColorRef

COLORREF value

Visual Basic for Applications (VBA) Syntax

See [TriadManipulator::SetColorRefAtIndex](#).

See Also

[ITriadManipulator Interface](#)
[ITriadManipulator Members](#)

Availability

SOLIDWORKS 2008 FCS, Revision Number 16.0

SOLIDWORKS API Help

[Send comments](#) on this topic.

UpdatePosition Method (ITriadManipulator)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ITriadManipulator Interface](#) : UpdatePosition Method (ITriadManipulator)

Updates the position of this triad manipulator.

.NET Syntax

Visual Basic (Declaration)

```
Function UpdatePosition() As System.Boolean
```

Visual Basic (Usage)



```
Dim instance As ITriadManipulator  
Dim value As System.Boolean  
  
value = instance.UpdatePosition()
```

C#

```
System.bool UpdatePosition()
```

C++/CLI

```
System.bool UpdatePosition();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Return Value

True if the position of the triad manipulator is updated, false if not

Visual Basic for Applications (VBA) Syntax

See [TriadManipulator::UpdatePosition](#).

Remarks

After setting any of these properties, call this method to update the position of the triad manipulator:

- [ITriadManipulator::Origin](#)
- [ITriadManipulator::XAxis](#)
- [ITriadManipulator::YAxis](#)
- [ITriadManipulator::ZAxis](#)

See Also

[ITriadManipulator Interface](#)
[ITriadManipulator Members](#)
[ITriadManipulator::DoNotShow Property](#)

Availability

SOLIDWORKS 2005 FCS, Revision Number 13.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

UpdateScale Method (ITriadManipulator)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ITriadManipulator Interface](#) : UpdateScale Method (ITriadManipulator)

Sets scale for the triad manipulator's x,y,z axes.

.NET Syntax

Visual Basic (Declaration)

```
Sub UpdateScale( _  
    ByVal Scale As System.Double _  
)
```

Visual Basic (Usage)



```
Dim instance As ITriadManipulator  
Dim Scale As System.Double  
  
instance.UpdateScale(Scale)
```

C#

```
void UpdateScale(  
    System.double Scale  
)
```

C++/CLI

```
void UpdateScale(  
& System.double Scale  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Scale
Scale

Visual Basic for Applications (VBA) Syntax

See [TriadManipulator::UpdateScale](#).

Remarks

The initial length of an axis is 40 pixels, and the length is unrestricted. Each axis is the same length.

See Also

[ITriadManipulator Interface](#)
[ITriadManipulator Members](#)
[ITriadManipulator::DoNotShow Property](#)

Availability

SOLIDWORKS 2005 FCS, Revision Number 13.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

XAxis Property (ITriadManipulator)

[See Also](#)



Gets or sets the x axis for this triad manipulator.

.NET Syntax

Visual Basic (Declaration)

Property XAxis As MathVector

Visual Basic (Usage)



```
Dim instance As ITriadManipulator
Dim value As MathVector
```

```
instance.XAxis = value
```

```
value = instance.XAxis
```

C#

```
MathVector XAxis {get; set;}
```

C++/CLI

```
property MathVector^ XAxis {
    MathVector^ get();
    void set ( & MathVector^ value);
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

[IMathVector](#)

Visual Basic for Applications (VBA) Syntax

See [TriadManipulator::XAxis](#).

Remarks

To update the position of the manipulator, call [ITriadManipulator::UpdatePosition](#). Moving the triad manipulator to the location set by this property is done by the [handler](#).

See Also

[ITriadManipulator Interface](#)
[ITriadManipulator Members](#)
[ITriadManipulator::UpdatePosition Method](#)
[ITriadManipulator::Origin Property](#)
[ITriadManipulator::YAxis Property](#)
[ITriadManipulator::ZAxis Property](#)

Availability

SOLIDWORKS 2005 FCS, Revision Number 13.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

YAxis Property (ITriadManipulator)

[See Also](#)



SolidWorks.Interop.sldworks Namespace > ITriadManipulator Interface : YAxis Property (ITriadManipulator)

Gets or sets the y axis for this triad manipulator.

.NET Syntax

Visual Basic (Declaration)

Property YAxis As MathVector

```
Dim instance As ITriadManipulator
Dim value As MathVector

instance.YAxis = value

value = instance.YAxis
```

C#

```
MathVector YAxis {get; set;}
```

C++/CLI

```
property MathVector^ YAxis {
    MathVector^ get();
    void set ( & MathVector^ value);
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

[IMathVector](#)

Visual Basic for Applications (VBA) Syntax

See [TriadManipulator::YAxis](#).

Remarks

To update the position of the manipulator, call [ITriadManipulator::UpdatePosition](#). Moving the triad manipulator to the location set by this property is done by the [handler](#).

See Also

[ITriadManipulator Interface](#)
[ITriadManipulator Members](#)
[ITriadManipulator::UpdatePosition Method](#)
[ITriadManipulator::Origin Property](#)
[ITriadManipulator::XAxis Property](#)
[ITriadManipulator::ZAxis Property](#)

Availability

SOLIDWORKS 2005 FCS, Revision Number 13.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

ZAxis Property (ITriadManipulator)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ITriadManipulator Interface](#) : ZAxis Property (ITriadManipulator)

Gets or sets the z axis for this triad manipulator.

.NET Syntax

Visual Basic (Declaration)

```
Property ZAxis As MathVector
```

Visual Basic (Usage)

Copy Code

```
Dim instance As ITriadManipulator
Dim value As MathVector

instance.ZAxis = value

value = instance.ZAxis
```

C#

```
MathVector ZAxis {get; set;}
```

C++/CLI

```
property MathVector^ ZAxis {  
    MathVector^ get();  
    void set ( & MathVector^ value);  
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

[IMathVector](#)

Visual Basic for Applications (VBA) Syntax

See [TriadManipulator::ZAxis](#).

Remarks

To update the position of the manipulator, call [ITriadManipulator::UpdatePosition](#). Moving the triad manipulator to the location set by this property is done by the [handler](#).

See Also

[ITriadManipulator Interface](#)
[ITriadManipulator Members](#)
[ITriadManipulator::UpdatePosition Method](#)
[ITriadManipulator::Origin Property](#)
[ITriadManipulator::XAxis Property](#)
[ITriadManipulator::YAxis Property](#)

Availability

SOLIDWORKS 2005 FCS, Revision Number 13.0