

SOLIDWORKS API (VB6 COM) — Reference (3/102): AssemblyDoc (part 1 of 2)

SOLIDWORKS API Documentation (converted from CHM)

AssemblyDoc (part 1 of 2) (Type)

SOLIDWORKS Type Library

AssemblyDoc Object

 Object Model

AssemblyDoc

- AddComponent4 (Component2)
- AddComponent5 (Component2)
- AddComponentConfiguration (Configuration)
- AddConcentricMateWithTolerance (Mate2)
- AddDistanceMate (Mate2)
- AddMate2 (Mate2)
- AddMate3 (Mate2)
- AddMate4 (Mate2)
- AddMate5 (Mate2)
- AddSmartComponent (Component2)
- GetAdvancedSelection (AdvancedSelectionCriteria)
- GetComponentByName (Component2)
- GetEditTargetComponent (Component2)
- GetSimulation (Simulation)
- IAddComponent2 (Component)
- IAddComponent3 (Component2)
- IAddComponents (Component)
- IAddComponents2 (Component2)
- IAddComponents3 (Component2)
- IFeatureByName (Feature)
- IGetComponents (Component2)
- IGetDragOperator (DragOperator)
- IGetEditTarget (ModelDoc)
- IGetEditTarget2 (ModelDoc2)
- IGetFeatureScope (Component2)
- IGetFirstMember (Member)
- IGetSelectedMember (Member)
- IGetVisibleComponentsInView (Component2)
- IMirrorComponents (Component2)
- InsertEnvelope (Component2)

InsertLoadReference (MateLoadReference)

InterferenceDetectionManager (InterferenceDetectionMgr)

SOLIDWORKS Type Library

AssemblyDoc Object Members

Public Methods

 [ActivateGroundPlane](#)

 [AddComponent](#)

 [AddComponent2](#)

 [AddComponent4](#)

 [AddComponent5](#)

 [AddComponentConfiguration](#)

 [AddComponents](#)

 [AddComponents3](#)

 [AddConcentricMateWithTolerance](#)

 [AddDistanceMate](#)

 [AddMate](#)

 [AddMate2](#)

 [AddMate3](#)

 [AddMate4](#)

 [AddMate5](#)

 [AddPipePenetration](#)

 [AddPipingFitting](#)

 [AddPLMComponent](#)

 [AddSmartComponent](#)

 [AddToFeatureScope](#)

 [AssemblyPartToggle](#)

 [AutoAngleAxis](#)

 [AutoExplode](#)

 [AutoMateRepair](#)

 [CollectAllSupportiveMates](#)

 [CompConfigProperties](#)

 [CompConfigProperties2](#)

 [CompConfigProperties3](#)

 [CompConfigProperties4](#)

 [CompConfigProperties5](#)

 [CompConfigProperties6](#)

 [ComponentReload](#)

 [ComponentReload2](#)

 [CopyWithMates](#)

 [CopyWithMates2](#)

 [CreateExplodedView](#)

[CreateMate](#)

	
	CreateMateData
	CreateSmartComponent
	CreateSpeedPak
	DeleteSelections
	DissolveComponentPattern
	DissolveSubAssembly
	EditAssembly
	EditConcentricMate
	EditDistanceMate
	EditExplodeParameters
	EditMate
	EditMate2
	EditMate3
	EditMate4
	EditPart
	EditPart2
	EditRebuild
	ExitIsolate
	FeatureByName
	FeatureExtrusion
	FileDeriveComponentPart
	FixComponent
	ForceRebuild
	ForceRebuild2
	ForceUpdateElectricalData
	ForceUpdateElectricalData2
	GetActiveGroundPlane
	GetAdvancedSelection
	GetBox
	GetComponentById
	GetComponentByName
	GetComponentCount
	GetComponents
	GetDragOperator
	GetDroppedAIEntity
	GetEditTarget
	GetEditTargetComponent
	GetExplodedViewConfigurationName
	GetExplodedViewCount
	GetExplodedViewCount2
	GetExplodedViewNames
	GetExplodedViewNames2
	GetFeatureScope

	
	<u>GetFeatureScopeCount</u>
	<u>GetFirstMember</u>
	<u>GetLargeDesignReviewState</u>
	<u>GetLightWeightComponentCount</u>
	<u>GetPhysicalSimulationComponents</u>
	<u>GetRouteManager</u>
	<u>GetSelectedMember</u>
	<u>GetSimulation</u>
	<u>GetUnloadedComponentNames</u>
	<u>GetVisibleComponentsInView</u>
	<u>GetVisibleComponentsInViewCount</u>
	<u>HasUnloadedComponents</u>
	<u>HideComponent</u>
	<u>IAddComponent2</u>
	<u>IAddComponent3</u>
	<u>IAddComponents</u>
	<u>IAddComponents2</u>
	<u>IAddComponents3</u>
	<u>IComponentReload2</u>
	<u>IComponentReload3</u>
	<u>IFeatureByName</u>
	<u>IGetBox</u>
	<u>IGetComponents</u>
	<u>IGetDragOperator</u>
	<u>IGetEditTarget</u>
	<u>IGetEditTarget2</u>
	<u>IGetExplodedViewNames</u>
	<u>IGetFeatureScope</u>
	<u>IGetFirstMember</u>
	<u>IGetSelectedMember</u>
	<u>IGetVisibleComponentsInView</u>
	<u>IMirrorComponents</u>
	<u>InsertCavity</u>
	<u>InsertCavity2</u>
	<u>InsertCavity3</u>
	<u>InsertCavity4</u>
	<u>InsertDerivedPattern</u>
	<u>InsertEnvelope</u>
	<u>InsertImportedComponent</u>
	<u>InsertJoin</u>
	<u>InsertJoin2</u>
	<u>InsertLoadReference</u>
	<u>InsertNewAssembly</u>

	
	InsertNewPart
	InsertNewPart2
	InsertNewVirtualAssembly
	InsertNewVirtualPart
	InsertWeid
	InsertWeid2
	IReorderComponents
	IReorganizeComponents
	IsComponentTreeValid
	ISetComponentState
	ISetComponentVisibility
	Isolate
	IsRouteAssembly
	IToolsCheckInterference2
	IToolsCheckInterference3
	LightweightAllResolved
	MakeAssemblyFromSelectedComponents
	MakeIndependent
	MakeLightWeight
	MirrorComponents
	MirrorComponents2
	MirrorComponents3
	OpenCompFile
	RemoveFromFeatureScope
	ReorderComponents
	ReorganizeComponents
	ReplaceComponents
	ReplaceComponents2
	ReplacePLMComponents
	ResolveAllLightweight
	ResolveAllLightWeightComponents
	ResolveOutOfDateLightWeightComponents
	RotateComponent
	RotateComponentAxis
	SaveIsolate
	SelectComponentsBySize
	SelectiveOpen
	SetComponentState
	SetComponentSuppression
	SetComponentTransparent
	SetComponentVisibility
	SetDroppedFileConfigName
	SetDroppedFileFeatureName

	
	SetDroppedFileName
	SetForceResetConfigName
	SetIsolateVisibility
	SetSpeedPakConfigurations
	SetSpeedPakToParent
	ShowComponent
	ShowExploded
	ShowExploded2
	TemporaryFixGroup
	TemporaryFixGroupExit
	ToolsCheckInterference
	ToolsCheckInterference2
	TranslateComponent
	UnfixComponent
	UngroupComponents
	UpdateBox
	UpdateFeatureScope
	UpdateSpeedPak
	UpdateToolboxComponent
	UseSpeedPak
	ViewCollapseAssembly
	ViewExplodeAssembly
	ViewFeatureManagerByDependencies
	ViewFeatureManagerByFeatures
	ViewFeatureManagerFeatureDetail

Public Properties

	ClearanceVerificationManager
	EnableAssemblyRebuild
	EnablePresentation
	InterferenceDetectionManager
	IsSupportedMatesAvailable
	LargeDesignReviewTransparencyLevel
	LargeDesignReviewTransparencyLevelDynamic
	LargeDesignReviewTransparencyLevelEnabled

Events

	ActiveAnnotationViewChangeNotify
	ActiveConfigChangeNotify
	ActiveConfigChangePostNotify
	ActiveDisplayStateChangePostNotify
	ActiveDisplayStateChangePreNotify
	ActiveViewChangeNotify
	AddCustomPropertyNotify



 [AddDependencyNotify](#)

 [AddDvePagePreNotify](#)

 [AddItemNotify](#)

 [AddMatePostNotify](#)

 [AddMatePostNotify2](#)

 [AssemblyElectricalDataUpdateNotify](#)

 [AutoSaveNotify](#)

 [AutoSaveToStorageNotify](#)

 [AutoSaveToStorageStoreNotify](#)

 [BeginInContextEditNotify](#)

 [BodyVisibleChangeNotify](#)

 [ChangeCustomPropertyNotify](#)

 [ClearSelectionsNotify](#)

 [CloseDesignTableNotify](#)

 [CommandManagerTabActivatedPreNotify](#)

 [ComponentConfigurationChangeNotify](#)

 [ComponentDisplayModeChangePostNotify](#)

 [ComponentDisplayModeChangePreNotify](#)

 [ComponentDisplayStateChangeNotify](#)

 [ComponentMoveNotify](#)

 [ComponentMoveNotify2](#)

 [ComponentReferredDisplayStateChangeNotify](#)

 [ComponentReorganizeNotify](#)

 [ComponentStateChangeNotify](#)

 [ComponentStateChangeNotify2](#)

 [ComponentStateChangeNotify3](#)

 [ComponentVisibleChangeNotify](#)

 [ComponentVisualPropertiesChangeNotify](#)

 [ConfigurationChangeNotify](#)

 [DeleteCustomPropertyNotify](#)

 [DeleteDependencyNotify](#)

 [DeleteItemNotify](#)

 [DeleteItemPreNotify](#)

 [DeleteSelectionPreNotify](#)

 [DestroyNotify](#)

 [DestroyNotify2](#)

 [DimensionChangeNotify](#)

 [DisplayPaneCollapseNotify](#)

 [DisplayPaneExpandNotify](#)

 [DragStateChangeNotify](#)

 [DynamicHighlightNotify](#)

 [EndInContextEditNotify](#)

[EquationEditorPostNotify](#)



 [EquationEditorPreNotify](#)

 [FeatureEditPreNotify](#)

 [FeatureManagerFilterStringChangeNotify](#)

 [FeatureManagerTabActivatedNotify](#)

 [FeatureManagerTabActivatedPreNotify](#)

 [FeatureManagerTreeRebuildNotify](#)

 [FeatureSketchEditPreNotify](#)

 [FileDropNotify](#)

 [FileDropPostNotify](#)

 [FileDropPreNotify](#)

 [FileReloadCancelNotify](#)

 [FileReloadNotify](#)

 [FileReloadPreNotify](#)

 [FileSaveAsNotify](#)

 [FileSaveAsNotify2](#)

 [FileSaveNotify](#)

 [FileSavePostCancelNotify](#)

 [FileSavePostNotify](#)

 [FlipLoopNotify](#)

 [InsertTableNotify](#)

 [InterferenceNotify](#)

 [LargeDesignReviewStateChangeNotify](#)

 [LightingDialogCreateNotify](#)

 [LoadFromStorageNotify](#)

 [LoadFromStorageStoreNotify](#)

 [ModifyNotify](#)

 [ModifyTableNotify](#)

 [NewSelectionNotify](#)

 [OpenDesignTableNotify](#)

 [PreRenameItemNotify](#)

 [PromptBodiesToKeepNotify](#)

 [PublishTo3DPDFNotify](#)

 [RedoPostNotify](#)

 [RedoPreNotify](#)

 [RegenNotify](#)

 [RegenPostNotify](#)

 [RegenPostNotify2](#)

 [RenamedDocumentNotify](#)

 [RenameDisplayTitleNotify](#)

 [RenameItemNotify](#)

 [SaveToStorageNotify](#)

 [SaveToStorageStoreNotify](#)

[SelectiveOpenPostNotify](#)

	
	SensorAlertPreNotify
	SketchSolveNotify
	SolidBodyFolderReorderNotify
	SuppressionStateChangeNotify
	UndoPostNotify
	UndoPreNotify
	UnitsChangeNotify
	UserSelectionPostNotify
	UserSelectionPreNotify
	ViewNewNotify
	ViewNewNotify2

SOLIDWORKS Type Library

ActivateGroundPlane Method (AssemblyDoc)

 Syntax

Visual Basic for Applications (VBA)

```
Public Function ActivateGroundPlane( _  
    ByVal Config_opt As Long, _  
    ByVal Config_names As Variant _  
    ) As Boolean
```

SOLIDWORKS Type Library

ActiveAnnotationViewChangeNotify Event (AssemblyDoc)



 Syntax

Visual Basic for Applications (VBA)

```
Public Event ActiveAnnotationViewChangeNotify()
```

SOLIDWORKS Type Library

ActiveConfigChangeNotify Event (AssemblyDoc)



 Syntax

Visual Basic for Applications (VBA)

```
Public Event ActiveConfigChangeNotify()
```

SOLIDWORKS Type Library

ActiveConfigChangePostNotify Event (AssemblyDoc)



 Syntax

Visual Basic for Applications (VBA)

```
Public Event ActiveConfigChangePostNotify()
```

SOLIDWORKS Type Library

ActiveDisplayStateChangePostNotify Event (AssemblyDoc)



 Syntax

Visual Basic for Applications (VBA)

```
Public Event ActiveDisplayStateChangePostNotify( _  
    ByVal DisplayStateName As String _  
)
```

SOLIDWORKS Type Library

ActiveDisplayStateChangePreNotify Event (AssemblyDoc)



Syntax

Visual Basic for Applications (VBA)

```
Public Event ActiveDisplayStateChangePreNotify()
```

SOLIDWORKS Type Library

ActiveViewChangeNotify Event (AssemblyDoc)



Syntax

Visual Basic for Applications (VBA)

```
Public Event ActiveViewChangeNotify()
```

SOLIDWORKS Type Library

AddComponent Method (AssemblyDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Function AddComponent( _  
    ByVal CompName As String, _  
    ByVal X As Double, _  
    ByVal Y As Double, _  
    ByVal Z As Double _  
) As Boolean
```

SOLIDWORKS Type Library

AddComponent2 Method (AssemblyDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Function AddComponent2( _  
    ByVal CompName As String, _  
    ByVal X As Double, _  
    ByVal Y As Double, _  
    ByVal Z As Double _  
) As Object
```

SOLIDWORKS Type Library

AddComponent4 Method (AssemblyDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Function AddComponent4( _  
    ByVal CompName As String, _  
    ByVal ConfigName As String, _  
    ByVal X As Double, _  
    ByVal Y As Double, _  
    ByVal Z As Double _  
) As Component2
```

SOLIDWORKS Type Library

AddComponent5 Method (AssemblyDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Function AddComponent5( _  
    ByVal CompName As String, _  
    ByVal ConfigOption As Long, _  
    ByVal NewConfigName As String, _  
    ByVal UseConfigForPartReferences As Boolean, _  
    ByVal ExistingConfigName As String, _  
    ByVal X As Double, _  
    ByVal Y As Double, _  
    ByVal Z As Double _  
) As Component2
```

SOLIDWORKS Type Library

AddComponentConfiguration Method (AssemblyDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Function AddComponentConfiguration( _  
    ByVal Name As String, _  
    ByVal Comment As String, _  
    ByVal AlternateName As String, _  
    ByVal Options As Long _  
) As Configuration
```

SOLIDWORKS Type Library

AddComponents Method (AssemblyDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Function AddComponents( _  
    ByVal Names As Variant, _  
    ByVal Transforms As Variant _  
) As Variant
```

SOLIDWORKS Type Library

AddComponents3 Method (AssemblyDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Function AddComponents3( _  
    ByVal Names As Variant, _  
    ByVal Transforms As Variant, _  
    ByVal CoordinateSystemNames As Variant _  
) As Variant
```

SOLIDWORKS Type Library

AddConcentricMateWithTolerance Method (AssemblyDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Function AddConcentricMateWithTolerance( _  
    ByVal AlignFromEnum As Long, _  
    ByVal ConcentricPositionType As Long, _  
    ByVal ConcentricToleranceCheck As Boolean, _  
    ByVal ConcentricToleranceValue As Double, _  
    ByRef ErrorStatus As Long _  
) As Mate2
```

SOLIDWORKS Type Library

AddCustomPropertyNotify Event (AssemblyDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Event AddCustomPropertyNotify( _  
    ByVal propName As String, _  
    ByVal Configuration As String, _  
    ByVal Value As String, _  
    ByVal valueType As Long _  
)
```

SOLIDWORKS Type Library

AddDependencyNotify Event (AssemblyDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Event AddDependencyNotify( _  
    ByVal PathName As String _  
)
```

SOLIDWORKS Type Library

AddDistanceMate Method (AssemblyDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Function AddDistanceMate( _  
    ByVal AlignFromEnum As Long, _  
    ByVal Flip As Boolean, _  
    ByVal Distance As Double, _  
    ByVal DistanceAbsUpperLimit As Double, _  
    ByVal DistanceAbsLowerLimit As Double, _  
    ByVal FirstArcCondition As Long, _  
    ByVal SecondArcCondition As Long, _  
    ByRef ErrorStatus As Long _  
) As Mate2
```

SOLIDWORKS Type Library

AddDvePagePreNotify Event (AssemblyDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Event AddDvePagePreNotify( _  
    ByVal Command As Long, _  
    ByRef PageToAdd As Object _  
)
```

SOLIDWORKS Type Library

AddItemNotify Event (AssemblyDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Event AddItemNotify( _  
    ByVal EntityType As Long, _  
    ByVal itemName As String _  
)
```

SOLIDWORKS Type Library

AddMate Method (AssemblyDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub AddMate( _  
    ByVal MateType As Long, _  
    ByVal Align As Long, _  
    ByVal Flip As Boolean, _  
    ByVal Dist As Double, _  
    ByVal Angle As Double _  
)
```

SOLIDWORKS Type Library

AddMate2 Method (AssemblyDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Function AddMate2( _  
    ByVal MateTypeFromEnum As Long, _  
    ByVal AlignFromEnum As Long, _  
    ByVal Flip As Boolean, _  
    ByVal Distance As Double, _  
    ByVal DistanceAbsUpperLimit As Double, _  
    ByVal DistanceAbsLowerLimit As Double, _  
    ByVal GearRatioNumerator As Double, _  
    ByVal GearRatioDenominator As Double, _  
    ByVal Angle As Double, _  
    ByVal AngleAbsUpperLimit As Double, _  
    ByVal AngleAbsLowerLimit As Double, _  
    ByRef ErrorStatus As Long _  
) As Mate2
```

SOLIDWORKS Type Library

AddMate3 Method (AssemblyDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Function AddMate3( _  
    ByVal MateTypeFromEnum As Long, _  
    ByVal AlignFromEnum As Long, _  
    ByVal Flip As Boolean, _  
    ByVal Distance As Double, _  
    ByVal DistanceAbsUpperLimit As Double, _  
    ByVal DistanceAbsLowerLimit As Double, _  
    ByVal GearRatioNumerator As Double, _  
    ByVal GearRatioDenominator As Double, _  
    ByVal Angle As Double, _  
    ByVal AngleAbsUpperLimit As Double, _  
    ByVal AngleAbsLowerLimit As Double, _  
    ByVal ForPositioningOnly As Boolean, _  
    ByRef ErrorStatus As Long _  
) As Mate2
```

SOLIDWORKS Type Library

AddMate4 Method (AssemblyDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Function AddMate4( _  
    ByVal MateTypeFromEnum As Long, _  
    ByVal AlignFromEnum As Long, _  
    ByVal Flip As Boolean, _  
    ByVal Distance As Double, _  
    ByVal DistanceAbsUpperLimit As Double, _
```

```
ByVal DistanceAbsLowerLimit As Double, _  
ByVal GearRatioNumerator As Double, _  
ByVal GearRatioDenominator As Double, _  
ByVal Angle As Double, _  
ByVal AngleAbsUpperLimit As Double, _  
ByVal AngleAbsLowerLimit As Double, _  
ByVal ForPositioningOnly As Boolean, _  
ByVal LockRotation As Boolean, _  
ByRef ErrorStatus As Long _  
) As Mate2
```

SOLIDWORKS Type Library

AddMate5 Method (AssemblyDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Function AddMate5( _  
    ByVal MateTypeFromEnum As Long, _  
    ByVal AlignFromEnum As Long, _  
    ByVal Flip As Boolean, _  
    ByVal Distance As Double, _  
    ByVal DistanceAbsUpperLimit As Double, _  
    ByVal DistanceAbsLowerLimit As Double, _  
    ByVal GearRatioNumerator As Double, _  
    ByVal GearRatioDenominator As Double, _  
    ByVal Angle As Double, _  
    ByVal AngleAbsUpperLimit As Double, _  
    ByVal AngleAbsLowerLimit As Double, _  
    ByVal ForPositioningOnly As Boolean, _  
    ByVal LockRotation As Boolean, _  
    ByVal WidthMateOption As Long, _  
    ByRef ErrorStatus As Long _  
) As Mate2
```

SOLIDWORKS Type Library

AddMatePostNotify2 Event (AssemblyDoc)



Syntax

Visual Basic for Applications (VBA)

```
Public Event AddMatePostNotify2( _  
    ByRef Mates As Variant _  
)
```

SOLIDWORKS Type Library

AddMatePostNotify Event (AssemblyDoc)



Syntax

Visual Basic for Applications (VBA)

```
Public Event AddMatePostNotify()
```

SOLIDWORKS Type Library

AddPipePenetration Method (AssemblyDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Function AddPipePenetration() As Long
```

SOLIDWORKS Type Library

AddPipingFitting Method (AssemblyDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Function AddPipingFitting( _  
    ByVal PathName As String, _  
    ByVal ConfigName As String, _  
    ByVal AlignmentIndex As Integer _  
    ) As Boolean
```

SOLIDWORKS Type Library

AddPLMComponent Method (AssemblyDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Function AddPLMComponent( _  
    ByVal PLMID As String, _  
    ByVal ConfigName As String, _  
    ByVal X As Double, _  
    ByVal Y As Double, _  
    ByVal Z As Double _  
    ) As Object
```

SOLIDWORKS Type Library

AddSmartComponent Method (AssemblyDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Function AddSmartComponent( _  
    ByVal CompName As String, _  
    ByVal X As Double, _  
    ByVal Y As Double, _  
    ByVal Z As Double _  
    ) As Component2
```

SOLIDWORKS Type Library

AddToFeatureScope Method (AssemblyDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Function AddToFeatureScope( _  
    ByVal CompName As String _  
    ) As Boolean
```

SOLIDWORKS Type Library

AssemblyElectricalDataUpdateNotify Event (AssemblyDoc)



Syntax

Visual Basic for Applications (VBA)

```
Public Event AssemblyElectricalDataUpdateNotify( _  
    ByVal saveType As Long _  
    )
```

SOLIDWORKS Type Library

AssemblyPartToggle Method (AssemblyDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub AssemblyPartToggle()
```

SOLIDWORKS Type Library

AutoAngleAxis Method (AssemblyDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub AutoAngleAxis( _  
    ByVal Mate As Object _  
)
```

SOLIDWORKS Type Library

AutoExplode Method (AssemblyDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Function AutoExplode() As Boolean
```

SOLIDWORKS Type Library

AutoMateRepair Method (AssemblyDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Function AutoMateRepair( _  
    ByRef ProcessedMates As Variant, _  
    ByRef FailedMates As Variant _  
) As Long
```

SOLIDWORKS Type Library

AutoSaveNotify Event (AssemblyDoc)



Syntax

Visual Basic for Applications (VBA)

```
Public Event AutoSaveNotify( _  
    ByVal FileName As String _  
)
```

SOLIDWORKS Type Library

AutoSaveToStorageNotify Event (AssemblyDoc)



Syntax

Visual Basic for Applications (VBA)

```
Public Event AutoSaveToStorageNotify()
```

SOLIDWORKS Type Library

AutoSaveToStorageStoreNotify Event (AssemblyDoc)



Syntax

Visual Basic for Applications (VBA)

```
Public Event AutoSaveToStorageStoreNotify()
```

SOLIDWORKS Type Library

BeginInContextEditNotify Event (AssemblyDoc)



Syntax

Visual Basic for Applications (VBA)

```
Public Event BeginInContextEditNotify( _  
    ByVal docBeingEdited As Object, _  
    ByVal DocType As Long _  
)
```

SOLIDWORKS Type Library

BodyVisibleChangeNotify Event (AssemblyDoc)



Syntax

Visual Basic for Applications (VBA)

```
Public Event BodyVisibleChangeNotify()
```

SOLIDWORKS Type Library

ChangeCustomPropertyNotify Event (AssemblyDoc)



Syntax

Visual Basic for Applications (VBA)

```
Public Event ChangeCustomPropertyNotify( _  
    ByVal propName As String, _  
    ByVal Configuration As String, _  
    ByVal oldValue As String, _  
    ByVal NewValue As String, _  
    ByVal valueType As Long _  
)
```

SOLIDWORKS Type Library

ClearanceVerificationManager Property (AssemblyDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Property ClearanceVerificationManager As Object
```

SOLIDWORKS Type Library

ClearSelectionsNotify Event (AssemblyDoc)



Syntax

Visual Basic for Applications (VBA)

```
Public Event ClearSelectionsNotify()
```

SOLIDWORKS Type Library

CloseDesignTableNotify Event (AssemblyDoc)



Syntax

Visual Basic for Applications (VBA)

```
Public Event CloseDesignTableNotify( _  
    ByVal DesignTable As Object _  
)
```

SOLIDWORKS Type Library

CollectAllSupportiveMates Method (AssemblyDoc)

Syntax

Visual Basic for Applications (VBA)

Public Function CollectAllSupportiveMates() As Variant

SOLIDWORKS Type Library

CommandManagerTabActivatedPreNotify Event (AssemblyDoc)



Syntax

Visual Basic for Applications (VBA)

```
Public Event CommandManagerTabActivatedPreNotify( _  
    ByVal CommandTabIndex As Long, _  
    ByVal CommandTabName As String _  
)
```

SOLIDWORKS Type Library

CompConfigProperties Method (AssemblyDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub CompConfigProperties( _  
    ByVal M_suppressed As Boolean, _  
    ByVal M_show_component As Boolean, _  
    ByVal M_fdetail As Boolean _  
)
```

SOLIDWORKS Type Library

CompConfigProperties2 Method (AssemblyDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Function CompConfigProperties2( _  
    ByVal Suppression As Long, _  
    ByVal Visibility As Boolean, _  
    ByVal FeatureDetails As Boolean _  
) As Boolean
```

SOLIDWORKS Type Library

CompConfigProperties3 Method (AssemblyDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Function CompConfigProperties3( _  
    ByVal Suppression As Long, _  
    ByVal Solving As Long, _  
    ByVal Visibility As Boolean, _  
    ByVal FeatureDetails As Boolean _  
) As Boolean
```

SOLIDWORKS Type Library

CompConfigProperties4 Method (AssemblyDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Function CompConfigProperties4( _
    ByVal Suppression As Long, _
    ByVal Solving As Long, _
    ByVal Visibility As Boolean, _
    ByVal UseNamedRefConfig As Boolean, _
    ByVal RefConfigName As String, _
    ByVal ExcludeFromBOM As Boolean _
) As Boolean
```

SOLIDWORKS Type Library

CompConfigProperties5 Method (AssemblyDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Function CompConfigProperties5( _
    ByVal Suppression As Long, _
    ByVal Solving As Long, _
    ByVal Visibility As Boolean, _
    ByVal UseNamedRefConfig As Boolean, _
    ByVal RefConfigName As String, _
    ByVal ExcludeFromBOM As Boolean, _
    ByVal IsEnvelope As Boolean _
) As Boolean
```

SOLIDWORKS Type Library

CompConfigProperties6 Method (AssemblyDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Function CompConfigProperties6( _
    ByVal Suppression As Long, _
    ByVal Solving As Long, _
    ByVal Visibility As Boolean, _
    ByVal UseNamedRefConfig As Boolean, _
    ByVal RefConfigName As String, _
    ByVal ExcludeFromBOM As Boolean, _
    ByVal IsEnvelope As Boolean, _
    ByVal SaveAssemblyAsPartOption As Long _
) As Boolean
```

SOLIDWORKS Type Library

ComponentConfigurationChangeNotify Event (AssemblyDoc)



Syntax

Visual Basic for Applications (VBA)

```
Public Event ComponentConfigurationChangeNotify( _
    ByVal componentName As String, _
    ByVal oldConfigurationName As String, _
    ByVal newConfigurationName As String _
)
```

SOLIDWORKS Type Library

ComponentDisplayModeChangePostNotify Event (AssemblyDoc)



Syntax

Visual Basic for Applications (VBA)

```
Public Event ComponentDisplayModeChangePostNotify( _
    ByVal Component As Object _
)
```

ComponentDisplayModeChangePreNotify Event (AssemblyDoc) **Syntax**

Visual Basic for Applications (VBA)

```
Public Event ComponentDisplayModeChangePreNotify( _  
    ByVal Component As Object _  
)
```

ComponentDisplayStateChangeNotify Event (AssemblyDoc) **Syntax**

Visual Basic for Applications (VBA)

```
Public Event ComponentDisplayStateChangeNotify( _  
    ByVal Component As Object _  
)
```

ComponentMoveNotify2 Event (AssemblyDoc) **Syntax**

Visual Basic for Applications (VBA)

```
Public Event ComponentMoveNotify2( _  
    ByRef Components As Variant _  
)
```

ComponentMoveNotify Event (AssemblyDoc) **Syntax**

Visual Basic for Applications (VBA)

```
Public Event ComponentMoveNotify()
```

ComponentReferredDisplayStateChangeNotify Event (AssemblyDoc) **Syntax**

Visual Basic for Applications (VBA)

```
Public Event ComponentReferredDisplayStateChangeNotify( _  
    ByVal componentModel As Object, _  
    ByVal CompName As String, _  
    ByVal oldDSId As Long, _  
    ByVal oldDSName As String, _  
    ByVal newDSId As Long, _  
    ByVal newDSName As String _  
)
```

ComponentReload Method (AssemblyDoc) **Syntax**

Visual Basic for Applications (VBA)

```
Public Sub ComponentReload()
```

SOLIDWORKS Type Library

ComponentReload2 Method (AssemblyDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Function ComponentReload2( _  
    ByVal Component As Object, _  
    ByVal ReadOnly As Boolean, _  
    ByVal Options As Long _  
    ) As Long
```

SOLIDWORKS Type Library

ComponentReorganizeNotify Event (AssemblyDoc)



Syntax

Visual Basic for Applications (VBA)

```
Public Event ComponentReorganizeNotify( _  
    ByVal sourceName As String, _  
    ByVal targetName As String _  
    )
```

SOLIDWORKS Type Library

ComponentStateChangeNotify2 Event (AssemblyDoc)



Syntax

Visual Basic for Applications (VBA)

```
Public Event ComponentStateChangeNotify2( _  
    ByVal componentModel As Object, _  
    ByVal CompName As String, _  
    ByVal oldCompState As Integer, _  
    ByVal newCompState As Integer _  
    )
```

SOLIDWORKS Type Library

ComponentStateChangeNotify3 Event (AssemblyDoc)



Syntax

Visual Basic for Applications (VBA)

```
Public Event ComponentStateChangeNotify3( _  
    ByVal Component As Object, _  
    ByVal CompName As String, _  
    ByVal oldCompState As Integer, _  
    ByVal newCompState As Integer _  
    )
```

SOLIDWORKS Type Library

ComponentStateChangeNotify Event (AssemblyDoc)



Syntax

Visual Basic for Applications (VBA)

```
Public Event ComponentStateChangeNotify( _  
    ByVal componentModel As Object, _
```

```
ByVal oldCompState As Integer, _  
ByVal newCompState As Integer _  
)
```

SOLIDWORKS Type Library

ComponentVisibleChangeNotify Event (AssemblyDoc)



Syntax

Visual Basic for Applications (VBA)

```
Public Event ComponentVisibleChangeNotify()
```

SOLIDWORKS Type Library

ComponentVisualPropertiesChangeNotify Event (AssemblyDoc)



Syntax

Visual Basic for Applications (VBA)

```
Public Event ComponentVisualPropertiesChangeNotify( _  
ByVal Component As Object _  
)
```

SOLIDWORKS Type Library

ConfigurationChangeNotify Event (AssemblyDoc)



Syntax

Visual Basic for Applications (VBA)

```
Public Event ConfigurationChangeNotify( _  
ByVal ConfigurationName As String, _  
ByVal Object As Object, _  
ByVal ObjectType As Long, _  
ByVal changeType As Long _  
)
```

SOLIDWORKS Type Library

CopyWithMates Method (AssemblyDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Function CopyWithMates( _  
ByVal ComponentsToCopy As Variant, _  
ByVal Repeat As Variant, _  
ByVal NewEntityToMateTo As Variant, _  
ByVal Values As Variant, _  
ByVal FlipAlignment As Variant _  
) As Boolean
```

SOLIDWORKS Type Library

CopyWithMates2 Method (AssemblyDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Function CopyWithMates2( _  
ByVal ComponentsToCopy As Variant, _  
ByVal Repeat As Variant, _  
ByVal NewEntityToMateTo As Variant, _  
ByVal Values As Variant, _  
ByVal FlipAlignment As Variant, _  
ByVal FlipDimension As Variant, _
```

```
    ByVal LockRotation As Variant, _  
    ByVal Orientation As Variant _  
) As Boolean
```

SOLIDWORKS Type Library

CreateExplodedView Method (AssemblyDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Function CreateExplodedView() As Boolean
```

SOLIDWORKS Type Library

CreateMate Method (AssemblyDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Function CreateMate( _  
    ByVal MateData As Object _  
) As Object
```

SOLIDWORKS Type Library

CreateMateData Method (AssemblyDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Function CreateMateData( _  
    ByVal Type As Long _  
) As Object
```

SOLIDWORKS Type Library

CreateSmartComponent Method (AssemblyDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Function CreateSmartComponent( _  
    ByVal ComponentIn As Component2, _  
    ByVal RelatedComponents As Variant, _  
    ByVal RelatedFeatures As Variant, _  
    ByVal AutoSizeDiameter As Boolean, _  
    ByVal LpMateReference As Entity, _  
    ByVal BoundingValues As Variant _  
) As Boolean
```

SOLIDWORKS Type Library

CreateSpeedPak Method (AssemblyDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Function CreateSpeedPak( _  
    ByVal SpeedPakType As Long _  
) As Boolean
```

SOLIDWORKS Type Library

DeleteCustomPropertyNotify Event (AssemblyDoc)



Syntax

Visual Basic for Applications (VBA)

```
Public Event DeleteCustomPropertyNotify( _  
    ByVal propName As String, _  
    ByVal Configuration As String, _  
    ByVal Value As String, _  
    ByVal valueType As Long _  
)
```

SOLIDWORKS Type Library

DeleteDependencyNotify Event (AssemblyDoc)



Syntax

Visual Basic for Applications (VBA)

```
Public Event DeleteDependencyNotify( _  
    ByVal PathName As String _  
)
```

SOLIDWORKS Type Library

DeleteItemNotify Event (AssemblyDoc)



Syntax

Visual Basic for Applications (VBA)

```
Public Event DeleteItemNotify( _  
    ByVal EntityType As Long, _  
    ByVal itemName As String _  
)
```

SOLIDWORKS Type Library

DeleteItemPreNotify Event (AssemblyDoc)



Syntax

Visual Basic for Applications (VBA)

```
Public Event DeleteItemPreNotify( _  
    ByVal EntityType As Long, _  
    ByVal itemName As String _  
)
```

SOLIDWORKS Type Library

DeleteSelectionPreNotify Event (AssemblyDoc)



Syntax

Visual Basic for Applications (VBA)

```
Public Event DeleteSelectionPreNotify()
```

SOLIDWORKS Type Library

DeleteSelections Method (AssemblyDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Function DeleteSelections( _  
    ByVal DeleteOptions As Long _  
) As Boolean
```

SOLIDWORKS Type Library

DestroyNotify2 Event (AssemblyDoc)



Visual Basic for Applications (VBA)

```
Public Event DestroyNotify2( _  
    ByVal DestroyType As Long _  
)
```

SOLIDWORKS Type Library

DestroyNotify Event (AssemblyDoc)



Visual Basic for Applications (VBA)

```
Public Event DestroyNotify()
```

SOLIDWORKS Type Library

DimensionChangeNotify Event (AssemblyDoc)



Visual Basic for Applications (VBA)

```
Public Event DimensionChangeNotify( _  
    ByVal displayDim As Object _  
)
```

SOLIDWORKS Type Library

DisplayPaneCollapseNotify Event (AssemblyDoc)



Visual Basic for Applications (VBA)

```
Public Event DisplayPaneCollapseNotify()
```

SOLIDWORKS Type Library

DisplayPaneExpandNotify Event (AssemblyDoc)



Visual Basic for Applications (VBA)

```
Public Event DisplayPaneExpandNotify()
```

SOLIDWORKS Type Library

DissolveComponentPattern Method (AssemblyDoc)



Visual Basic for Applications (VBA)

```
Public Function DissolveComponentPattern() As Boolean
```

SOLIDWORKS Type Library

DissolveSubAssembly Method (AssemblyDoc)



Visual Basic for Applications (VBA)

```
Public Function DissolveSubAssembly() As Boolean
```

DragStateChangeNotify Event (AssemblyDoc) **Syntax**

Visual Basic for Applications (VBA)

```
Public Event DragStateChangeNotify( _  
    ByVal State As Boolean _  
)
```

DynamicHighlightNotify Event (AssemblyDoc) **Syntax**

Visual Basic for Applications (VBA)

```
Public Event DynamicHighlightNotify( _  
    ByVal bHighlightState As Boolean _  
)
```

EditAssembly Method (AssemblyDoc) **Syntax**

Visual Basic for Applications (VBA)

```
Public Sub EditAssembly()
```

EditConcentricMate Method (AssemblyDoc) **Syntax**

Visual Basic for Applications (VBA)

```
Public Sub EditConcentricMate( _  
    ByVal AlignFromEnum As Long, _  
    ByVal ConcentricPositionType As Long, _  
    ByVal ConcentricToleranceCheck As Boolean, _  
    ByVal ConcentricToleranceValue As Double, _  
    ByRef ErrorStatus As Long _  
)
```

EditDistanceMate Method (AssemblyDoc) **Syntax**

Visual Basic for Applications (VBA)

```
Public Sub EditDistanceMate( _  
    ByVal AlignFromEnum As Long, _  
    ByVal Flip As Boolean, _  
    ByVal Distance As Double, _  
    ByVal DistanceAbsUpperLimit As Double, _  
    ByVal DistanceAbsLowerLimit As Double, _  
    ByVal FirstArcCondition As Long, _  
    ByVal SecondArcCondition As Long, _  
    ByRef ErrorStatus As Long _  
)
```

EditExplodeParameters Method (AssemblyDoc) **Syntax**

```
Public Sub EditExplodeParameters()
```

EditMate Method (AssemblyDoc) **Syntax**

```
Public Sub EditMate( _
    ByVal MateType As Long, _
    ByVal Align As Long, _
    ByVal Flip As Boolean, _
    ByVal Dist As Double, _
    ByVal Angle As Double _
)
```

EditMate2 Method (AssemblyDoc) **Syntax**

```
Public Sub EditMate2( _
    ByVal MateTypeFromEnum As Long, _
    ByVal AlignFromEnum As Long, _
    ByVal Flip As Boolean, _
    ByVal Distance As Double, _
    ByVal DistanceAbsUpperLimit As Double, _
    ByVal DistanceAbsLowerLimit As Double, _
    ByVal GearRatioNumerator As Double, _
    ByVal GearRatioDenominator As Double, _
    ByVal Angle As Double, _
    ByVal AngleAbsUpperLimit As Double, _
    ByVal AngleAbsLowerLimit As Double, _
    ByRef ErrorStatus As Long _
)
```

EditMate3 Method (AssemblyDoc) **Syntax**

```
Public Sub EditMate3( _
    ByVal MateTypeFromEnum As Long, _
    ByVal AlignFromEnum As Long, _
    ByVal Flip As Boolean, _
    ByVal Distance As Double, _
    ByVal DistanceAbsUpperLimit As Double, _
    ByVal DistanceAbsLowerLimit As Double, _
    ByVal GearRatioNumerator As Double, _
    ByVal GearRatioDenominator As Double, _
    ByVal Angle As Double, _
    ByVal AngleAbsUpperLimit As Double, _
    ByVal AngleAbsLowerLimit As Double, _
    ByVal ForPositioningOnly As Boolean, _
    ByVal LockRotation As Boolean, _
    ByVal WidthMateOption As Long, _
    ByRef ErrorStatus As Long _
)
```

EditMate4 Method (AssemblyDoc) **Syntax**

```
Public Sub EditMate4( _
    ByVal MateTypeEnum As Long, _
    ByVal AlignFromEnum As Long, _
    ByVal Flip As Boolean, _
    ByVal Distance As Double, _
    ByVal DistanceAbsUpperLimit As Double, _
    ByVal DistanceAbsLowerLimit As Double, _
    ByVal GearRatioNumerator As Double, _
    ByVal GearRatioDenominator As Double, _
    ByVal Angle As Double, _
    ByVal AngleAbsUpperLimit As Double, _
    ByVal AngleAbsLowerLimit As Double, _
    ByVal ForPositioningOnly As Boolean, _
    ByVal LockRotation As Boolean, _
    ByVal WidthMateOption As Long, _
    ByVal RepairMatesWithSameMissingEntity As Boolean, _
    ByRef ErrorStatus As Long _
)
```

SOLIDWORKS Type Library

EditPart Method (AssemblyDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub EditPart()
```

SOLIDWORKS Type Library

EditPart2 Method (AssemblyDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Function EditPart2( _
    ByVal Silent As Boolean, _
    ByVal AllowReadOnly As Boolean, _
    ByRef Information As Long _
) As Long
```

SOLIDWORKS Type Library

EditRebuild Method (AssemblyDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub EditRebuild()
```

SOLIDWORKS Type Library

EnableAssemblyRebuild Property (AssemblyDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Property EnableAssemblyRebuild As Boolean
```

SOLIDWORKS Type Library

EnablePresentation Property (AssemblyDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Property EnablePresentation As Boolean
```

SOLIDWORKS Type Library

EndInContextEditNotify Event (AssemblyDoc)



Visual Basic for Applications (VBA)

```
Public Event EndInContextEditNotify( _  
    ByVal docBeingEdited As Object, _  
    ByVal DocType As Long _  
)
```

SOLIDWORKS Type Library

EquationEditorPostNotify Event (AssemblyDoc)



Visual Basic for Applications (VBA)

```
Public Event EquationEditorPostNotify( _  
    ByVal Changed As Boolean _  
)
```

SOLIDWORKS Type Library

EquationEditorPreNotify Event (AssemblyDoc)



Visual Basic for Applications (VBA)

```
Public Event EquationEditorPreNotify()
```

SOLIDWORKS Type Library

ExitIsolate Method (AssemblyDoc)



Visual Basic for Applications (VBA)

```
Public Function ExitIsolate() As Boolean
```

SOLIDWORKS Type Library

FeatureByName Method (AssemblyDoc)



Visual Basic for Applications (VBA)

```
Public Function FeatureByName( _  
    ByVal Name As String _  
) As Object
```

SOLIDWORKS Type Library

FeatureEditPreNotify Event (AssemblyDoc)



Visual Basic for Applications (VBA)

```
Public Event FeatureEditPreNotify( _  
    ByVal EditFeature As Object _  
)
```

SOLIDWORKS Type Library

FeatureExtrusion Method (AssemblyDoc)



Visual Basic for Applications (VBA)

```
Public Sub FeatureExtrusion()
```

SOLIDWORKS Type Library

FeatureManagerFilterStringChangeNotify Event (AssemblyDoc)



Syntax

Visual Basic for Applications (VBA)

```
Public Event FeatureManagerFilterStringChangeNotify( _  
    ByVal FilterString As String _  
)
```

SOLIDWORKS Type Library

FeatureManagerTabActivatedNotify Event (AssemblyDoc)



Syntax

Visual Basic for Applications (VBA)

```
Public Event FeatureManagerTabActivatedNotify( _  
    ByVal CommandIndex As Long, _  
    ByVal CommandTabName As String _  
)
```

SOLIDWORKS Type Library

FeatureManagerTabActivatedPreNotify Event (AssemblyDoc)



Syntax

Visual Basic for Applications (VBA)

```
Public Event FeatureManagerTabActivatedPreNotify( _  
    ByVal CommandIndex As Long, _  
    ByVal CommandTabName As String _  
)
```

SOLIDWORKS Type Library

FeatureManagerTreeRebuildNotify Event (AssemblyDoc)



Syntax

Visual Basic for Applications (VBA)

```
Public Event FeatureManagerTreeRebuildNotify()
```

SOLIDWORKS Type Library

FeatureSketchEditPreNotify Event (AssemblyDoc)



Syntax

Visual Basic for Applications (VBA)

```
Public Event FeatureSketchEditPreNotify( _  
    ByVal EditFeature As Object, _  
    ByVal featureSketch As Object _  
)
```

SOLIDWORKS Type Library

FileDeriveComponentPart Method (AssemblyDoc)

Syntax

```
Public Sub FileDeriveComponentPart()
```

SOLIDWORKS Type Library

FileDropNotify Event (AssemblyDoc)



Syntax

Visual Basic for Applications (VBA)

```
Public Event FileDropNotify( _  
    ByVal FileName As String _  
)
```

SOLIDWORKS Type Library

FileDropPostNotify Event (AssemblyDoc)



Syntax

Visual Basic for Applications (VBA)

```
Public Event FileDropPostNotify()
```

SOLIDWORKS Type Library

FileDropPreNotify Event (AssemblyDoc)



Syntax

Visual Basic for Applications (VBA)

```
Public Event FileDropPreNotify( _  
    ByVal FileName As String _  
)
```

SOLIDWORKS Type Library

FileReloadCancelNotify Event (AssemblyDoc)



Syntax

Visual Basic for Applications (VBA)

```
Public Event FileReloadCancelNotify( _  
    ByVal ErrorCode As Long _  
)
```

SOLIDWORKS Type Library

FileReloadNotify Event (AssemblyDoc)



Syntax

Visual Basic for Applications (VBA)

```
Public Event FileReloadNotify()
```

SOLIDWORKS Type Library

FileReloadPreNotify Event (AssemblyDoc)



Syntax

Visual Basic for Applications (VBA)

Public Event FileReloadPreNotify()

SOLIDWORKS Type Library

FileSaveAsNotify2 Event (AssemblyDoc)



Syntax

Visual Basic for Applications (VBA)

```
Public Event FileSaveAsNotify2( _  
    ByVal FileName As String _  
)
```

SOLIDWORKS Type Library

FileSaveAsNotify Event (AssemblyDoc)



Syntax

Visual Basic for Applications (VBA)

```
Public Event FileSaveAsNotify( _  
    ByVal FileName As String _  
)
```

SOLIDWORKS Type Library

FileSaveNotify Event (AssemblyDoc)



Syntax

Visual Basic for Applications (VBA)

```
Public Event FileSaveNotify( _  
    ByVal FileName As String _  
)
```

SOLIDWORKS Type Library

FileSavePostCancelNotify Event (AssemblyDoc)



Syntax

Visual Basic for Applications (VBA)

```
Public Event FileSavePostCancelNotify()
```

SOLIDWORKS Type Library

FileSavePostNotify Event (AssemblyDoc)



Syntax

Visual Basic for Applications (VBA)

```
Public Event FileSavePostNotify( _  
    ByVal saveType As Long, _  
    ByVal FileName As String _  
)
```

SOLIDWORKS Type Library

FixComponent Method (AssemblyDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub FixComponent()
```

SOLIDWORKS Type Library

FlipLoopNotify Event (AssemblyDoc)



Syntax

Visual Basic for Applications (VBA)

```
Public Event FlipLoopNotify( _  
    ByVal TheLoop As Object, _  
    ByVal TheEdge As Object _  
)
```

SOLIDWORKS Type Library

ForceRebuild Method (AssemblyDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub ForceRebuild()
```

SOLIDWORKS Type Library

ForceRebuild2 Method (AssemblyDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub ForceRebuild2( _  
    ByVal TopOnly As Boolean _  
)
```

SOLIDWORKS Type Library

ForceUpdateElectricalData Method (AssemblyDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub ForceUpdateElectricalData( _  
    ByVal Stream As Long _  
)
```

SOLIDWORKS Type Library

ForceUpdateElectricalData2 Method (AssemblyDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Function ForceUpdateElectricalData2( _  
    ByVal Stream As Long _  
) As Long
```

SOLIDWORKS Type Library

GetActiveGroundPlane Method (AssemblyDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetActiveGroundPlane( _  
    ByVal Config_opt As Long, _  
    ByVal Config_names As Variant _  
) As Variant
```

SOLIDWORKS Type Library

GetAdvancedSelection Method (AssemblyDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetAdvancedSelection() As AdvancedSelectionCriteria
```

SOLIDWORKS Type Library

GetBox Method (AssemblyDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetBox( _  
    ByVal Options As Long _  
) As Variant
```

SOLIDWORKS Type Library

GetComponentByID Method (AssemblyDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetComponentByID( _  
    ByVal ID As Long _  
) As Object
```

SOLIDWORKS Type Library

GetComponentByName Method (AssemblyDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetComponentByName( _  
    ByVal CompName As String _  
) As Component2
```

SOLIDWORKS Type Library

GetComponentCount Method (AssemblyDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetComponentCount( _  
    ByVal ToplevelOnly As Boolean _  
) As Long
```

SOLIDWORKS Type Library

GetComponents Method (AssemblyDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetComponents( _  
    ByVal ToplevelOnly As Boolean _  
) As Variant
```

SOLIDWORKS Type Library

GetDragOperator Method (AssemblyDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetDragOperator() As Object
```

GetDroppedAtEntity Method (AssemblyDoc)**Syntax**

Visual Basic for Applications (VBA)

```
Public Function GetDroppedAtEntity() As Object
```

GetEditTarget Method (AssemblyDoc)**Syntax**

Visual Basic for Applications (VBA)

```
Public Function GetEditTarget() As Object
```

GetEditTargetComponent Method (AssemblyDoc)**Syntax**

Visual Basic for Applications (VBA)

```
Public Function GetEditTargetComponent() As Component2
```

GetExplodedViewConfigurationName Method (AssemblyDoc)**Syntax**

Visual Basic for Applications (VBA)

```
Public Function GetExplodedViewConfigurationName( _  
    ByVal ExplodedViewName As String _  
) As String
```

GetExplodedViewCount Method (AssemblyDoc)**Syntax**

Visual Basic for Applications (VBA)

```
Public Function GetExplodedViewCount() As Long
```