

SOLIDWORKS API (VB6 COM) — Reference (6/102): BlockDefinition-Body

SOLIDWORKS API Documentation (converted from CHM)

BlockDefinition (Type)

SOLIDWORKS Type Library

BlockDefinition Object

Object Model



SOLIDWORKS Type Library

BlockDefinition Object Members

Public Methods

 GetBasePoint
 GetBlockInstanceCount
 GetBlockInstances
 GetDimensionCount
 GetDimensions
 GetExternalFileName
 GetNoteCount
 GetNotes
 GetSketch
 GetUseExternalFile
 IGetBasePoint
 IGetBlockInstances
 IGetDimensions
 IGetNotes
 InsertInstance
 ISetBasePoint
 SetBasePoint
 SetExternalFileName
 SetUseExternalFile

Public Properties

 Name
--

SOLIDWORKS Type Library

GetBasePoint Method (BlockDefinition)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetBasePoint() As Variant
```

SOLIDWORKS Type Library

GetBlockInstanceCount Method (BlockDefinition)



Visual Basic for Applications (VBA)

```
Public Function GetBlockInstanceCount() As Long
```

SOLIDWORKS Type Library

GetBlockInstances Method (BlockDefinition)



Visual Basic for Applications (VBA)

```
Public Function GetBlockInstances() As Variant
```

SOLIDWORKS Type Library

GetDimensionCount Method (BlockDefinition)



Visual Basic for Applications (VBA)

```
Public Function GetDimensionCount() As Long
```

SOLIDWORKS Type Library

GetDimensions Method (BlockDefinition)



Visual Basic for Applications (VBA)

```
Public Function GetDimensions() As Variant
```

SOLIDWORKS Type Library

GetExternalFileName Method (BlockDefinition)



Visual Basic for Applications (VBA)

```
Public Function GetExternalFileName() As String
```

SOLIDWORKS Type Library

GetNoteCount Method (BlockDefinition)



Visual Basic for Applications (VBA)

```
Public Function GetNoteCount() As Long
```

SOLIDWORKS Type Library

GetNotes Method (BlockDefinition)



Visual Basic for Applications (VBA)

```
Public Function GetNotes() As Variant
```

SOLIDWORKS Type Library

GetSketch Method (BlockDefinition)



Visual Basic for Applications (VBA)

```
Public Function GetSketch() As Sketch
```

SOLIDWORKS Type Library

GetUseExternalFile Method (BlockDefinition)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetUseExternalFile() As Boolean
```

SOLIDWORKS Type Library

IGetBasePoint Method (BlockDefinition)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IGetBasePoint() As Double
```

SOLIDWORKS Type Library

IGetBlockInstances Method (BlockDefinition)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IGetBlockInstances( _  
    ByVal Count As Long _  
) As BlockInstance
```

SOLIDWORKS Type Library

IGetDimensions Method (BlockDefinition)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IGetDimensions( _  
    ByVal NumDimensions As Long _  
) As DisplayDimension
```

SOLIDWORKS Type Library

IGetNotes Method (BlockDefinition)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IGetNotes( _  
    ByVal NumNotes As Long _  
) As Note
```

SOLIDWORKS Type Library

InsertInstance Method (BlockDefinition)

Syntax

Visual Basic for Applications (VBA)

```
Public Function InsertInstance( _  
    ByVal X As Double, _  
    ByVal Y As Double, _  
    ByVal Angle As Double, _  
    ByVal Scale As Double _  
) As BlockInstance
```

SOLIDWORKS Type Library

ISetBasePoint Method (BlockDefinition)



Visual Basic for Applications (VBA)

```
Public Function ISetBasePoint( _  
    ByRef BasePoint As Double _  
) As Boolean
```

SOLIDWORKS Type Library

Name Property (BlockDefinition)



Visual Basic for Applications (VBA)

```
Public Property Name As String
```

SOLIDWORKS Type Library

SetBasePoint Method (BlockDefinition)



Visual Basic for Applications (VBA)

```
Public Function SetBasePoint( _  
    ByVal BasePoint As Variant _  
) As Boolean
```

SOLIDWORKS Type Library

SetExternalFileName Method (BlockDefinition)



Visual Basic for Applications (VBA)

```
Public Function SetExternalFileName( _  
    ByVal FileName As String _  
) As Long
```

SOLIDWORKS Type Library

SetUseExternalFile Method (BlockDefinition)



Visual Basic for Applications (VBA)

```
Public Function SetUseExternalFile( _  
    ByVal UseFile As Boolean _  
) As Long
```

BlockInstance (Type)

SOLIDWORKS Type Library

BlockInstance Object

Object Model

BlockInstance

Definition (BlockDefinition)

GetAnnotation (Annotation)

GetNext (BlockInstance)

IGetAttributes (Note)

SOLIDWORKS Type Library

BlockInstance Object Members

Public Methods

 [GetAnnotation](#)

 [GetAttributeCount](#)

 [GetAttributes](#)

 [GetAttributeValue](#)

 [GetNext](#)

 [IGetAttributes](#)

 [SetAttributeValue](#)

Public Properties

 [Angle](#)

 [Definition](#)

 [Scale2](#)

 [TextDisplay](#)

SOLIDWORKS Type Library

Angle Property (BlockInstance)

Syntax

Visual Basic for Applications (VBA)

Public Property Angle As Double

SOLIDWORKS Type Library

Definition Property (BlockInstance)

Syntax

Visual Basic for Applications (VBA)

Public Property Definition As [BlockDefinition](#)

SOLIDWORKS Type Library

GetAnnotation Method (BlockInstance)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetAnnotation() As Annotation
```

SOLIDWORKS Type Library

GetAttributeCount Method (BlockInstance)



Visual Basic for Applications (VBA)

```
Public Function GetAttributeCount() As Long
```

SOLIDWORKS Type Library

GetAttributes Method (BlockInstance)



Visual Basic for Applications (VBA)

```
Public Function GetAttributes() As Variant
```

SOLIDWORKS Type Library

GetAttributeValue Method (BlockInstance)



Visual Basic for Applications (VBA)

```
Public Function GetAttributeValue( _  
    ByVal TagName As String _  
) As String
```

SOLIDWORKS Type Library

GetNext Method (BlockInstance)



Visual Basic for Applications (VBA)

```
Public Function GetNext() As BlockInstance
```

SOLIDWORKS Type Library

IGetAttributes Method (BlockInstance)



Visual Basic for Applications (VBA)

```
Public Function IGetAttributes( _  
    ByVal NumAttribs As Long _  
) As Note
```

SOLIDWORKS Type Library

Scale2 Property (BlockInstance)



Visual Basic for Applications (VBA)

```
Public Property Scale2 As Double
```

SOLIDWORKS Type Library

SetAttributeValue Method (BlockInstance)



Visual Basic for Applications (VBA)

```
Public Function SetAttributeValue( _  
    ByVal TagName As String, _
```

```
ByVal Value As String _  
) As Boolean
```

SOLIDWORKS Type Library

TextDisplay Property (BlockInstance)

 **Syntax**

Visual Basic for Applications (VBA)

```
Public Property TextDisplay As Long
```

Body (Type)

SOLIDWORKS Type Library

Body Object

 Object Model

Body

EnumFaces

IAddProfileArc (Curve)

IAddProfileArcDLL (Curve)

IAddProfileBspine (Curve)

IAddProfileBspineDLL (Curve)

IAddProfileLine (Curve)

IAddProfileLineDLL (Curve)

IAddVertexPoint (Vertex)

ICopy (Body)

ICreateBlendSurface (Surface)

ICreateBodyFromFaces (Body)

ICreateBspineSurface (Surface)

ICreateBspineSurfaceDLL (Surface)

ICreateExtrusionSurface (Surface)

ICreateExtrusionSurfaceDLL (Surface)

ICreateNewSurface (Surface)

ICreateOffsetSurface (Surface)

ICreatePlanarSurface (Surface)

ICreatePlanarSurfaceDLL (Surface)

ICreatePspineSurfaceDLL (Surface)

ICreateRevolutionSurface (Surface)

ICreateRevolutionSurfaceDLL (Surface)

ICreateTempBodyFromSurfaces (Body)

IGetExcessBodyArray (Body)

IGetFirstFace (Face)

IGetFirstSelectedFace (Face)

IGetIntersectionEdges (Edge)

IGetNextSelectedFace (Face)

IGetProcessedBody (Body)

IGetProcessedBodyWithSelfFace (Body)

- IGetSheetBody (Body)
- IGetTessellation (Tessellation)
- IMatchedBoolean (EnumBodies)
- IOperations2 (EnumBodies)

SOLIDWORKS Type Library

Body Object Members

Public Methods

- [AddProfileArc](#)
- [AddProfileB spline](#)
- [AddProfileLine](#)
- [AddPropertyExtension](#)
- [AddVertexPoint](#)
- [Check](#)
- [Copy](#)
- [CreateBaseFeature](#)
- [CreateBlendSurface](#)
- [CreateBodyFromFaces](#)
- [CreateBodyFromSurfaces](#)
- [CreateBoundedSurface](#)
- [CreateB splineSurface](#)
- [CreateExtrusionSurface](#)
- [CreateNewSurface](#)
- [CreateOffsetSurface](#)
- [CreatePlanarSurface](#)
- [CreateRevolutionSurface](#)
- [CreateTempBodyFromSurfaces](#)
- [CreateTrimmedSurface](#)
- [DeleteBlends](#)
- [DeleteBlends2](#)
- [DeleteFaces](#)
- [DeleteFaces2](#)
- [Display](#)
- [DisplayWireFrameXOR](#)
- [DraftBody](#)
- [EnumFaces](#)
- [GetBodyBox](#)
- [GetEdgeCount](#)
- [GetExcessBodyArray](#)
- [GetExtremePoint](#)
- [GetFaceCount](#)
- [GetFirstFace](#)

	
	<u>GetFirstSelectedFace</u>
	<u>GetigesErrorCode</u>
	<u>GetigesErrorCount</u>
	<u>GetIntersectionEdges</u>
	<u>GetMassProperties</u>
	<u>GetMaterialIdName</u>
	<u>GetMaterialUserName</u>
	<u>GetNextSelectedFace</u>
	<u>GetProcessedBody</u>
	<u>GetProcessedBodyWithSelfFace</u>
	<u>GetPropertyExtension</u>
	<u>GetSelectedFaceCount</u>
	<u>GetSheetBody</u>
	<u>GetTessellation</u>
	<u>GetType</u>
	<u>Hide</u>
	<u>IAddProfileArc</u>
	<u>IAddProfileArcDLL</u>
	<u>IAddProfileB spline</u>
	<u>IAddProfileB splineDLL</u>
	<u>IAddProfileLine</u>
	<u>IAddProfileLineDLL</u>
	<u>IAddVertexPoint</u>
	<u>ICombineVolumes</u>
	<u>ICopy</u>
	<u>ICreateBaseFeature</u>
	<u>ICreateBlendSurface</u>
	<u>ICreateBodyFromFaces</u>
	<u>ICreateBoundedSurface</u>
	<u>ICreateB splineSurface</u>
	<u>ICreateB splineSurfaceDLL</u>
	<u>ICreateExtrusionSurface</u>
	<u>ICreateExtrusionSurfaceDLL</u>
	<u>ICreateNewSurface</u>
	<u>ICreateOffsetSurface</u>
	<u>ICreatePlanarSurface</u>
	<u>ICreatePlanarSurfaceDLL</u>
	<u>ICreatePlanarTrimSurfaceDLL</u>
	<u>ICreateP splineSurfaceDLL</u>
	<u>ICreateRevolutionSurface</u>
	<u>ICreateRevolutionSurfaceDLL</u>
	<u>ICreateTempBodyFromSurfaces</u>
	<u>IDeleteBlends</u>

	IDeleteBlends2
	IDeleteFaces2
	IDeleteFaces3
	IDisplay
	IDisplayWireFrameXOR
	IDraftBody
	IGetBodyBox
	IGetExcessBodyArray
	IGetExcessBodyCount
	IGetFirstFace
	IGetFirstSelectedFace
	IGetIntersectionEdgeCount
	IGetIntersectionEdges
	IGetMassProperties
	IGetNextSelectedFace
	IGetProcessedBody
	IGetProcessedBodyWithSelfFace
	IGetSheetBody
	IGetTessellation
	IHide
	IMatchedBoolean
	IOperations
	IOperations2
	IRemoveFacesFromSheet
	ISave
	ISectionBySheet
	ISetCurrentSurface
	ISetXform
	MatchedBoolean
	Operations
	Operations2
	RemoveFacesFromSheet
	RemoveRedundantTopology
	ResetPropertyExtension
	Save
	SetCurrentSurface
	SetigesInfo
	SetMaterialIdName
	SetMaterialUserName
	SetXform

Public Properties

	IMaterialPropertyValues
--	---



SOLIDWORKS Type Library

AddProfileArc Method (Body)



Visual Basic for Applications (VBA)

```
Public Function AddProfileArc( _  
    ByVal Center As Variant, _  
    ByVal Axis As Variant, _  
    ByVal Radius As Double, _  
    ByVal StartPoint As Variant, _  
    ByVal EndPoint As Variant _  
    ) As Object
```

SOLIDWORKS Type Library

AddProfileBspline Method (Body)



Visual Basic for Applications (VBA)

```
Public Function AddProfileBspline( _  
    ByVal Props As Variant, _  
    ByVal Knots As Variant, _  
    ByVal CtrlPtCoords As Variant _  
    ) As Object
```

SOLIDWORKS Type Library

AddProfileLine Method (Body)



Visual Basic for Applications (VBA)

```
Public Function AddProfileLine( _  
    ByVal RootPoint As Variant, _  
    ByVal Direction As Variant _  
    ) As Object
```

SOLIDWORKS Type Library

AddPropertyExtension Method (Body)



Visual Basic for Applications (VBA)

```
Public Function AddPropertyExtension( _  
    ByVal PropertyExtension As Variant _  
    ) As Long
```

SOLIDWORKS Type Library

AddVertexPoint Method (Body)



Visual Basic for Applications (VBA)

```
Public Function AddVertexPoint( _  
    ByVal Point As Variant _  
    ) As Object
```

SOLIDWORKS Type Library

Check Method (Body)



Visual Basic for Applications (VBA)

Public Function Check() As Long

SOLIDWORKS Type Library

Copy Method (Body)

 Syntax

Visual Basic for Applications (VBA)

Public Function Copy() As Object

SOLIDWORKS Type Library

CreateBaseFeature Method (Body)

 Syntax

Visual Basic for Applications (VBA)

```
Public Function CreateBaseFeature( _  
    ByVal BodyIn As Object _  
) As Boolean
```

SOLIDWORKS Type Library

CreateBlendSurface Method (Body)

 Syntax

Visual Basic for Applications (VBA)

```
Public Function CreateBlendSurface( _  
    ByVal Surface1 As Object, _  
    ByVal Range1 As Double, _  
    ByVal Surface2 As Object, _  
    ByVal Range2 As Double, _  
    ByVal StartVec As Variant, _  
    ByVal EndVec As Variant, _  
    ByVal HaveHelpVec As Integer, _  
    ByVal HelpVec As Variant, _  
    ByVal HaveHelpBox As Integer, _  
    ByVal HelpBox As Variant _  
) As Object
```

SOLIDWORKS Type Library

CreateBodyFromFaces Method (Body)

 Syntax

Visual Basic for Applications (VBA)

```
Public Function CreateBodyFromFaces( _  
    ByVal NumOfFaces As Long, _  
    ByVal FaceList As Variant _  
) As Object
```

SOLIDWORKS Type Library

CreateBodyFromSurfaces Method (Body)

 Syntax

Visual Basic for Applications (VBA)

Public Function CreateBodyFromSurfaces() As Boolean

SOLIDWORKS Type Library

CreateBoundedSurface Method (Body)

 Syntax

Visual Basic for Applications (VBA)

```
Public Function CreateBoundedSurface( _  
    ByVal UOpt As Boolean, _  
    ByVal VOpt As Boolean, _  
    ByVal UvParams As Variant _  
    ) As Boolean
```

SOLIDWORKS Type Library

CreateBsplineSurface Method (Body)

Syntax

Visual Basic for Applications (VBA)

```
Public Function CreateBsplineSurface( _  
    ByVal Props As Variant, _  
    ByVal UKnots As Variant, _  
    ByVal VKnots As Variant, _  
    ByVal CtrlPtCoords As Variant _  
    ) As Object
```

SOLIDWORKS Type Library

CreateExtrusionSurface Method (Body)

Syntax

Visual Basic for Applications (VBA)

```
Public Function CreateExtrusionSurface( _  
    ByVal ProfileCurve As Object, _  
    ByVal AxisDirection As Variant _  
    ) As Object
```

SOLIDWORKS Type Library

CreateNewSurface Method (Body)

Syntax

Visual Basic for Applications (VBA)

```
Public Function CreateNewSurface() As Object
```

SOLIDWORKS Type Library

CreateOffsetSurface Method (Body)

Syntax

Visual Basic for Applications (VBA)

```
Public Function CreateOffsetSurface( _  
    ByVal SurfaceIn As Object, _  
    ByVal Distance As Double _  
    ) As Object
```

SOLIDWORKS Type Library

CreatePlanarSurface Method (Body)

Syntax

Visual Basic for Applications (VBA)

```
Public Function CreatePlanarSurface( _  
    ByVal VRootPoint As Variant, _  
    ByVal VNormal As Variant _  
    ) As Object
```

SOLIDWORKS Type Library

CreateRevolutionSurface Method (Body)

Syntax

Visual Basic for Applications (VBA)

```
Public Function CreateRevolutionSurface( _  
    ByVal ProfileCurve As Object, _  
    ByVal AxisPoint As Variant, _  
    ByVal AxisDirection As Variant, _  
    ByVal ProfileEndPtParams As Variant _  
    ) As Object
```

SOLIDWORKS Type Library

CreateTempBodyFromSurfaces Method (Body)

Syntax

Visual Basic for Applications (VBA)

```
Public Function CreateTempBodyFromSurfaces() As Object
```

SOLIDWORKS Type Library

CreateTrimmedSurface Method (Body)

Syntax

Visual Basic for Applications (VBA)

```
Public Function CreateTrimmedSurface() As Boolean
```

SOLIDWORKS Type Library

DeleteBlends Method (Body)

Syntax

Visual Basic for Applications (VBA)

```
Public Function DeleteBlends( _  
    ByVal NumOfFaces As Long, _  
    ByVal FaceList As Variant _  
    ) As Boolean
```

SOLIDWORKS Type Library

DeleteBlends2 Method (Body)

Syntax

Visual Basic for Applications (VBA)

```
Public Function DeleteBlends2( _  
    ByVal NumOfFaces As Long, _  
    ByVal FaceList As Variant, _  
    ByVal DoLocalCheck As Boolean _  
    ) As Boolean
```

SOLIDWORKS Type Library

DeleteFaces Method (Body)

Syntax

Visual Basic for Applications (VBA)

```
Public Function DeleteFaces( _  
    ByVal NumOfFaces As Long, _  
    ByVal FaceList As Variant _  
    ) As Boolean
```

SOLIDWORKS Type Library

DeleteFaces2 Method (Body)

Syntax

Visual Basic for Applications (VBA)

```
Public Function DeleteFaces2( _  
    ByVal NumOfFaces As Long, _
```

```
    ByVal FaceList As Variant, _  
    ByVal Option As Integer _  
) As Long
```

SOLIDWORKS Type Library

Display Method (Body)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub Display( _  
    ByVal Part As Object, _  
    ByVal Color As Long _  
)
```

SOLIDWORKS Type Library

DisplayWireFrameXOR Method (Body)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub DisplayWireFrameXOR( _  
    ByVal Part As Object, _  
    ByVal Color As Long _  
)
```

SOLIDWORKS Type Library

DraftBody Method (Body)

Syntax

Visual Basic for Applications (VBA)

```
Public Function DraftBody( _  
    ByVal NumOfFaces As Long, _  
    ByVal FaceList As Variant, _  
    ByVal EdgeList As Variant, _  
    ByVal DraftAngle As Double, _  
    ByVal Dir As Variant _  
) As Boolean
```

SOLIDWORKS Type Library

EnumFaces Method (Body)

Syntax

Visual Basic for Applications (VBA)

```
Public Function EnumFaces() As EnumFaces
```

SOLIDWORKS Type Library

GetBodyBox Method (Body)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetBodyBox() As Variant
```

SOLIDWORKS Type Library

GetEdgeCount Method (Body)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetEdgeCount() As Long
```

SOLIDWORKS Type Library

GetExcessBodyArray Method (Body)



Visual Basic for Applications (VBA)

```
Public Function GetExcessBodyArray() As Variant
```

SOLIDWORKS Type Library

GetExtremePoint Method (Body)



Visual Basic for Applications (VBA)

```
Public Function GetExtremePoint( _  
    ByVal X As Double, _  
    ByVal Y As Double, _  
    ByVal Z As Double, _  
    ByRef Outx As Double, _  
    ByRef Outy As Double, _  
    ByRef Outz As Double _  
) As Boolean
```

SOLIDWORKS Type Library

GetFaceCount Method (Body)



Visual Basic for Applications (VBA)

```
Public Function GetFaceCount() As Long
```

SOLIDWORKS Type Library

GetFirstFace Method (Body)



Visual Basic for Applications (VBA)

```
Public Function GetFirstFace() As Object
```

SOLIDWORKS Type Library

GetFirstSelectedFace Method (Body)



Visual Basic for Applications (VBA)

```
Public Function GetFirstSelectedFace() As Object
```

SOLIDWORKS Type Library

GetIgesErrorCode Method (Body)



Visual Basic for Applications (VBA)

```
Public Function GetIgesErrorCode( _  
    ByVal Index As Long _  
) As Long
```

SOLIDWORKS Type Library

GetIgesErrorCount Method (Body)



Visual Basic for Applications (VBA)

```
Public Function GetIgesErrorCount() As Long
```

SOLIDWORKS Type Library

GetIntersectionEdges Method (Body)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetIntersectionEdges( _  
    ByVal ToolBodyIn As Object _  
) As Variant
```

SOLIDWORKS Type Library

GetMassProperties Method (Body)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetMassProperties( _  
    ByVal Density As Double _  
) As Variant
```

SOLIDWORKS Type Library

GetMaterialIdName Method (Body)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetMaterialIdName() As String
```

SOLIDWORKS Type Library

GetMaterialUserName Method (Body)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetMaterialUserName() As String
```

SOLIDWORKS Type Library

GetNextSelectedFace Method (Body)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetNextSelectedFace() As Object
```

SOLIDWORKS Type Library

GetProcessedBody Method (Body)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetProcessedBody() As Object
```

SOLIDWORKS Type Library

GetProcessedBodyWithSelFace Method (Body)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetProcessedBodyWithSelFace() As Object
```

SOLIDWORKS Type Library

GetPropertyExtension Method (Body)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetPropertyExtension( _  
    ByVal ID As Long _  
    ) As Variant
```

SOLIDWORKS Type Library

GetSelectedFaceCount Method (Body)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetSelectedFaceCount() As Long
```

SOLIDWORKS Type Library

GetSheetBody Method (Body)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetSheetBody( _  
    ByVal Index As Integer _  
    ) As Object
```

SOLIDWORKS Type Library

GetTessellation Method (Body)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetTessellation( _  
    ByVal FaceList As Variant _  
    ) As Object
```

SOLIDWORKS Type Library

GetType Method (Body)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetType() As Long
```

SOLIDWORKS Type Library

Hide Method (Body)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub Hide( _  
    ByVal Part As Object _  
    )
```

SOLIDWORKS Type Library

IAddProfileArc Method (Body)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IAddProfileArc( _  
    ByVal Center As Variant, _  
    ByVal Axis As Variant, _  
    ByVal Radius As Double, _  
    ByVal StartPoint As Variant, _  
    ByVal EndPoint As Variant _  
    ) As Curve
```

IAddProfileArcDLL Method (Body)**Syntax**

Visual Basic for Applications (VBA)

```
Public Function IAddProfileArcDLL( _  
    ByRef Center As Double, _  
    ByRef Axis As Double, _  
    ByVal Radius As Double, _  
    ByRef StartPoint As Double, _  
    ByRef EndPoint As Double _  
) As Curve
```

IAddProfileBspline Method (Body)**Syntax**

Visual Basic for Applications (VBA)

```
Public Function IAddProfileBspline( _  
    ByVal Props As Variant, _  
    ByVal Knots As Variant, _  
    ByVal CtrlPtCoords As Variant _  
) As Curve
```

IAddProfileBsplineDLL Method (Body)**Syntax**

Visual Basic for Applications (VBA)

```
Public Function IAddProfileBsplineDLL( _  
    ByRef Properties As Long, _  
    ByRef KnotArray As Double, _  
    ByRef ControlPointCoordArray As Double _  
) As Curve
```

IAddProfileLine Method (Body)**Syntax**

Visual Basic for Applications (VBA)

```
Public Function IAddProfileLine( _  
    ByVal RootPoint As Variant, _  
    ByVal Direction As Variant _  
) As Curve
```

IAddProfileLineDLL Method (Body)**Syntax**

Visual Basic for Applications (VBA)

```
Public Function IAddProfileLineDLL( _  
    ByRef RootPoint As Double, _  
    ByRef Direction As Double _  
) As Curve
```

IAddVertexPoint Method (Body)**Syntax**

Visual Basic for Applications (VBA)

```
Public Function IAddVertexPoint( _  
    ByRef Point As Double _  
) As Vertex
```

SOLIDWORKS Type Library

ICombineVolumes Method (Body)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub ICombineVolumes( _  
    ByVal ToolBody As Body _  
)
```

SOLIDWORKS Type Library

ICopy Method (Body)

Syntax

Visual Basic for Applications (VBA)

```
Public Function ICopy() As Body
```

SOLIDWORKS Type Library

ICreateBaseFeature Method (Body)

Syntax

Visual Basic for Applications (VBA)

```
Public Function ICreateBaseFeature( _  
    ByVal BodyIn As Body _  
) As Boolean
```

SOLIDWORKS Type Library

ICreateBlendSurface Method (Body)

Syntax

Visual Basic for Applications (VBA)

```
Public Function ICreateBlendSurface( _  
    ByVal Surface1 As Surface, _  
    ByVal Range1 As Double, _  
    ByVal Surface2 As Surface, _  
    ByVal Range2 As Double, _  
    ByRef StartVec As Double, _  
    ByRef EndVec As Double, _  
    ByVal HaveHelpVec As Integer, _  
    ByRef HelpVec As Double, _  
    ByVal HaveHelpBox As Integer, _  
    ByRef HelpBox As Double _  
) As Surface
```

SOLIDWORKS Type Library

ICreateBodyFromFaces Method (Body)

Syntax

Visual Basic for Applications (VBA)

```
Public Function ICreateBodyFromFaces( _  
    ByVal NumOfFaces As Long, _  
    ByVal FaceList As Variant _  
) As Body
```

SOLIDWORKS Type Library

ICreateBoundedSurface Method (Body)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub ICreateBoundedSurface( _  
    ByVal UOpt As Boolean, _  
    ByVal VOpt As Boolean, _  
    ByRef UvParams As Double _  
)
```

SOLIDWORKS Type Library

ICreateBsplineSurface Method (Body)

Syntax

Visual Basic for Applications (VBA)

```
Public Function ICreateBsplineSurface( _  
    ByVal Props As Variant, _  
    ByVal UKnots As Variant, _  
    ByVal VKnots As Variant, _  
    ByVal CtrlPtCoords As Variant _  
) As Surface
```

SOLIDWORKS Type Library

ICreateBsplineSurfaceDLL Method (Body)

Syntax

Visual Basic for Applications (VBA)

```
Public Function ICreateBsplineSurfaceDLL( _  
    ByRef Properties As Long, _  
    ByRef UKnotArray As Double, _  
    ByRef VKnotArray As Double, _  
    ByRef ControlPointCoordArray As Double _  
) As Surface
```

SOLIDWORKS Type Library

ICreateExtrusionSurface Method (Body)

Syntax

Visual Basic for Applications (VBA)

```
Public Function ICreateExtrusionSurface( _  
    ByVal ProfileCurve As Curve, _  
    ByVal AxisDirection As Variant _  
) As Surface
```

SOLIDWORKS Type Library

ICreateExtrusionSurfaceDLL Method (Body)

Syntax

Visual Basic for Applications (VBA)

```
Public Function ICreateExtrusionSurfaceDLL( _  
    ByVal ProfileCurve As Curve, _  
    ByRef AxisDirection As Double _  
) As Surface
```

SOLIDWORKS Type Library

ICreateNewSurface Method (Body)

Syntax

Visual Basic for Applications (VBA)

```
Public Function ICreateNewSurface() As Surface
```

SOLIDWORKS Type Library

ICreateOffsetSurface Method (Body)

Syntax

Visual Basic for Applications (VBA)

```
Public Function ICreateOffsetSurface( _  
    ByVal SurfaceIn As Surface, _  
    ByVal Distance As Double _  
) As Surface
```

SOLIDWORKS Type Library

ICreatePlanarSurface Method (Body)

Syntax

Visual Basic for Applications (VBA)

```
Public Function ICreatePlanarSurface( _  
    ByVal VRootPoint As Variant, _  
    ByVal VNormal As Variant _  
) As Surface
```

SOLIDWORKS Type Library

ICreatePlanarSurfaceDLL Method (Body)

Syntax

Visual Basic for Applications (VBA)

```
Public Function ICreatePlanarSurfaceDLL( _  
    ByRef RootPoint As Double, _  
    ByRef Normal As Double _  
) As Surface
```

SOLIDWORKS Type Library

ICreatePlanarTrimSurfaceDLL Method (Body)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub ICreatePlanarTrimSurfaceDLL( _  
    ByVal VertexCount As Long, _  
    ByRef Points As Double, _  
    ByRef Normal As Double _  
)
```

SOLIDWORKS Type Library

ICreatePsplineSurfaceDLL Method (Body)

Syntax

Visual Basic for Applications (VBA)

```
Public Function ICreatePsplineSurfaceDLL( _  
    ByVal Dim As Long, _  
    ByVal UOrder As Long, _  
    ByVal VOrder As Long, _  
    ByVal Ncol As Long, _  
    ByVal Nrow As Long, _  
    ByRef Coeffs As Double, _  
    ByVal Basis As Long, _  
    ByRef Xform As Double, _  
    ByVal ScaleFactor As Double _  
) As Surface
```

SOLIDWORKS Type Library

ICreateRevolutionSurface Method (Body)

Syntax

Visual Basic for Applications (VBA)

```
Public Function ICreateRevolutionSurface( _  
    ByVal ProfileCurve As Curve, _  
    ByVal AxisPoint As Variant, _  
    ByVal AxisDirection As Variant, _  
    ByVal ProfileEndPtParams As Variant _  
    ) As Surface
```

SOLIDWORKS Type Library

ICreateRevolutionSurfaceDLL Method (Body)

Syntax

Visual Basic for Applications (VBA)

```
Public Function ICreateRevolutionSurfaceDLL( _  
    ByVal ProfileCurve As Curve, _  
    ByRef AxisPoint As Double, _  
    ByRef AxisDirection As Double, _  
    ByRef ProfileEndPtParams As Double _  
    ) As Surface
```

SOLIDWORKS Type Library

ICreateTempBodyFromSurfaces Method (Body)

Syntax

Visual Basic for Applications (VBA)

```
Public Function ICreateTempBodyFromSurfaces() As Body
```

SOLIDWORKS Type Library

IDeleteBlends Method (Body)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IDeleteBlends( _  
    ByVal NumOfFaces As Long, _  
    ByVal FaceList As Face _  
    ) As Boolean
```

SOLIDWORKS Type Library

IDeleteBlends2 Method (Body)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IDeleteBlends2( _  
    ByVal NumOfFaces As Long, _  
    ByVal FaceList As Face, _  
    ByVal DoLocalCheck As Boolean _  
    ) As Boolean
```

SOLIDWORKS Type Library

IDeleteFaces2 Method (Body)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IDeleteFaces2( _  
    ByVal NumOfFaces As Long, _  
    ByVal FaceList As Face, _  
    ByVal Option As Integer _  
    ) As Long
```

SOLIDWORKS Type Library

IDeleteFaces3 Method (Body)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub IDeleteFaces3( _  
    ByVal NumOfFaces As Long, _  
    ByVal FaceList As Face, _  
    ByVal Option As Long, _  
    ByVal DoLocalCheck As Boolean, _  
    ByRef LocalCheckResult As Boolean _  
)
```

SOLIDWORKS Type Library

IDisplay Method (Body)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub IDisplay( _  
    ByVal Part As PartDoc, _  
    ByVal Color As Long _  
)
```

SOLIDWORKS Type Library

IDisplayWireFrameXOR Method (Body)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub IDisplayWireFrameXOR( _  
    ByVal Part As PartDoc, _  
    ByVal Color As Long _  
)
```

SOLIDWORKS Type Library

IDraftBody Method (Body)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IDraftBody( _  
    ByVal NumOfFaces As Long, _  
    ByVal FaceList As Face, _  
    ByVal EdgeList As Edge, _  
    ByVal DraftAngle As Double, _  
    ByRef Dir As Double _  
) As Boolean
```

SOLIDWORKS Type Library

IGetBodyBox Method (Body)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub IGetBodyBox( _  
    ByRef BoxCorners As Double _  
)
```

SOLIDWORKS Type Library

IGetExcessBodyArray Method (Body)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IGetExcessBodyArray() As Body
```

SOLIDWORKS Type Library

IGetExcessBodyCount Method (Body)



Visual Basic for Applications (VBA)

```
Public Function IGetExcessBodyCount() As Integer
```

SOLIDWORKS Type Library

IGetFirstFace Method (Body)



Visual Basic for Applications (VBA)

```
Public Function IGetFirstFace() As Face
```

SOLIDWORKS Type Library

IGetFirstSelectedFace Method (Body)



Visual Basic for Applications (VBA)

```
Public Function IGetFirstSelectedFace() As Face
```

SOLIDWORKS Type Library

IGetIntersectionEdgeCount Method (Body)



Visual Basic for Applications (VBA)

```
Public Function IGetIntersectionEdgeCount( _  
    ByVal ToolBodyIn As Body _  
    ) As Long
```

SOLIDWORKS Type Library

IGetIntersectionEdges Method (Body)



Visual Basic for Applications (VBA)

```
Public Function IGetIntersectionEdges( _  
    ByVal ToolBodyIn As Body _  
    ) As Edge
```

SOLIDWORKS Type Library

IGetMassProperties Method (Body)



Visual Basic for Applications (VBA)

```
Public Function IGetMassProperties( _  
    ByVal Density As Double _  
    ) As Double
```

SOLIDWORKS Type Library

IGetNextSelectedFace Method (Body)



Visual Basic for Applications (VBA)

```
Public Function IGetNextSelectedFace() As Face
```

SOLIDWORKS Type Library

IGetProcessedBody Method (Body)



```
Public Function IGetProcessedBody() As Body
```

SOLIDWORKS Type Library

IGetProcessedBodyWithSelFace Method (Body)

Syntax

```
Public Function IGetProcessedBodyWithSelFace() As Body
```

SOLIDWORKS Type Library

IGetSheetBody Method (Body)

Syntax

```
Public Function IGetSheetBody( _  
    ByVal Index As Integer _  
) As Body
```

SOLIDWORKS Type Library

IGetTessellation Method (Body)

Syntax

```
Public Function IGetTessellation( _  
    ByVal NumOfFaces As Long, _  
    ByVal FaceList As Face _  
) As Tessellation
```

SOLIDWORKS Type Library

IHide Method (Body)

Syntax

```
Public Sub IHide( _  
    ByVal Part As PartDoc _  
)
```

SOLIDWORKS Type Library

IMatchedBoolean Method (Body)

Syntax

```
Public Function IMatchedBoolean( _  
    ByVal OperationType As Integer, _  
    ByVal ToolBody As Body, _  
    ByVal NumOfMatchingFaces As Long, _  
    ByVal FaceList1 As Face, _  
    ByVal FaceList2 As Face, _  
    ByRef ErrorCode As Long _  
) As EnumBodies
```

SOLIDWORKS Type Library

IMaterialPropertyValues Property (Body)

Syntax

```
Public Property IMaterialPropertyValues As Double
```

IOperations Method (Body) **Syntax**

Visual Basic for Applications (VBA)

```
Public Function IOperations( _  
    ByVal OperationType As Integer, _  
    ByVal ToolBody As Body, _  
    ByVal NumMaxSections As Long, _  
    ByVal ResultingBodies As Body _  
) As Long
```

IOperations2 Method (Body) **Syntax**

Visual Basic for Applications (VBA)

```
Public Function IOperations2( _  
    ByVal OperationType As Integer, _  
    ByVal ToolBody As Body, _  
    ByRef ErrorCode As Long _  
) As EnumBodies
```

IRemoveFacesFromSheet Method (Body) **Syntax**

Visual Basic for Applications (VBA)

```
Public Sub IRemoveFacesFromSheet( _  
    ByVal NumOfFaces As Long, _  
    ByVal FacesToRemove As Face _  
)
```

ISave Method (Body) **Syntax**

Visual Basic for Applications (VBA)

```
Public Sub ISave( _  
    ByVal StreamIn As Unknown _  
)
```

ISectionBySheet Method (Body) **Syntax**

Visual Basic for Applications (VBA)

```
Public Function ISectionBySheet( _  
    ByVal Sheet As Body, _  
    ByVal NumMaxSections As Long, _  
    ByVal SectionedBodies As Body _  
) As Long
```

ISetCurrentSurface Method (Body) **Syntax**

Visual Basic for Applications (VBA)

```
Public Sub ISetCurrentSurface( _  
    ByVal SurfaceIn As Surface _
```

)

SOLIDWORKS Type Library

ISetXform Method (Body)

Syntax

Visual Basic for Applications (VBA)

```
Public Function ISetXform( _  
    ByRef XformIn As Double _  
) As Boolean
```

SOLIDWORKS Type Library

MatchedBoolean Method (Body)

Syntax

Visual Basic for Applications (VBA)

```
Public Function MatchedBoolean( _  
    ByVal OperationType As Integer, _  
    ByVal ToolBody As Object, _  
    ByVal NumOfMatchingFaces As Long, _  
    ByVal FaceList1 As Variant, _  
    ByVal FaceList2 As Variant, _  
    ByRef ErrorCode As Long _  
) As Variant
```

SOLIDWORKS Type Library

MaterialPropertyValues Property (Body)

Syntax

Visual Basic for Applications (VBA)

```
Public Property MaterialPropertyValues As Variant
```

SOLIDWORKS Type Library

Operations Method (Body)

Syntax

Visual Basic for Applications (VBA)

```
Public Function Operations( _  
    ByVal OperationType As Integer, _  
    ByVal ToolBody As Object, _  
    ByVal NumMaxSections As Long _  
) As Variant
```

SOLIDWORKS Type Library

Operations2 Method (Body)

Syntax

Visual Basic for Applications (VBA)

```
Public Function Operations2( _  
    ByVal OperationType As Integer, _  
    ByVal ToolBody As Object, _  
    ByRef ErrorCode As Long _  
) As Variant
```

SOLIDWORKS Type Library

RemoveFacesFromSheet Method (Body)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub RemoveFacesFromSheet( _  
    ByVal NumOfFaces As Long, _  
    ByVal FacesToRemove As Variant _  
)
```

SOLIDWORKS Type Library

RemoveRedundantTopology Method (Body)

Syntax

Visual Basic for Applications (VBA)

```
Public Function RemoveRedundantTopology() As Boolean
```

SOLIDWORKS Type Library

ResetPropertyExtension Method (Body)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub ResetPropertyExtension()
```

SOLIDWORKS Type Library

Save Method (Body)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub Save( _  
    ByVal StreamIn As Unknown _  
)
```

SOLIDWORKS Type Library

SetCurrentSurface Method (Body)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub SetCurrentSurface( _  
    ByVal SurfaceIn As Object _  
)
```

SOLIDWORKS Type Library

SetIgesInfo Method (Body)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub SetIgesInfo( _  
    ByVal SystemName As String, _  
    ByVal Granularity As Double, _  
    ByVal AttemptKnitting As Boolean _  
)
```

SOLIDWORKS Type Library

SetMaterialIdName Method (Body)

Syntax

Visual Basic for Applications (VBA)

```
Public Function SetMaterialIdName( _  
    ByVal Name As String _  
) As Boolean
```

SOLIDWORKS Type Library

SetMaterialUserName Method (Body)



Syntax

Visual Basic for Applications (VBA)

```
Public Function SetMaterialUserName( _  
    ByVal Name As String _  
) As Boolean
```

SOLIDWORKS Type Library

SetXform Method (Body)



Syntax

Visual Basic for Applications (VBA)

```
Public Function SetXform( _  
    ByVal XformIn As Variant _  
) As Boolean
```

SOLIDWORKS Type Library

Visible Property (Body)



Syntax

Visual Basic for Applications (VBA)

```
Public Property Visible As Boolean
```