

SOLIDWORKS API (VB6 COM) — Reference (79/102): RevolveFeatureData2- SecondaryMemberBetweenPointsFeatureData

SOLIDWORKS API Documentation (converted from CHM)

RevolveFeatureData2 (Type)

SOLIDWORKS Type Library

RevolveFeatureData2 Object

 Object Model

RevolveFeatureData2

IGetFeatureScopeBodies (Body2)

SOLIDWORKS Type Library

RevolveFeatureData2 Object Members

 Public Methods

	AccessSelections
	GetAxisType
	GetContoursCount
	GetFeatureScopeBodiesCount
	GetRevolutionAngle
	GetWallThickness
	IAccessSelections
	IGetContours
	IGetFeatureScopeBodies
	IsBossFeature
	ISetContours
	ISetFeatureScopeBodies
	IsThinFeature
	ReleaseSelectionAccess
	SetRevolutionAngle
	SetWallThickness

 Public Properties

	AssemblyFeatureScope
	AutoSelect
	AutoSelectComponents
	Axis
	Contours
	FeatureScope
	FeatureScopeBodies
	Merge
	PropagateFeatureToParts
	ReverseDirection
	ThinWallType
	Type

SOLIDWORKS Type Library

AccessSelections Method (RevolveFeatureData2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function AccessSelections( _  
    ByVal TopDoc As Object, _  
    ByVal Component As Object _  
    ) As Boolean
```

SOLIDWORKS Type Library

AssemblyFeatureScope Property (RevolveFeatureData2)

Syntax

Visual Basic for Applications (VBA)

```
Public Property AssemblyFeatureScope As Boolean
```

SOLIDWORKS Type Library

AutoSelect Property (RevolveFeatureData2)

Syntax

Visual Basic for Applications (VBA)

```
Public Property AutoSelect As Boolean
```

SOLIDWORKS Type Library

AutoSelectComponents Property (RevolveFeatureData2)

Syntax

Visual Basic for Applications (VBA)

```
Public Property AutoSelectComponents As Boolean
```

SOLIDWORKS Type Library

Axis Property (RevolveFeatureData2)

Syntax

Visual Basic for Applications (VBA)

```
Public Property Axis As Object
```

SOLIDWORKS Type Library

Contours Property (RevolveFeatureData2)

Syntax

Visual Basic for Applications (VBA)

```
Public Property Contours As Variant
```

SOLIDWORKS Type Library

FeatureScope Property (RevolveFeatureData2)

Syntax

Visual Basic for Applications (VBA)

```
Public Property FeatureScope As Boolean
```

SOLIDWORKS Type Library

FeatureScopeBodies Property (RevolveFeatureData2)

Syntax

Visual Basic for Applications (VBA)

Public Property FeatureScopeBodies As Variant

SOLIDWORKS Type Library

GetAxisType Method (RevolveFeatureData2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetAxisType() As Long
```

SOLIDWORKS Type Library

GetContoursCount Method (RevolveFeatureData2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetContoursCount() As Long
```

SOLIDWORKS Type Library

GetFeatureScopeBodiesCount Method (RevolveFeatureData2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetFeatureScopeBodiesCount() As Long
```

SOLIDWORKS Type Library

GetRevolutionAngle Method (RevolveFeatureData2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetRevolutionAngle( _  
    ByVal Forward As Boolean _  
) As Double
```

SOLIDWORKS Type Library

GetWallThickness Method (RevolveFeatureData2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetWallThickness( _  
    ByVal Forward As Boolean _  
) As Double
```

SOLIDWORKS Type Library

IAccessSelections Method (RevolveFeatureData2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IAccessSelections( _  
    ByVal TopDoc As ModelDoc2, _  
    ByVal Component As Component2 _  
) As Boolean
```

SOLIDWORKS Type Library

IGetContours Method (RevolveFeatureData2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IGetContours( _  
    ByVal Count As Long _  
) As Object
```

SOLIDWORKS Type Library

IGetFeatureScopeBodies Method (RevolveFeatureData2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IGetFeatureScopeBodies( _  
    ByVal Count As Long _  
) As Body2
```

SOLIDWORKS Type Library

IsBossFeature Method (RevolveFeatureData2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IsBossFeature() As Boolean
```

SOLIDWORKS Type Library

ISetContours Method (RevolveFeatureData2)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub ISetContours( _  
    ByVal Count As Long, _  
    ByRef Contours As Object _  
)
```

SOLIDWORKS Type Library

ISetFeatureScopeBodies Method (RevolveFeatureData2)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub ISetFeatureScopeBodies( _  
    ByVal Count As Long, _  
    ByVal BodyArr As Body2 _  
)
```

SOLIDWORKS Type Library

IsThinFeature Method (RevolveFeatureData2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IsThinFeature() As Boolean
```

SOLIDWORKS Type Library

Merge Property (RevolveFeatureData2)

Syntax

Visual Basic for Applications (VBA)

```
Public Property Merge As Boolean
```

SOLIDWORKS Type Library

PropagateFeatureToParts Property (RevolveFeatureData2)

Syntax

Visual Basic for Applications (VBA)

Public Property PropagateFeatureToParts As Boolean

SOLIDWORKS Type Library

ReleaseSelectionAccess Method (RevolveFeatureData2)



Visual Basic for Applications (VBA)

Public Sub ReleaseSelectionAccess()

SOLIDWORKS Type Library

ReverseDirection Property (RevolveFeatureData2)



Visual Basic for Applications (VBA)

Public Property ReverseDirection As Boolean

SOLIDWORKS Type Library

SetRevolutionAngle Method (RevolveFeatureData2)



Visual Basic for Applications (VBA)

```
Public Sub SetRevolutionAngle( _  
    ByVal Forward As Boolean, _  
    ByVal Angle As Double _  
)
```

SOLIDWORKS Type Library

SetWallThickness Method (RevolveFeatureData2)



Visual Basic for Applications (VBA)

```
Public Sub SetWallThickness( _  
    ByVal Forward As Boolean, _  
    ByVal WallThickness As Double _  
)
```

SOLIDWORKS Type Library

ThinWallType Property (RevolveFeatureData2)



Visual Basic for Applications (VBA)

Public Property ThinWallType As Long

SOLIDWORKS Type Library

Type Property (RevolveFeatureData2)



Visual Basic for Applications (VBA)

Public Property Type As Integer

RibFeatureData (Type)

SOLIDWORKS Type Library

RibFeatureData Object

Object Model

RibFeatureData

SOLIDWORKS Type Library

RibFeatureData Object Members

Public Methods

NextReference

Public Properties

DraftAngle

DraftOutward

EnableDraft

FlipSide

IsTwoSided

RefSketchIndex

ReverseThicknessDir

Thickness

SOLIDWORKS Type Library

DraftAngle Property (RibFeatureData)

Syntax

Visual Basic for Applications (VBA)

Public Property DraftAngle As Double

SOLIDWORKS Type Library

DraftOutward Property (RibFeatureData)

Syntax

Visual Basic for Applications (VBA)

Public Property DraftOutward As Boolean

SOLIDWORKS Type Library

EnableDraft Property (RibFeatureData)

Syntax

Visual Basic for Applications (VBA)

Public Property EnableDraft As Boolean

SOLIDWORKS Type Library

FlipSide Property (RibFeatureData)

Syntax

Visual Basic for Applications (VBA)

Public Property FlipSide As Boolean

SOLIDWORKS Type Library

IsTwoSided Property (RibFeatureData)



Visual Basic for Applications (VBA)

```
Public Property IsTwoSided As Boolean
```

SOLIDWORKS Type Library

NextReference Method (RibFeatureData)



Visual Basic for Applications (VBA)

```
Public Function NextReference() As Integer
```

SOLIDWORKS Type Library

RefSketchIndex Property (RibFeatureData)



Visual Basic for Applications (VBA)

```
Public Property RefSketchIndex As Integer
```

SOLIDWORKS Type Library

ReverseThicknessDir Property (RibFeatureData)



Visual Basic for Applications (VBA)

```
Public Property ReverseThicknessDir As Boolean
```

SOLIDWORKS Type Library

Thickness Property (RibFeatureData)




Visual Basic for Applications (VBA)

```
Public Property Thickness As Double
```

RibFeatureData2 (Type)

SOLIDWORKS Type Library
RibFeatureData2 Object



SOLIDWORKS Type Library
RibFeatureData2 Object Members

Public Methods

- [AccessSelections](#)
- [IAccessSelections](#)
- [NextReference](#)
- [ReleaseSelectionAccess](#)

Public Properties

- [Body](#)
- [DraftAngle](#)
- [DraftFromWall](#)
- [DraftOutward](#)
- [EnableDraft](#)
- [ExtrusionDirection](#)
- [FlipSide](#)
- [IsTwoSided](#)
- [RefSketchIndex](#)
- [ReverseThicknessDir](#)
- [Thickness](#)
- [Type](#)

SOLIDWORKS Type Library
AccessSelections Method (RibFeatureData2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function AccessSelections( _  
    ByVal TopDoc As Object, _  
    ByVal Component As Object _  
) As Boolean
```

SOLIDWORKS Type Library
Body Property (RibFeatureData2)

Syntax

Visual Basic for Applications (VBA)

```
Public Property Body As Body2
```

SOLIDWORKS Type Library

DraftAngle Property (RibFeatureData2)

Syntax

Visual Basic for Applications (VBA)

```
Public Property DraftAngle As Double
```

SOLIDWORKS Type Library

DraftFromWall Property (RibFeatureData2)

Syntax

Visual Basic for Applications (VBA)

```
Public Property DraftFromWall As Boolean
```

SOLIDWORKS Type Library

DraftOutward Property (RibFeatureData2)

Syntax

Visual Basic for Applications (VBA)

```
Public Property DraftOutward As Boolean
```

SOLIDWORKS Type Library

EnableDraft Property (RibFeatureData2)

Syntax

Visual Basic for Applications (VBA)

```
Public Property EnableDraft As Boolean
```

SOLIDWORKS Type Library

ExtrusionDirection Property (RibFeatureData2)

Syntax

Visual Basic for Applications (VBA)

```
Public Property ExtrusionDirection As Long
```

SOLIDWORKS Type Library

FlipSide Property (RibFeatureData2)

Syntax

Visual Basic for Applications (VBA)

```
Public Property FlipSide As Boolean
```

SOLIDWORKS Type Library

IAccessSelections Method (RibFeatureData2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IAccessSelections( _  
    ByVal TopDoc As ModelDoc2, _  
    ByVal Component As Component2 _  
) As Boolean
```

SOLIDWORKS Type Library

IsTwoSided Property (RibFeatureData2)

Syntax

Visual Basic for Applications (VBA)

Public Property IsTwoSided As Boolean

SOLIDWORKS Type Library

NextReference Method (RibFeatureData2)



Visual Basic for Applications (VBA)

Public Function NextReference() As Integer

SOLIDWORKS Type Library

RefSketchIndex Property (RibFeatureData2)



Visual Basic for Applications (VBA)

Public Property RefSketchIndex As Integer

SOLIDWORKS Type Library

ReleaseSelectionAccess Method (RibFeatureData2)



Visual Basic for Applications (VBA)

Public Sub ReleaseSelectionAccess()

SOLIDWORKS Type Library

ReverseThicknessDir Property (RibFeatureData2)



Visual Basic for Applications (VBA)

Public Property ReverseThicknessDir As Boolean

SOLIDWORKS Type Library

Thickness Property (RibFeatureData2)



Visual Basic for Applications (VBA)

Public Property Thickness As Double

SOLIDWORKS Type Library

Type Property (RibFeatureData2)



Visual Basic for Applications (VBA)

Public Property Type As Long

RipFeatureData (Type)

SOLIDWORKS Type Library

RipFeatureData Object

Object Model

RipFeatureData

SOLIDWORKS Type Library

RipFeatureData Object Members

Public Methods

 AccessSelections
 GetDirection
 GetEdgesCount
 IAccessSelections
 IGetEdges
 ISetEdges
 ReleaseSelectionAccess
 SetDirection

Public Properties

 Edges
 Gap

SOLIDWORKS Type Library

AccessSelections Method (RipFeatureData)

Syntax

```
Visual Basic for Applications (VBA)

Public Function AccessSelections( _
    ByVal TopDoc As Object, _
    ByVal Component As Object _
) As Boolean
```

SOLIDWORKS Type Library

Edges Property (RipFeatureData)

Syntax

```
Visual Basic for Applications (VBA)

Public Property Edges As Variant
```

SOLIDWORKS Type Library

Gap Property (RipFeatureData)

Syntax

```
Visual Basic for Applications (VBA)

Public Property Gap As Double
```

SOLIDWORKS Type Library

GetDirection Method (RipFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetDirection( _  
    ByVal Edge As Object _  
    ) As Long
```

SOLIDWORKS Type Library

GetEdgesCount Method (RipFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetEdgesCount() As Long
```

SOLIDWORKS Type Library

IAccessSelections Method (RipFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IAccessSelections( _  
    ByVal TopDoc As ModelDoc2, _  
    ByVal Component As Component2 _  
    ) As Boolean
```

SOLIDWORKS Type Library

IGetEdges Method (RipFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IGetEdges( _  
    ByVal EdgeCount As Long _  
    ) As Object
```

SOLIDWORKS Type Library

ISetEdges Method (RipFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub ISetEdges( _  
    ByVal EdgeCount As Long, _  
    ByRef EdgeArr As Object _  
    )
```

SOLIDWORKS Type Library

ReleaseSelectionAccess Method (RipFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub ReleaseSelectionAccess()
```

SOLIDWORKS Type Library

SetDirection Method (RipFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub SetDirection( _  
    ByVal Edge As Object, _  
    ByVal Dir As Long _  
    )
```

RoutingSettings (Type)

SOLIDWORKS Type Library
RoutingSettings Object

Object Model

RoutingSettings

SOLIDWORKS Type Library
RoutingSettings Object Members

Public Methods

	GetFromToListHeaderDefinitions
	GetRoutingUserPreferenceDoubleValue
	GetRoutingUserPreferenceIntegerValue
	GetRoutingUserPreferenceStringValue
	GetRoutingUserPreferenceToggle
	LoadDefaultRoutingSettings
	LoadRoutingSettingsFromFile
	SaveRoutingSettingsToFile
	SetFromToListHeaderDefinitions
	SetRoutingUserPreferenceDoubleValue
	SetRoutingUserPreferenceIntegerValue
	SetRoutingUserPreferenceStringValue
	SetRoutingUserPreferenceToggle

SOLIDWORKS Type Library
GetFromToListHeaderDefinitions Method (RoutingSettings)

Syntax

```
Visual Basic for Applications (VBA)

Public Function GetFromToListHeaderDefinitions( _
    ByRef WireNameHdr As String, _
    ByRef FromRefHdr As String, _
    ByRef FromPinHdr As String, _
    ByRef FromPartnoHdr As String, _
    ByRef ToRefHdr As String, _
    ByRef ToPinHdr As String, _
    ByRef ToPartnoHdr As String, _
    ByRef CableNameHdr As String, _
    ByRef CoreNameHdr As String, _
    ByRef ColourHdr As String, _
    ByRef WireSpecHdr As String, _
    ByRef OtherAttribHdr As String _
) As Boolean
```

SOLIDWORKS Type Library
GetRoutingUserPreferenceDoubleValue Method (RoutingSettings)

Syntax

```
Visual Basic for Applications (VBA)

Public Function GetRoutingUserPreferenceDoubleValue( _
    ByVal UserPreferenceValue As Long _
```

) As Double

SOLIDWORKS Type Library

GetRoutingUserPreferenceIntegerValue Method (RoutingSettings)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetRoutingUserPreferenceIntegerValue( _  
    ByVal UserPreferenceValue As Long _  
) As Long
```

SOLIDWORKS Type Library

GetRoutingUserPreferenceStringValue Method (RoutingSettings)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetRoutingUserPreferenceStringValue( _  
    ByVal UserPreference As Long, _  
    ByVal UseDefaultVal As Boolean _  
) As String
```

SOLIDWORKS Type Library

GetRoutingUserPreferenceToggle Method (RoutingSettings)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetRoutingUserPreferenceToggle( _  
    ByVal UserPreferenceToggle As Long _  
) As Boolean
```

SOLIDWORKS Type Library

LoadDefaultRoutingSettings Method (RoutingSettings)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub LoadDefaultRoutingSettings()
```

SOLIDWORKS Type Library

LoadRoutingSettingsFromFile Method (RoutingSettings)

Syntax

Visual Basic for Applications (VBA)

```
Public Function LoadRoutingSettingsFromFile( _  
    ByVal RoutingSettingsFilename As String _  
) As Boolean
```

SOLIDWORKS Type Library

SaveRoutingSettingsToFile Method (RoutingSettings)

Syntax

Visual Basic for Applications (VBA)

```
Public Function SaveRoutingSettingsToFile( _  
    ByVal RoutingSettingsFilename As String _  
) As Boolean
```

SOLIDWORKS Type Library

SetFromToListHeaderDefinitions Method (RoutingSettings)

Syntax

```
Public Function SetFromToListHeaderDefinitions( _
    ByVal WireNameHdr As String, _
    ByVal FromRefHdr As String, _
    ByVal FromPinHdr As String, _
    ByVal FromPartnoHdr As String, _
    ByVal ToRefHdr As String, _
    ByVal ToPinHdr As String, _
    ByVal ToPartnoHdr As String, _
    ByVal CableNameHdr As String, _
    ByVal CoreNameHdr As String, _
    ByVal ColourHdr As String, _
    ByVal WireSpecHdr As String, _
    ByVal OtherAttribHdr As String _
) As Boolean
```

SetRoutingUserPreferenceDoubleValue Method (RoutingSettings)

```
Public Function SetRoutingUserPreferenceDoubleValue( _
    ByVal UserPreferenceValue As Long, _
    ByVal Value As Double _
) As Boolean
```

SetRoutingUserPreferenceIntegerValue Method (RoutingSettings)

```
Public Function SetRoutingUserPreferenceIntegerValue( _
    ByVal UserPreferenceValue As Long, _
    ByVal Value As Long _
) As Boolean
```

SetRoutingUserPreferenceStringValue Method (RoutingSettings)

```
Public Function SetRoutingUserPreferenceStringValue( _
    ByVal UserPreference As Long, _
    ByVal Value As String _
) As Boolean
```

SetRoutingUserPreferenceToggle Method (RoutingSettings)

```
Public Sub SetRoutingUserPreferenceToggle( _
    ByVal UserPreferenceValue As Long, _
    ByVal OnFlag As Boolean _
)
```

RuledSurfaceFeatureData (Type)

SOLIDWORKS Type Library

RuledSurfaceFeatureData Object

Object Model

RuledSurfaceFeatureData

DirectionVector (MathVector)

SOLIDWORKS Type Library

RuledSurfaceFeatureData Object Members

Public Methods

	AccessSelections
	GetDirectionReference
	GetEdges
	GetEdgesCount
	IGetEdges
	ISetEdges
	ReleaseSelectionAccess
	SetDirectionReference
	SetEdges

Public Properties

	Angle
	Connect
	DirectionVector
	Distance
	TrimAndKrit
	Type
	UseVector

SOLIDWORKS Type Library

AccessSelections Method (RuledSurfaceFeatureData)

Syntax

```
Visual Basic for Applications (VBA)

Public Function AccessSelections( _
    ByVal TopDoc As ModelDoc2, _
    ByVal Component As Component2 _
) As Boolean
```

SOLIDWORKS Type Library

Angle Property (RuledSurfaceFeatureData)

Syntax

```
Visual Basic for Applications (VBA)

Public Property Angle As Double
```

SOLIDWORKS Type Library

Connect Property (RuledSurfaceFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Property Connect As Boolean
```

SOLIDWORKS Type Library

DirectionVector Property (RuledSurfaceFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Property DirectionVector As MathVector
```

SOLIDWORKS Type Library

Distance Property (RuledSurfaceFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Property Distance As Double
```

SOLIDWORKS Type Library

GetDirectionReference Method (RuledSurfaceFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetDirectionReference( _  
    ByRef Ref1 As Object, _  
    ByRef Type1 As Long, _  
    ByRef Ref2 As Object, _  
    ByRef Type2 As Long _  
    ) As Long
```

SOLIDWORKS Type Library

GetEdges Method (RuledSurfaceFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub GetEdges( _  
    ByRef Edges As Variant, _  
    ByRef SideFlags As Variant _  
    )
```

SOLIDWORKS Type Library

GetEdgesCount Method (RuledSurfaceFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetEdgesCount() As Long
```

SOLIDWORKS Type Library

IGetEdges Method (RuledSurfaceFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub IGetEdges( _  
    ByVal Count As Long, _  
    ByRef Entities As Object, _
```

```
ByRef SideFlags As Long _  
)
```

SOLIDWORKS Type Library

ISetEdges Method (RuledSurfaceFeatureData)

 Syntax

Visual Basic for Applications (VBA)

```
Public Sub ISetEdges( _  
    ByVal Count As Long, _  
    ByRef Entities As Object, _  
    ByRef SideFlags As Long _  
)
```

SOLIDWORKS Type Library

ReleaseSelectionAccess Method (RuledSurfaceFeatureData)

 Syntax

Visual Basic for Applications (VBA)

```
Public Sub ReleaseSelectionAccess()
```

SOLIDWORKS Type Library

SetDirectionReference Method (RuledSurfaceFeatureData)

 Syntax

Visual Basic for Applications (VBA)

```
Public Sub SetDirectionReference( _  
    ByVal Ref1 As Object, _  
    ByVal Ref2 As Object _  
)
```

SOLIDWORKS Type Library

SetEdges Method (RuledSurfaceFeatureData)

 Syntax

Visual Basic for Applications (VBA)

```
Public Sub SetEdges( _  
    ByVal Edges As Variant, _  
    ByVal SideFlags As Variant _  
)
```

SOLIDWORKS Type Library

TrimAndKnit Property (RuledSurfaceFeatureData)

 Syntax

Visual Basic for Applications (VBA)

```
Public Property TrimAndKnit As Boolean
```

SOLIDWORKS Type Library

Type Property (RuledSurfaceFeatureData)

 Syntax

Visual Basic for Applications (VBA)

```
Public Property Type As Long
```

SOLIDWORKS Type Library

UseVector Property (RuledSurfaceFeatureData)

 Syntax

Public Property UseVector As Boolean

SafeArrayUtility (Type)

SOLIDWORKS Type Library
SafeArrayUtility Object

Object Model

SafeArrayUtility

SOLIDWORKS Type Library
SafeArrayUtility Object Members

Public Methods

	GetBoolean
	GetBstr
	GetByte
	GetDispatch
	GetDouble
	GetInfo
	GetLong
	GetLongLong
	GetShort
	GetUNKNOWN
	PackVariant
	PutBoolean
	PutBstr
	PutByte
	PutDispatch
	PutDouble
	PutLong
	PutLongLong
	PutShort
	PutUNKNOWN
	UnPackVariant

SOLIDWORKS Type Library
GetBoolean Method (SafeArrayUtility)

Syntax

```
Visual Basic for Applications (VBA)

Public Function GetBoolean( _
    ByVal VariantArray As Variant, _
    ByVal Index As Long _
) As Boolean
```

SOLIDWORKS Type Library
GetBstr Method (SafeArrayUtility)

Syntax

```
Visual Basic for Applications (VBA)
```

```
Public Function GetBstr( _  
    ByVal VariantArray As Variant, _  
    ByVal Index As Long _  
    ) As String
```

SOLIDWORKS Type Library

GetByte Method (SafeArrayUtility)



Syntax

Visual Basic for Applications (VBA)

```
Public Function GetByte( _  
    ByVal VariantArray As Variant, _  
    ByVal Index As Long _  
    ) As Byte
```

SOLIDWORKS Type Library

GetDispatch Method (SafeArrayUtility)



Syntax

Visual Basic for Applications (VBA)

```
Public Function GetDispatch( _  
    ByVal VariantArray As Variant, _  
    ByVal Index As Long _  
    ) As Object
```

SOLIDWORKS Type Library

GetDouble Method (SafeArrayUtility)



Syntax

Visual Basic for Applications (VBA)

```
Public Function GetDouble( _  
    ByVal VariantArray As Variant, _  
    ByVal Index As Long _  
    ) As Double
```

SOLIDWORKS Type Library

GetInfo Method (SafeArrayUtility)



Syntax

Visual Basic for Applications (VBA)

```
Public Sub GetInfo( _  
    ByVal VariantArray As Variant, _  
    ByRef Count As Long, _  
    ByRef Type As Long _  
    )
```

SOLIDWORKS Type Library

GetLong Method (SafeArrayUtility)



Syntax

Visual Basic for Applications (VBA)

```
Public Function GetLong( _  
    ByVal VariantArray As Variant, _  
    ByVal Index As Long _  
    ) As Long
```

SOLIDWORKS Type Library

GetLongLong Method (SafeArrayUtility)



Syntax

Visual Basic for Applications (VBA)

```
Public Function GetLongLong( _  
    ByVal VariantArray As Variant, _  
    ByVal Index As Long _  
    ) As Unknown
```

SOLIDWORKS Type Library

GetShort Method (SafeArrayUtility)



Visual Basic for Applications (VBA)

```
Public Function GetShort( _  
    ByVal VariantArray As Variant, _  
    ByVal Index As Long _  
    ) As Integer
```

SOLIDWORKS Type Library

GetUNKNOWN Method (SafeArrayUtility)



Visual Basic for Applications (VBA)

```
Public Function GetUNKNOWN( _  
    ByVal VariantArray As Variant, _  
    ByVal Index As Long _  
    ) As Unknown
```

SOLIDWORKS Type Library

PackVariant Method (SafeArrayUtility)



Visual Basic for Applications (VBA)

```
Public Sub PackVariant( _  
    ByRef VariantArray As Variant, _  
    ByVal Count As Long, _  
    ByVal Type As Long, _  
    ByRef Data As Long _  
    )
```

SOLIDWORKS Type Library

PutBoolean Method (SafeArrayUtility)



Visual Basic for Applications (VBA)

```
Public Sub PutBoolean( _  
    ByRef VariantArray As Variant, _  
    ByVal Index As Long, _  
    ByVal Value As Boolean _  
    )
```

SOLIDWORKS Type Library

PutBstr Method (SafeArrayUtility)



Visual Basic for Applications (VBA)

```
Public Sub PutBstr( _  
    ByRef VariantArray As Variant, _  
    ByVal Index As Long, _  
    ByVal Value As String _  
    )
```

SOLIDWORKS Type Library

PutByte Method (SafeArrayUtility)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub PutByte( _  
    ByRef VariantArray As Variant, _  
    ByVal Index As Long, _  
    ByVal Value As Byte _  
)
```

SOLIDWORKS Type Library

PutDispatch Method (SafeArrayUtility)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub PutDispatch( _  
    ByRef VariantArray As Variant, _  
    ByVal Index As Long, _  
    ByVal Value As Object _  
)
```

SOLIDWORKS Type Library

PutDouble Method (SafeArrayUtility)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub PutDouble( _  
    ByRef VariantArray As Variant, _  
    ByVal Index As Long, _  
    ByVal Value As Double _  
)
```

SOLIDWORKS Type Library

PutLong Method (SafeArrayUtility)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub PutLong( _  
    ByRef VariantArray As Variant, _  
    ByVal Index As Long, _  
    ByVal Value As Long _  
)
```

SOLIDWORKS Type Library

PutLongLong Method (SafeArrayUtility)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub PutLongLong( _  
    ByRef VariantArray As Variant, _  
    ByVal Index As Long, _  
    ByVal Value As Unknown _  
)
```

SOLIDWORKS Type Library

PutShort Method (SafeArrayUtility)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub PutShort( _  
    ByRef VariantArray As Variant, _  
    ByVal Index As Long, _  
    ByVal Value As Integer _  
)
```

SOLIDWORKS Type Library

PutUNKNOWN Method (SafeArrayUtility)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub PutUNKNOWN( _  
    ByRef VariantArray As Variant, _  
    ByVal Index As Long, _  
    ByVal Value As Unknown _  
)
```

SOLIDWORKS Type Library

UnPackVariant Method (SafeArrayUtility)

Syntax

Visual Basic for Applications (VBA)

```
Public Function UnPackVariant( _  
    ByVal VariantArray As Variant, _  
    ByVal Count As Long _  
) As Long
```

SaveBodyFeatureData (Type)

SOLIDWORKS Type Library
SaveBodyFeatureData Object

Object Model

SaveBodyFeatureData

SOLIDWORKS Type Library
SaveBodyFeatureData Object Members

Public Methods

 AccessSelections
 AddSaveBodies
 GetSaveBodies
 GetSaveBodiesCount
 ReleaseSelectionAccess
 RemoveSaveBodies

Public Properties

 AssemblyPath
 ConsumeBody
 CopyCustomProperties

SOLIDWORKS Type Library
AccessSelections Method (SaveBodyFeatureData)

Syntax

```
Visual Basic for Applications (VBA)

Public Function AccessSelections( _
    ByVal TopDoc As ModelDoc2, _
    ByVal Component As Component2 _
) As Boolean
```

SOLIDWORKS Type Library
AddSaveBodies Method (SaveBodyFeatureData)

Syntax

```
Visual Basic for Applications (VBA)

Public Function AddSaveBodies( _
    ByVal Bodies As Variant, _
    ByVal FilePaths As Variant _
) As Boolean
```

SOLIDWORKS Type Library
AssemblyPath Property (SaveBodyFeatureData)

Syntax

```
Visual Basic for Applications (VBA)

Public Property AssemblyPath As String
```

SOLIDWORKS Type Library
ConsumeBody Property (SaveBodyFeatureData)



Visual Basic for Applications (VBA)

```
Public Property ConsumeBody As Boolean
```

SOLIDWORKS Type Library

CopyCustomProperties Property (SaveBodyFeatureData)



Visual Basic for Applications (VBA)

```
Public Property CopyCustomProperties As Boolean
```

SOLIDWORKS Type Library

GetSaveBodies Method (SaveBodyFeatureData)



Visual Basic for Applications (VBA)

```
Public Sub GetSaveBodies( _  
    ByRef Bodies As Variant, _  
    ByRef FilePaths As Variant, _  
    ByRef Flags As Variant _  
)
```

SOLIDWORKS Type Library

GetSaveBodiesCount Method (SaveBodyFeatureData)



Visual Basic for Applications (VBA)

```
Public Function GetSaveBodiesCount() As Long
```

SOLIDWORKS Type Library

ReleaseSelectionAccess Method (SaveBodyFeatureData)



Visual Basic for Applications (VBA)

```
Public Sub ReleaseSelectionAccess()
```

SOLIDWORKS Type Library

RemoveSaveBodies Method (SaveBodyFeatureData)



Visual Basic for Applications (VBA)

```
Public Function RemoveSaveBodies( _  
    ByVal Bodies As Variant _  
) As Boolean
```

SaveTo3DExperienceOptions (Type)

SOLIDWORKS Type Library
SaveTo3DExperienceOptions Object

Object Model

SaveTo3DExperienceOptions

SOLIDWORKS Type Library
SaveTo3DExperienceOptions Object Members

Public Methods

SetRevisionComments

Public Properties

FileName

SOLIDWORKS Type Library
FileName Property (SaveTo3DExperienceOptions)

Syntax

Visual Basic for Applications (VBA)

```
Public Property FileName As String
```

SOLIDWORKS Type Library
SetRevisionComments Method (SaveTo3DExperienceOptions)


Syntax

Visual Basic for Applications (VBA)

```
Public Function SetRevisionComments( _  
    ByVal RevisionComments As String _  
) As Boolean
```

ScaleFeatureData (Type)

SOLIDWORKS Type Library
ScaleFeatureData Object



SOLIDWORKS Type Library
ScaleFeatureData Object Members

Public Methods

 AccessSelections
 GetBodiesCount
 GetScale
 IAccessSelections
 IGetBodies
 ISetBodies
 ReleaseSelectionAccess
 SetScale

Public Properties

 Bodies
 CoordinateSystem
 IsUniform
 ScaleUniform
 ScaleX
 ScaleY
 ScaleZ
 Type

SOLIDWORKS Type Library
AccessSelections Method (ScaleFeatureData)

Syntax

```
Visual Basic for Applications (VBA)

Public Function AccessSelections( _
    ByVal TopDoc As Object, _
    ByVal Component As Object _
) As Boolean
```

SOLIDWORKS Type Library
Bodies Property (ScaleFeatureData)

Syntax

```
Visual Basic for Applications (VBA)

Public Property Bodies As Variant
```

CoordinateSystem Property (ScaleFeatureData) **Syntax**

Visual Basic for Applications (VBA)

```
Public Property CoordinateSystem As Object
```

GetBodiesCount Method (ScaleFeatureData) **Syntax**

Visual Basic for Applications (VBA)

```
Public Function GetBodiesCount() As Long
```

GetScale Method (ScaleFeatureData) **Syntax**

Visual Basic for Applications (VBA)

```
Public Sub GetScale( _  
    ByRef X As Double, _  
    ByRef Y As Double, _  
    ByRef Z As Double, _  
    ByRef Uniform As Boolean _  
)
```

IAccessSelections Method (ScaleFeatureData) **Syntax**

Visual Basic for Applications (VBA)

```
Public Function IAccessSelections( _  
    ByVal TopDoc As ModelDoc2, _  
    ByVal Component As Component2 _  
) As Boolean
```

IGetBodies Method (ScaleFeatureData) **Syntax**

Visual Basic for Applications (VBA)

```
Public Function IGetBodies( _  
    ByVal Count As Long _  
) As Body2
```

ISetBodies Method (ScaleFeatureData) **Syntax**

Visual Basic for Applications (VBA)

```
Public Sub ISetBodies( _  
    ByVal Count As Long, _  
    ByVal BodyArr As Body2 _  
)
```

IsUniform Property (ScaleFeatureData) **Syntax**

Visual Basic for Applications (VBA)

Public Property IsUniform As Boolean

SOLIDWORKS Type Library

ReleaseSelectionAccess Method (ScaleFeatureData)

 Syntax

Visual Basic for Applications (VBA)

```
Public Sub ReleaseSelectionAccess()
```

SOLIDWORKS Type Library

ScaleUniform Property (ScaleFeatureData)

 Syntax

Visual Basic for Applications (VBA)

```
Public Property ScaleUniform As Double
```

SOLIDWORKS Type Library

ScaleX Property (ScaleFeatureData)

 Syntax

Visual Basic for Applications (VBA)

```
Public Property ScaleX As Double
```

SOLIDWORKS Type Library

ScaleY Property (ScaleFeatureData)

 Syntax

Visual Basic for Applications (VBA)

```
Public Property ScaleY As Double
```

SOLIDWORKS Type Library

ScaleZ Property (ScaleFeatureData)

 Syntax

Visual Basic for Applications (VBA)

```
Public Property ScaleZ As Double
```

SOLIDWORKS Type Library

SetScale Method (ScaleFeatureData)

 Syntax

Visual Basic for Applications (VBA)

```
Public Sub SetScale( _  
    ByVal X As Double, _  
    ByVal Y As Double, _  
    ByVal Z As Double, _  
    ByVal Uniform As Boolean _  
)
```

SOLIDWORKS Type Library

Type Property (ScaleFeatureData)

 Syntax

Visual Basic for Applications (VBA)

```
Public Property Type As Long
```

ScrewMateFeatureData (Type)

SOLIDWORKS Type Library
ScrewMateFeatureData Object

Object Model

ScrewMateFeatureData

SOLIDWORKS Type Library
ScrewMateFeatureData Object Members

Public Properties

- EntitiesToMate
- MateAlignment
- Reverse
- RevolutionType
- RevolutionVal

SOLIDWORKS Type Library
EntitiesToMate Property (ScrewMateFeatureData)

Syntax

Visual Basic for Applications (VBA)

Public Property EntitiesToMate As Variant

SOLIDWORKS Type Library
MateAlignment Property (ScrewMateFeatureData)

Syntax

Visual Basic for Applications (VBA)

Public Property MateAlignment As Long

SOLIDWORKS Type Library
Reverse Property (ScrewMateFeatureData)

Syntax

Visual Basic for Applications (VBA)

Public Property Reverse As Boolean

SOLIDWORKS Type Library
RevolutionType Property (ScrewMateFeatureData)

Syntax

Visual Basic for Applications (VBA)

Public Property RevolutionType As Long

SOLIDWORKS Type Library
RevolutionVal Property (ScrewMateFeatureData)

Syntax

Visual Basic for Applications (VBA)

Public Property RevolutionVal As Double

SecondaryMemberBetweenPointsFeatureData (Type)

SOLIDWORKS Type Library

SecondaryMemberBetweenPointsFeatureData Object

Object Model

SecondaryMemberBetweenPointsFeatureData

SOLIDWORKS Type Library

SecondaryMemberBetweenPointsFeatureData Object Members

Public Methods

GetMemberPairs

SetMemberPairs

Public Properties

DistanceMember1

DistanceMember2

LengthRatioMember1

LengthRatioMember2

RevDirectionDistanceMember1

RevDirectionDistanceMember2

RevDirectionLengthRatioMember1

RevDirectionLengthRatioMember2

SecondaryMemberOffsetType

UnChainMemberPairs

SOLIDWORKS Type Library

DistanceMember1 Property (SecondaryMemberBetweenPointsFeatureData)

Syntax

Visual Basic for Applications (VBA)

Public Property DistanceMember1 As Double

SOLIDWORKS Type Library

DistanceMember2 Property (SecondaryMemberBetweenPointsFeatureData)

Syntax

Visual Basic for Applications (VBA)

Public Property DistanceMember2 As Double

SOLIDWORKS Type Library

GetMemberPairs Method (SecondaryMemberBetweenPointsFeatureData)

Syntax

Visual Basic for Applications (VBA)

Public Function GetMemberPairs() As Variant

SOLIDWORKS Type Library

LengthRatioMember1 Property (SecondaryMemberBetweenPointsFeatureData)



Visual Basic for Applications (VBA)

```
Public Property LengthRatioMember1 As Double
```

SOLIDWORKS Type Library

LengthRatioMember2 Property (SecondaryMemberBetweenPointsFeatureData)



Visual Basic for Applications (VBA)

```
Public Property LengthRatioMember2 As Double
```

SOLIDWORKS Type Library

RevDirectionDistanceMember1 Property (SecondaryMemberBetweenPointsFeatureData)



Visual Basic for Applications (VBA)

```
Public Property RevDirectionDistanceMember1 As Boolean
```

SOLIDWORKS Type Library

RevDirectionDistanceMember2 Property (SecondaryMemberBetweenPointsFeatureData)



Visual Basic for Applications (VBA)

```
Public Property RevDirectionDistanceMember2 As Boolean
```

SOLIDWORKS Type Library

RevDirectionLengthRatioMember1 Property (SecondaryMemberBetweenPointsFeatureData)



Visual Basic for Applications (VBA)

```
Public Property RevDirectionLengthRatioMember1 As Boolean
```

SOLIDWORKS Type Library

RevDirectionLengthRatioMember2 Property (SecondaryMemberBetweenPointsFeatureData)



Visual Basic for Applications (VBA)

```
Public Property RevDirectionLengthRatioMember2 As Boolean
```

SOLIDWORKS Type Library

SecondaryMemberOffsetType Property (SecondaryMemberBetweenPointsFeatureData)



Visual Basic for Applications (VBA)

```
Public Property SecondaryMemberOffsetType As Long
```

SOLIDWORKS Type Library

SetMemberPairs Method (SecondaryMemberBetweenPointsFeatureData)



Visual Basic for Applications (VBA)

```
Public Function SetMemberPairs( _  
    ByVal Pairs As Variant _  
) As Boolean
```

SOLIDWORKS Type Library



Syntax

Visual Basic for Applications (VBA)

```
Public Property UnChainMemberPairs As Boolean
```