

SOLIDWORKS API (VB6 COM) — Reference (98/102): View (part 1 of 3)

SOLIDWORKS API Documentation (converted from CHM)

View (part 1 of 3) (Type)

SOLIDWORKS Type Library

View Object

 Object Model

View

- EnumHiddenComponents (EnumComponents)
- EnumHiddenComponents2 (EnumComponents2)
- EnumSectionLines (EnumDrSections)
- EnumSectionLines2 (EnumDrSections)
- GetCenterLineSketch (Sketch)
- GetFirstAnnotation3 (Annotation)
- GetFirstBlockInstance (BlockInstance)
- GetFirstCenterLine (Centerline)
- GetFirstCenterMark (CenterMark)
- GetFirstDatumOrigin (DatumOrigin)
- GetFirstDisplayDimension4 (DisplayDimension)
- GetFirstDisplayDimension5 (DisplayDimension)
- GetFirstTableAnnotation (TableAnnotation)
- GetFirstWeldBead (WeldBead)
- IGetAnnotations (Annotation)
- IGetBaseView (View)
- IGetBendLines (SketchSegment)
- IGetBodies (Body2)
- IGetBomTable (BomTable)
- IGetBreakLines (BreakLine)
- IGetBreakOutSections (Feature)
- IGetCenterLines (Centerline)
- IGetCenterMarks (CenterMark)
- IGetCThreads (CThread)
- IGetDatumOrigins (DatumOrigin)
- IGetDatumTags (DatumTag)
- IGetDatumTargetSyms (DatumTargetSym)
- IGetDependentViews (View)
- IGetDetail (DetailCircle)
- IGetDetailCircles (DetailCircle)

IGetDisplayData (DisplayData)
IGetDisplayData2 (DisplayData)
IGetDisplayData3 (DisplayData)
IGetDisplayDimensions (DisplayDimension)
IGetDowelSymbols (DowelSymbol)
IGetFaceHatches (FaceHatch)
IGetFirstAnnotation (Annotation)
IGetFirstAnnotation2 (Annotation)
IGetFirstCenterOfMass (CenterOfMass)
IGetFirstCThread (CThread)
IGetFirstCustomSymbol (CustomSymbol)
IGetFirstDatumTag (DatumTag)
IGetFirstDatumTargetSym (DatumTargetSym)
IGetFirstDisplayDimension (DisplayDimension)
IGetFirstDisplayDimension2 (DisplayDimension)
IGetFirstDisplayDimension3 (DisplayDimension)
IGetFirstDowelSymbol (DowelSymbol)
IGetFirstGTOL (Gtol)
IGetFirstMultiJogLeader (MultiJogLeader)
IGetFirstNote (Note)
IGetFirstRevisionCloud (RevisionCloud)
IGetFirstSFSymbol (SFSymbol)
IGetFirstWeldSymbol (WeldSymbol)
IGetGTols (Gtol)
IGetHiddenEdges (Edge)
IGetMultiJogLeaders (MultiJogLeader)
IGetNextView (View)
IGetNotes (Note)
IGetPolylines6 (Edge)
IGetProjectionArrow (ProjectionArrow)
IGetProjectionLines (ProjectionArrow)
IGetProjectionLines2 (ProjectionArrow)

IGetRelatedTangentEdges (Edge)
IGetRevisionClouds (RevisionCloud)
IGetSection (DrSection)
IGetSectionLines (DrSection)
IGetSFSymbols (SFSymbol)
IGetSketch (Sketch)
IGetSketchPictures (SketchPicture)
IGetSMBoundingBoxDisplayData (DisplayData)
IGetTableAnnotations (TableAnnotation)
IGetVisibleComponents (Component2)
IGetVisibleEntities (Entity)
IGetVisibleEntities2 (Entity)
IGetWeldBeads (WeldBead)
IGetWeldSymbols (WeldSymbol)
IInsertBomTable (BomTable)
InsertAlternateView (View)
InsertBendTable (BendTableAnnotation)
InsertBomTable2 (BomTableAnnotation)
InsertBomTable3 (BomTableAnnotation)
InsertBomTable4 (BomTableAnnotation)
InsertBreak (BreakLine)
InsertBreak2 (BreakLine)
InsertHoleTable (HoleTableAnnotation)
InsertHoleTable2 (HoleTableAnnotation)
InsertPunchTable (PunchTableAnnotation)
InsertWeldmentTable (WeldmentCutListAnnotation)
ModelToViewTransform (MathTransform)
ReferencedDocument (ModelDoc2)
RootDrawingComponent (DrawingComponent)
RootDrawingComponent2 (DrawingComponent)
Sheet

**Public Methods**

	AlignDrawingView
	AlignHorizontalTo
	AlignVerticalTo
	AlignWithView
	AutoInsertCenterMarks
	AutoInsertCenterMarks2
	CreateViewArrow
	Crop
	Crop2
	EnumHiddenComponents
	EnumHiddenComponents2
	EnumSectionLines
	EnumSectionLines2
	GetAlignment
	GetAnnotationCount
	GetAnnotations
	GetAnnotationsByType
	GetArcCount
	GetArcs
	GetArcs2
	GetArcs3
	GetArcs4
	GetBaseView
	GetBendLineCount
	GetBendLines
	GetBendNoteAttributeString
	GetBendNoteTextFormat
	GetBodiesCount
	GetBomTable
	GetBreakLineCount
	GetBreakLineCount2
	GetBreakLineInfo
	GetBreakLineInfo2
	GetBreakLines
	GetBreakOutSectionCount
	GetBreakOutSections
	GetCenterLineCount
	GetCenterLines
	GetCenterLineSketch
	GetCenterMarkCount

	
	GetCenterMarkCount2
	GetCenterMarkInfo
	GetCenterMarks
	GetCorresponding
	GetCorrespondingEntity
	GetCThreadCount
	GetCThreadQuality
	GetCThreads
	GetDatumOriginCount
	GetDatumOrigins
	GetDatumPoints
	GetDatumPoints2
	GetDatumPointsCount
	GetDatumTagCount
	GetDatumTags
	GetDatumTargetSymCount
	GetDatumTargetSyms
	GetDependentViewCount
	GetDependentViews
	GetDesignTableExtent
	GetDetail
	GetDetailCircleCount
	GetDetailCircleCount2
	GetDetailCircleInfo
	GetDetailCircleInfo2
	GetDetailCircles
	GetDetailCircleStrings
	GetDimensionCount
	GetDimensionCount2
	GetDimensionCount3
	GetDimensionCount4
	GetDimensionDisplayInfo
	GetDimensionDisplayInfo2
	GetDimensionDisplayInfo3
	GetDimensionDisplayInfo4
	GetDimensionDisplayInfo5
	GetDimensionDisplayInfoSize
	GetDimensionDisplayInfoSize2
	GetDimensionDisplayString
	GetDimensionDisplayString2
	GetDimensionDisplayString3
	GetDimensionDisplayString4
	GetDimensionDisplayString5

	
	<u>GetDimensionIds</u>
	<u>GetDimensionIds2</u>
	<u>GetDimensionIds3</u>
	<u>GetDimensionIds4</u>
	<u>GetDimensionInfo</u>
	<u>GetDimensionInfo2</u>
	<u>GetDimensionInfo3</u>
	<u>GetDimensionInfo4</u>
	<u>GetDimensionInfo5</u>
	<u>GetDimensionInfo6</u>
	<u>GetDimensionInfo7</u>
	<u>GetDimensionString</u>
	<u>GetDimensionString2</u>
	<u>GetDimensionString3</u>
	<u>GetDimensionString4</u>
	<u>GetDisplayData</u>
	<u>GetDisplayData2</u>
	<u>GetDisplayData3</u>
	<u>GetDisplayData4</u>
	<u>GetDisplayDimensionCount</u>
	<u>GetDisplayDimensions</u>
	<u>GetDisplayEdgesInShadedMode</u>
	<u>GetDisplayMode</u>
	<u>GetDisplayMode2</u>
	<u>GetDisplayTangentEdges</u>
	<u>GetDisplayTangentEdges2</u>
	<u>GetDowelSymbolCount</u>
	<u>GetDowelSymbols</u>
	<u>GetEllipseCount</u>
	<u>GetEllipses</u>
	<u>GetEllipses2</u>
	<u>GetEllipses3</u>
	<u>GetEllipses4</u>
	<u>GetEllipses5</u>
	<u>GetFaceHatchCount</u>
	<u>GetFaceHatches</u>
	<u>GetFacettedHirDisplay</u>
	<u>GetFirstAnnotation</u>
	<u>GetFirstAnnotation2</u>
	<u>GetFirstAnnotation3</u>
	<u>GetFirstBlockInstance</u>
	<u>GetFirstCenterLine</u>
	<u>GetFirstCenterMark</u>

	
	<u>GetFirstCenterMark2</u>
	<u>GetFirstCenterOfMass</u>
	<u>GetFirstCThread</u>
	<u>GetFirstCustomSymbol</u>
	<u>GetFirstDatumOrigin</u>
	<u>GetFirstDatumTag</u>
	<u>GetFirstDatumTargetSym</u>
	<u>GetFirstDisplayDimension</u>
	<u>GetFirstDisplayDimension2</u>
	<u>GetFirstDisplayDimension3</u>
	<u>GetFirstDisplayDimension4</u>
	<u>GetFirstDisplayDimension5</u>
	<u>GetFirstDisplayDimension6</u>
	<u>GetFirstDowelSymbol</u>
	<u>GetFirstGTOL</u>
	<u>GetFirstMultiJogLeader</u>
	<u>GetFirstMultiJogLeader2</u>
	<u>GetFirstNote</u>
	<u>GetFirstNote2</u>
	<u>GetFirstRevisionCloud</u>
	<u>GetFirstRevisionCloud2</u>
	<u>GetFirstSFSymbol</u>
	<u>GetFirstTableAnnotation</u>
	<u>GetFirstTableAnnotation2</u>
	<u>GetFirstWeldBead</u>
	<u>GetFirstWeldSymbol</u>
	<u>GetGTolCount</u>
	<u>GetGTols</u>
	<u>GetHiddenComponents</u>
	<u>GetHiddenEdgeCount</u>
	<u>GetKeepLinkedToBOM</u>
	<u>GetKeepLinkedToBOMName</u>
	<u>GetLineCount</u>
	<u>GetLineCount2</u>
	<u>GetLines</u>
	<u>GetLines2</u>
	<u>GetLines3</u>
	<u>GetLines4</u>
	<u>GetMirrorViewOrientation</u>
	<u>GetMultiJogLeaderCount</u>
	<u>GetMultiJogLeaders</u>
	<u>GetName2</u>
	<u>GetNextView</u>

	
	GetNoteCount
	GetNotes
	GetOrientationName
	GetOutline
	GetParabolaCount
	GetParabolas
	GetParabolas2
	GetPolyLineCount
	GetPolyLineCount2
	GetPolyLineCount3
	GetPolyLineCount4
	GetPolyLineCount5
	GetPolylines
	GetPolylines2
	GetPolylines3
	GetPolylines4
	GetPolylines5
	GetPolylines6
	GetPolylines7
	GetPolyLinesAndCurves
	GetPolyLinesAndCurvesCount
	GetProjectionArrow
	GetProjectionLineCount
	GetProjectionLines
	GetReferencedModelName
	GetRelatedTangentEdgeCount
	GetRelatedTangentEdges
	GetRevisionCloudCount
	GetRevisionClouds
	GetSection
	GetSectionLineCount
	GetSectionLineCount2
	GetSectionLineInfo
	GetSectionLineInfo2
	GetSectionLines
	GetSectionLineStrings
	GetSFSymbolCount
	GetSFSymbols
	GetSketch
	GetSketchPictureCount
	GetSketchPictures
	GetSMBoundingBoxDisplayData
	GetSMBoundingBoxDisplayData2

	
	<u>GetSolidHatchCount</u>
	<u>GetSolidHatchInfo</u>
	<u>GetSplineCount</u>
	<u>GetSplines</u>
	<u>GetSplines2</u>
	<u>GetSplines3</u>
	<u>GetTableAnnotationCount</u>
	<u>GetTableAnnotations</u>
	<u>GetTemporaryAxes</u>
	<u>GetTemporaryAxesCount</u>
	<u>GetUniqueName</u>
	<u>GetUseParentDisplayMode</u>
	<u>GetUserPoints</u>
	<u>GetUserPoints2</u>
	<u>GetUserPointsCount</u>
	<u>GetViewXform</u>
	<u>GetVisible</u>
	<u>GetVisibleComponentCount</u>
	<u>GetVisibleComponents</u>
	<u>GetVisibleDrawingComponents</u>
	<u>GetVisibleEntities</u>
	<u>GetVisibleEntities2</u>
	<u>GetVisibleEntityCount</u>
	<u>GetVisibleEntityCount2</u>
	<u>GetWeldBeadCount</u>
	<u>GetWeldBeads</u>
	<u>GetWeldSymbolCount</u>
	<u>GetWeldSymbols</u>
	<u>GetWitnessEntitiesCount</u>
	<u>GetWitnessGeomInfo</u>
	<u>GetXform</u>
	<u>HasDesignTable</u>
	<u>IGetAnnotations</u>
	<u>IGetArcs</u>
	<u>IGetArcs2</u>
	<u>IGetArcs3</u>
	<u>IGetArcs4</u>
	<u>IGetBaseView</u>
	<u>IGetBendLines</u>
	<u>IGetBodies</u>
	<u>IGetBomTable</u>
	<u>IGetBreakLineInfo</u>
	<u>IGetBreakLineInfo2</u>

	
	<u>IGetBreakLines</u>
	<u>IGetBreakOutSections</u>
	<u>IGetCenterLines</u>
	<u>IGetCenterMarkInfo</u>
	<u>IGetCenterMarks</u>
	<u>IGetCThreads</u>
	<u>IGetDatumOrigins</u>
	<u>IGetDatumPoints</u>
	<u>IGetDatumPoints2</u>
	<u>IGetDatumTags</u>
	<u>IGetDatumTargetSyms</u>
	<u>IGetDependentViews</u>
	<u>IGetDesignTableExtent</u>
	<u>IGetDetail</u>
	<u>IGetDetailCircleInfo</u>
	<u>IGetDetailCircleInfo2</u>
	<u>IGetDetailCircles</u>
	<u>IGetDetailCircleStrings</u>
	<u>IGetDimensionDisplayInfo</u>
	<u>IGetDimensionDisplayInfo2</u>
	<u>IGetDimensionDisplayInfo3</u>
	<u>IGetDimensionDisplayInfo4</u>
	<u>IGetDimensionDisplayInfo5</u>
	<u>IGetDimensionDisplayString</u>
	<u>IGetDimensionDisplayString2</u>
	<u>IGetDimensionDisplayString3</u>
	<u>IGetDimensionDisplayString4</u>
	<u>IGetDimensionIds</u>
	<u>IGetDimensionIds2</u>
	<u>IGetDimensionIds3</u>
	<u>IGetDimensionIds4</u>
	<u>IGetDimensionInfo</u>
	<u>IGetDimensionInfo2</u>
	<u>IGetDimensionInfo3</u>
	<u>IGetDimensionInfo4</u>
	<u>IGetDimensionInfo5</u>
	<u>IGetDimensionInfo6</u>
	<u>IGetDimensionString</u>
	<u>IGetDimensionString2</u>
	<u>IGetDimensionString3</u>
	<u>IGetDimensionString4</u>
	<u>IGetDisplayData</u>
	<u>IGetDisplayData2</u>



[IGetDisplayData3](#)



[IGetDisplayDimensions](#)



[IGetDowelSymbols](#)



[IGetEllipses](#)



[IGetEllipses2](#)



[IGetEllipses3](#)



[IGetEllipses4](#)



[IGetEllipses5](#)



[IGetFaceHatches](#)



[IGetFirstAnnotation](#)



[IGetFirstAnnotation2](#)



[IGetFirstCenterOfMass](#)



[IGetFirstCThread](#)



[IGetFirstCustomSymbol](#)



[IGetFirstDatumTag](#)



[IGetFirstDatumTargetSym](#)



[IGetFirstDisplayDimension](#)



[IGetFirstDisplayDimension2](#)



[IGetFirstDisplayDimension3](#)



[IGetFirstDowelSymbol](#)



[IGetFirstGTOL](#)



[IGetFirstMultiJogLeader](#)



[IGetFirstNote](#)



[IGetFirstRevisionCloud](#)



[IGetFirstSFSymbol](#)



[IGetFirstWeldSymbol](#)



[IGetGTols](#)



[IGetHiddenEdges](#)



[IGetLines](#)



[IGetLines2](#)



[IGetLines3](#)



[IGetLines4](#)



[IGetMultiJogLeaders](#)



[IGetNextView](#)



[IGetNotes](#)



[IGetOutline](#)



[IGetParabolas](#)



[IGetParabolas2](#)



[IGetPolylines](#)



[IGetPolylines2](#)



[IGetPolylines3](#)



[IGetPolylines4](#)

[IGetPolylines5](#)

	
	<u>IGetPolylines6</u>
	<u>IGetPolylines7</u>
	<u>IGetPolyLinesAndCurves</u>
	<u>IGetProjectionArrow</u>
	<u>IGetProjectionLines</u>
	<u>IGetRelatedTangentEdges</u>
	<u>IGetRevisionClouds</u>
	<u>IGetSection</u>
	<u>IGetSectionLineInfo</u>
	<u>IGetSectionLineInfo2</u>
	<u>IGetSectionLines</u>
	<u>IGetSectionLineStrings</u>
	<u>IGetSF-Symbols</u>
	<u>IGetSketch</u>
	<u>IGetSketchPictures</u>
	<u>IGetSMBoundingBoxDisplayData</u>
	<u>IGetSolidHatchInfo</u>
	<u>IGetSplines</u>
	<u>IGetSplines2</u>
	<u>IGetSplines3</u>
	<u>IGetTableAnnotations</u>
	<u>IGetTemporaryAxes</u>
	<u>IGetUserPoints</u>
	<u>IGetUserPoints2</u>
	<u>IGetViewXform</u>
	<u>IGetVisibleComponents</u>
	<u>IGetVisibleEntities</u>
	<u>IGetVisibleEntities2</u>
	<u>IGetWeldBeads</u>
	<u>IGetWeldSymbols</u>
	<u>IGetWitnessGeomInfo</u>
	<u>IGetXform</u>
	<u>InsertBomTable</u>
	<u>ImportAnnotations</u>
	<u>InsertAlternateView</u>
	<u>InsertBendTable</u>
	<u>InsertBomTable</u>
	<u>InsertBomTable2</u>
	<u>InsertBomTable3</u>
	<u>InsertBomTable4</u>
	<u>InsertBomTable5</u>
	<u>InsertBomTable6</u>
	<u>InsertBreak</u>

	
 InsertBreak2	
 InsertBreak3	
 InsertCutListPropertyNote	
 InsertHoleTable	
 InsertHoleTable2	
 InsertHoleTable3	
 InsertPunchTable	
 InsertViewAsBlock	
 InsertWeldmentTable	
 InsertWeldTable	
 IsBroken	
 IsCropped	
 IsSelectEntity	
 IsSetBodies	
 IsSetHiddenEdges	
 IsSetXform	
 IsExploded	
 IsFlatPatternView	
 IsLightweight	
 IsModelBreakState	
 IsModelLoaded	
 IsModelOutOfDate	
 IsPerspectiveView	
 LoadModel	
 MergeBendTags	
 ModifyViewArrow	
 MoveViewArrow	
 RemoveAlignment	
 ReplaceViewWithBlock	
 ReplaceViewWithSketch	
 ResetSketchVisibility	
 SelectEntity	
 SetBendNoteTextFormat	
 SetDisplayMode	
 SetDisplayMode2	
 SetDisplayMode3	
 SetDisplayMode4	
 SetDisplayTangentEdges	
 SetDisplayTangentEdges2	
 SetKeepLinkedToBOM	
 SetLightweightToResolved	
 SetMirrorViewOrientation	
SetName2	

	SetResolvedToLightweight
	SetViewPosition
	SetVisible
	SetXform
	ShowExploded
	ShowModelBreakState
	UpdateViewDisplayGeometry
	UseDefaultAlignment

Public Properties

	Angle
	Bodies
	BreakLineGap
	CropViewJaggedOutline
	CropViewJaggedShapeIntensity
	CropViewNoOutline
	DisableAutoUpdate
	DisplayState
	EmphasizeOutline
	FlipView
	FocusLocked
	HiddenEdges
	IPosition
	IScaleRatio
	LinkParentConfiguration
	ModelToViewTransform
	Name
	Position
	PositionLocked
	ProjectedDimensions
	ReferencedConfiguration
	ReferencedConfigurationID
	ReferencedDocument
	RootDrawingComponent
	RootDrawingComponent2
	ScaleDecimal
	ScaleHatchPattern
	ScaleRatio
	Sheet
	ShowSheetMetalBendNotes
	SuppressState
	Type
	UseParentScale



SOLIDWORKS Type Library

AlignDrawingView Method (View)

Syntax

Visual Basic for Applications (VBA)

```
Public Function AlignDrawingView( _  
    ByVal AlignViewType As Long _  
) As Boolean
```

SOLIDWORKS Type Library

AlignHorizontalTo Method (View)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub AlignHorizontalTo( _  
    ByVal ViewNameIn As String _  
)
```

SOLIDWORKS Type Library

AlignVerticalTo Method (View)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub AlignVerticalTo( _  
    ByVal ViewNameIn As String _  
)
```

SOLIDWORKS Type Library

AlignWithView Method (View)

Syntax

Visual Basic for Applications (VBA)

```
Public Function AlignWithView( _  
    ByVal AlignType As Long, _  
    ByVal BaseView As View _  
) As Boolean
```

SOLIDWORKS Type Library

Angle Property (View)

Syntax

Visual Basic for Applications (VBA)

```
Public Property Angle As Double
```

SOLIDWORKS Type Library

AutoInsertCenterMarks Method (View)

Syntax

Visual Basic for Applications (VBA)

```
Public Function AutoInsertCenterMarks( _  
    ByVal InsertType As Long, _  
    ByVal InsertOption As Long, _  
    ByVal LinearSlotCenter As Boolean, _  
    ByVal ArcSlotCenter As Boolean, _  
    ByVal UseDocumentDefaults As Boolean, _  
    ByVal Size As Double, _  
    ByVal ExtendedLines As Boolean, _  
    ByVal CenterLineFont As Boolean, _
```

```
    ByVal Angle As Double _  
  ) As Boolean
```

SOLIDWORKS Type Library

AutoInsertCenterMarks2 Method (View)

Syntax

Visual Basic for Applications (VBA)

```
Public Function AutoInsertCenterMarks2( _  
    ByVal InsertType As Long, _  
    ByVal InsertOption As Long, _  
    ByVal LinearSlotCenter As Boolean, _  
    ByVal ArcSlotCenter As Boolean, _  
    ByVal UseDocumentDefaults As Boolean, _  
    ByVal Size As Double, _  
    ByVal Gap As Double, _  
    ByVal ExtendedLines As Boolean, _  
    ByVal CenterLineFont As Boolean, _  
    ByVal Angle As Double _  
  ) As Boolean
```

SOLIDWORKS Type Library

Bodies Property (View)

Syntax

Visual Basic for Applications (VBA)

```
Public Property Bodies As Variant
```

SOLIDWORKS Type Library

BreakLineGap Property (View)

Syntax

Visual Basic for Applications (VBA)

```
Public Property BreakLineGap As Double
```

SOLIDWORKS Type Library

CreateViewArrow Method (View)

Syntax

Visual Basic for Applications (VBA)

```
Public Function CreateViewArrow( _  
    ByVal DrawingViewNameIn As String, _  
    ByVal ArrowNameIn As String _  
  ) As Boolean
```

SOLIDWORKS Type Library

Crop Method (View)

Syntax

Visual Basic for Applications (VBA)

```
Public Function Crop() As Long
```

SOLIDWORKS Type Library

Crop2 Method (View)

Syntax

Visual Basic for Applications (VBA)

```
Public Function Crop2( _  
    ByVal JaggedOutline As Boolean, _  
    ByVal NoOutline As Boolean, _
```

```
ByVal ShapeIntensity As Long _  
) As Long
```

SOLIDWORKS Type Library

CropViewJaggedOutline Property (View)



Syntax

Visual Basic for Applications (VBA)

```
Public Property CropViewJaggedOutline As Boolean
```

SOLIDWORKS Type Library

CropViewJaggedShapeIntensity Property (View)



Syntax

Visual Basic for Applications (VBA)

```
Public Property CropViewJaggedShapeIntensity As Long
```

SOLIDWORKS Type Library

CropViewNoOutline Property (View)



Syntax

Visual Basic for Applications (VBA)

```
Public Property CropViewNoOutline As Boolean
```

SOLIDWORKS Type Library

DisableAutoUpdate Property (View)



Syntax

Visual Basic for Applications (VBA)

```
Public Property DisableAutoUpdate As Boolean
```

SOLIDWORKS Type Library

DisplayState Property (View)



Syntax

Visual Basic for Applications (VBA)

```
Public Property DisplayState As String
```

SOLIDWORKS Type Library

EmphasizeOutline Property (View)



Syntax

Visual Basic for Applications (VBA)

```
Public Property EmphasizeOutline As Boolean
```

SOLIDWORKS Type Library

EnumHiddenComponents Method (View)



Syntax

Visual Basic for Applications (VBA)

```
Public Function EnumHiddenComponents() As EnumComponents
```

SOLIDWORKS Type Library

EnumHiddenComponents2 Method (View)



Syntax

Visual Basic for Applications (VBA)

```
Public Function EnumHiddenComponents2() As EnumComponents2
```

SOLIDWORKS Type Library

EnumSectionLines Method (View)



Visual Basic for Applications (VBA)

```
Public Function EnumSectionLines() As EnumDrSections
```

SOLIDWORKS Type Library

EnumSectionLines2 Method (View)



Visual Basic for Applications (VBA)

```
Public Function EnumSectionLines2( _  
    ByVal IgnoreSuppressed As Boolean _  
) As EnumDrSections
```

SOLIDWORKS Type Library

FlipView Property (View)



Visual Basic for Applications (VBA)

```
Public Property FlipView As Boolean
```

SOLIDWORKS Type Library

FocusLocked Property (View)



Visual Basic for Applications (VBA)

```
Public Property FocusLocked As Boolean
```

SOLIDWORKS Type Library

GetAlignment Method (View)



Visual Basic for Applications (VBA)

```
Public Function GetAlignment() As Long
```

SOLIDWORKS Type Library

GetAnnotationCount Method (View)



Visual Basic for Applications (VBA)

```
Public Function GetAnnotationCount() As Long
```

SOLIDWORKS Type Library

GetAnnotations Method (View)



Visual Basic for Applications (VBA)

```
Public Function GetAnnotations() As Variant
```

SOLIDWORKS Type Library

GetAnnotationsByType Method (View)



Syntax

Visual Basic for Applications (VBA)

```
Public Function GetAnnotationsByType( _  
    ByVal Type As Long _  
) As Variant
```

SOLIDWORKS Type Library

GetArcCount Method (View)



Syntax

Visual Basic for Applications (VBA)

```
Public Function GetArcCount() As Long
```

SOLIDWORKS Type Library

GetArcs Method (View)



Syntax

Visual Basic for Applications (VBA)

```
Public Function GetArcs() As Variant
```

SOLIDWORKS Type Library

GetArcs2 Method (View)



Syntax

Visual Basic for Applications (VBA)

```
Public Function GetArcs2() As Variant
```

SOLIDWORKS Type Library

GetArcs3 Method (View)



Syntax

Visual Basic for Applications (VBA)

```
Public Function GetArcs3() As Variant
```

SOLIDWORKS Type Library

GetArcs4 Method (View)



Syntax

Visual Basic for Applications (VBA)

```
Public Function GetArcs4() As Variant
```

SOLIDWORKS Type Library

GetBaseView Method (View)



Syntax

Visual Basic for Applications (VBA)

```
Public Function GetBaseView() As Object
```

SOLIDWORKS Type Library

GetBendLineCount Method (View)



Syntax

Visual Basic for Applications (VBA)

```
Public Function GetBendLineCount() As Long
```

SOLIDWORKS Type Library

GetBendLines Method (View)



Visual Basic for Applications (VBA)

```
Public Function GetBendLines() As Variant
```

SOLIDWORKS Type Library

GetBendNoteAttributeString Method (View)



Visual Basic for Applications (VBA)

```
Public Function GetBendNoteAttributeString( _  
    ByVal Attribute As Long _  
    ) As String
```

SOLIDWORKS Type Library

GetBendNoteTextFormat Method (View)



Visual Basic for Applications (VBA)

```
Public Function GetBendNoteTextFormat() As String
```

SOLIDWORKS Type Library

GetBodiesCount Method (View)



Visual Basic for Applications (VBA)

```
Public Function GetBodiesCount() As Long
```

SOLIDWORKS Type Library

GetBomTable Method (View)



Visual Basic for Applications (VBA)

```
Public Function GetBomTable() As Object
```

SOLIDWORKS Type Library

GetBreakLineCount Method (View)



Visual Basic for Applications (VBA)

```
Public Function GetBreakLineCount( _  
    ByRef Size As Long _  
    ) As Long
```

SOLIDWORKS Type Library

GetBreakLineCount2 Method (View)



Visual Basic for Applications (VBA)

```
Public Function GetBreakLineCount2( _  
    ByRef Size As Long _  
    ) As Long
```

SOLIDWORKS Type Library

GetBreakLineInfo Method (View)



Public Function GetBreakLineInfo() As Variant

SOLIDWORKS Type Library

GetBreakLineInfo2 Method (View)



Public Function GetBreakLineInfo2() As Variant

SOLIDWORKS Type Library

GetBreakLines Method (View)



Public Function GetBreakLines() As Variant

SOLIDWORKS Type Library

GetBreakOutSectionCount Method (View)



Public Function GetBreakOutSectionCount() As Long

SOLIDWORKS Type Library

GetBreakOutSections Method (View)



Public Function GetBreakOutSections() As Variant

SOLIDWORKS Type Library

GetCenterLineCount Method (View)



Public Function GetCenterLineCount() As Long

SOLIDWORKS Type Library

GetCenterLines Method (View)



Public Function GetCenterLines() As Variant

SOLIDWORKS Type Library

GetCenterLineSketch Method (View)



Public Function GetCenterLineSketch() As [Sketch](#)

SOLIDWORKS Type Library

GetCenterMarkCount Method (View)



```
Public Function GetCenterMarkCount() As Long
```

SOLIDWORKS Type Library

GetCenterMarkCount2 Method (View)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetCenterMarkCount2( _  
    ByRef Size As Long _  
) As Long
```

SOLIDWORKS Type Library

GetCenterMarkInfo Method (View)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetCenterMarkInfo() As Variant
```

SOLIDWORKS Type Library

GetCenterMarks Method (View)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetCenterMarks() As Variant
```

SOLIDWORKS Type Library

GetCorresponding Method (View)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetCorresponding( _  
    ByVal InputObject As Object _  
) As Object
```

SOLIDWORKS Type Library

GetCorrespondingEntity Method (View)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetCorrespondingEntity( _  
    ByVal Entity As Object _  
) As Object
```

SOLIDWORKS Type Library

GetCThreadCount Method (View)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetCThreadCount() As Long
```

SOLIDWORKS Type Library

GetCThreadQuality Method (View)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetCThreadQuality() As Boolean
```

SOLIDWORKS Type Library

GetCThreads Method (View)



Visual Basic for Applications (VBA)

```
Public Function GetCThreads() As Variant
```

SOLIDWORKS Type Library

GetDatumOriginCount Method (View)



Visual Basic for Applications (VBA)

```
Public Function GetDatumOriginCount() As Long
```

SOLIDWORKS Type Library

GetDatumOrigins Method (View)



Visual Basic for Applications (VBA)

```
Public Function GetDatumOrigins() As Variant
```

SOLIDWORKS Type Library

GetDatumPoints Method (View)



Visual Basic for Applications (VBA)

```
Public Function GetDatumPoints() As Variant
```

SOLIDWORKS Type Library

GetDatumPoints2 Method (View)



Visual Basic for Applications (VBA)

```
Public Function GetDatumPoints2() As Variant
```

SOLIDWORKS Type Library

GetDatumPointsCount Method (View)



Visual Basic for Applications (VBA)

```
Public Function GetDatumPointsCount() As Long
```

SOLIDWORKS Type Library

GetDatumTagCount Method (View)



Visual Basic for Applications (VBA)

```
Public Function GetDatumTagCount() As Long
```

SOLIDWORKS Type Library

GetDatumTags Method (View)



Visual Basic for Applications (VBA)

```
Public Function GetDatumTags() As Variant
```

SOLIDWORKS Type Library

GetDatumTargetSymCount Method (View)



Visual Basic for Applications (VBA)

```
Public Function GetDatumTargetSymCount() As Long
```

SOLIDWORKS Type Library

GetDatumTargetSyms Method (View)



Visual Basic for Applications (VBA)

```
Public Function GetDatumTargetSyms() As Variant
```

SOLIDWORKS Type Library

GetDependentViewCount Method (View)



Visual Basic for Applications (VBA)

```
Public Function GetDependentViewCount( _  
    ByVal AllViews As Boolean, _  
    ByVal SpecificViewType As Long _  
) As Long
```

SOLIDWORKS Type Library

GetDependentViews Method (View)



Visual Basic for Applications (VBA)

```
Public Function GetDependentViews( _  
    ByVal AllViews As Boolean, _  
    ByVal SpecificViewType As Long _  
) As Variant
```

SOLIDWORKS Type Library

GetDesignTableExtent Method (View)



Visual Basic for Applications (VBA)

```
Public Function GetDesignTableExtent() As Variant
```

SOLIDWORKS Type Library

GetDetail Method (View)



Visual Basic for Applications (VBA)

```
Public Function GetDetail() As Object
```

SOLIDWORKS Type Library

GetDetailCircleCount Method (View)



Visual Basic for Applications (VBA)

```
Public Function GetDetailCircleCount() As Long
```

SOLIDWORKS Type Library

GetDetailCircleCount2 Method (View)



Syntax

Visual Basic for Applications (VBA)

```
Public Function GetDetailCircleCount2( _  
    ByRef Size As Long _  
) As Long
```

SOLIDWORKS Type Library

GetDetailCircleInfo Method (View)



Syntax

Visual Basic for Applications (VBA)

```
Public Function GetDetailCircleInfo() As Variant
```

SOLIDWORKS Type Library

GetDetailCircleInfo2 Method (View)



Syntax

Visual Basic for Applications (VBA)

```
Public Function GetDetailCircleInfo2() As Variant
```

SOLIDWORKS Type Library

GetDetailCircles Method (View)



Syntax

Visual Basic for Applications (VBA)

```
Public Function GetDetailCircles() As Variant
```

SOLIDWORKS Type Library

GetDetailCircleStrings Method (View)



Syntax

Visual Basic for Applications (VBA)

```
Public Function GetDetailCircleStrings() As Variant
```

SOLIDWORKS Type Library

GetDimensionCount Method (View)



Syntax

Visual Basic for Applications (VBA)

```
Public Function GetDimensionCount() As Long
```

SOLIDWORKS Type Library

GetDimensionCount2 Method (View)



Syntax

Visual Basic for Applications (VBA)

```
Public Function GetDimensionCount2() As Long
```

SOLIDWORKS Type Library

GetDimensionCount3 Method (View)



Syntax

Visual Basic for Applications (VBA)

```
Public Function GetDimensionCount3() As Long
```

SOLIDWORKS Type Library

GetDimensionCount4 Method (View)



Syntax

Visual Basic for Applications (VBA)

```
Public Function GetDimensionCount4() As Long
```

SOLIDWORKS Type Library

GetDimensionDisplayInfo Method (View)



Syntax

Visual Basic for Applications (VBA)

```
Public Function GetDimensionDisplayInfo() As Variant
```

SOLIDWORKS Type Library

GetDimensionDisplayInfo2 Method (View)



Syntax

Visual Basic for Applications (VBA)

```
Public Function GetDimensionDisplayInfo2() As Variant
```

SOLIDWORKS Type Library

GetDimensionDisplayInfo3 Method (View)



Syntax

Visual Basic for Applications (VBA)

```
Public Function GetDimensionDisplayInfo3() As Variant
```

SOLIDWORKS Type Library

GetDimensionDisplayInfo4 Method (View)



Syntax

Visual Basic for Applications (VBA)

```
Public Function GetDimensionDisplayInfo4() As Variant
```

SOLIDWORKS Type Library

GetDimensionDisplayInfo5 Method (View)



Syntax

Visual Basic for Applications (VBA)

```
Public Function GetDimensionDisplayInfo5() As Variant
```

SOLIDWORKS Type Library

GetDimensionDisplayInfoSize Method (View)



Syntax

Visual Basic for Applications (VBA)

```
Public Function GetDimensionDisplayInfoSize() As Long
```

SOLIDWORKS Type Library

GetDimensionDisplayInfoSize2 Method (View)



Syntax

Visual Basic for Applications (VBA)

```
Public Function GetDimensionDisplayInfoSize2() As Long
```

SOLIDWORKS Type Library

GetDimensionDisplayString Method (View)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetDimensionDisplayString() As Variant
```

SOLIDWORKS Type Library

GetDimensionDisplayString2 Method (View)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetDimensionDisplayString2() As Variant
```

SOLIDWORKS Type Library

GetDimensionDisplayString3 Method (View)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetDimensionDisplayString3() As Variant
```

SOLIDWORKS Type Library

GetDimensionDisplayString4 Method (View)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetDimensionDisplayString4() As Variant
```

SOLIDWORKS Type Library

GetDimensionDisplayString5 Method (View)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetDimensionDisplayString5( _  
    ByRef DimensionSize As Long _  
) As Variant
```

SOLIDWORKS Type Library

GetDimensionIds Method (View)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetDimensionIds() As Variant
```

SOLIDWORKS Type Library

GetDimensionIds2 Method (View)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetDimensionIds2() As Variant
```

SOLIDWORKS Type Library

GetDimensionIds3 Method (View)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetDimensionIds3() As Variant
```

SOLIDWORKS Type Library

GetDimensionIds4 Method (View)



Visual Basic for Applications (VBA)

```
Public Function GetDimensionIds4() As Variant
```

SOLIDWORKS Type Library

GetDimensionInfo Method (View)



Visual Basic for Applications (VBA)

```
Public Function GetDimensionInfo() As Variant
```

SOLIDWORKS Type Library

GetDimensionInfo2 Method (View)



Visual Basic for Applications (VBA)

```
Public Function GetDimensionInfo2() As Variant
```

SOLIDWORKS Type Library

GetDimensionInfo3 Method (View)



Visual Basic for Applications (VBA)

```
Public Function GetDimensionInfo3() As Variant
```

SOLIDWORKS Type Library

GetDimensionInfo4 Method (View)



Visual Basic for Applications (VBA)

```
Public Function GetDimensionInfo4() As Variant
```

SOLIDWORKS Type Library

GetDimensionInfo5 Method (View)



Visual Basic for Applications (VBA)

```
Public Function GetDimensionInfo5() As Variant
```

SOLIDWORKS Type Library

GetDimensionInfo6 Method (View)



Visual Basic for Applications (VBA)

```
Public Function GetDimensionInfo6() As Variant
```

SOLIDWORKS Type Library

GetDimensionInfo7 Method (View)



Visual Basic for Applications (VBA)

```
Public Function GetDimensionInfo7() As Variant
```

SOLIDWORKS Type Library

GetDimensionString Method (View)



Syntax

Visual Basic for Applications (VBA)

```
Public Function GetDimensionString() As Variant
```

SOLIDWORKS Type Library

GetDimensionString2 Method (View)



Syntax

Visual Basic for Applications (VBA)

```
Public Function GetDimensionString2() As Variant
```

SOLIDWORKS Type Library

GetDimensionString3 Method (View)



Syntax

Visual Basic for Applications (VBA)

```
Public Function GetDimensionString3() As Variant
```

SOLIDWORKS Type Library

GetDimensionString4 Method (View)



Syntax

Visual Basic for Applications (VBA)

```
Public Function GetDimensionString4() As Variant
```

SOLIDWORKS Type Library

GetDisplayData Method (View)



Syntax

Visual Basic for Applications (VBA)

```
Public Function GetDisplayData() As Object
```

SOLIDWORKS Type Library

GetDisplayData2 Method (View)



Syntax

Visual Basic for Applications (VBA)

```
Public Function GetDisplayData2() As Object
```

SOLIDWORKS Type Library

GetDisplayData3 Method (View)



Syntax

Visual Basic for Applications (VBA)

```
Public Function GetDisplayData3() As Object
```

SOLIDWORKS Type Library

GetDisplayData4 Method (View)



Syntax

Visual Basic for Applications (VBA)

```
Public Function GetDisplayData4() As Object
```

SOLIDWORKS Type Library

GetDisplayDimensionCount Method (View)



Visual Basic for Applications (VBA)

```
Public Function GetDisplayDimensionCount() As Long
```

SOLIDWORKS Type Library

GetDisplayDimensions Method (View)



Visual Basic for Applications (VBA)

```
Public Function GetDisplayDimensions() As Variant
```

SOLIDWORKS Type Library

GetDisplayEdgesInShadedMode Method (View)



Visual Basic for Applications (VBA)

```
Public Function GetDisplayEdgesInShadedMode() As Boolean
```

SOLIDWORKS Type Library

GetDisplayMode Method (View)



Visual Basic for Applications (VBA)

```
Public Function GetDisplayMode() As Long
```

SOLIDWORKS Type Library

GetDisplayMode2 Method (View)



Visual Basic for Applications (VBA)

```
Public Function GetDisplayMode2() As Long
```

SOLIDWORKS Type Library

GetDisplayTangentEdges Method (View)



Visual Basic for Applications (VBA)

```
Public Function GetDisplayTangentEdges() As Boolean
```

SOLIDWORKS Type Library

GetDisplayTangentEdges2 Method (View)



Visual Basic for Applications (VBA)

```
Public Function GetDisplayTangentEdges2() As Long
```

SOLIDWORKS Type Library

GetDowelSymbolCount Method (View)



Visual Basic for Applications (VBA)

```
Public Function GetDowelSymbolCount() As Long
```

SOLIDWORKS Type Library

GetDowelSymbols Method (View)



Visual Basic for Applications (VBA)

```
Public Function GetDowelSymbols() As Variant
```

SOLIDWORKS Type Library

GetEllipseCount Method (View)



Visual Basic for Applications (VBA)

```
Public Function GetEllipseCount() As Long
```

SOLIDWORKS Type Library

GetEllipses Method (View)



Visual Basic for Applications (VBA)

```
Public Function GetEllipses() As Variant
```

SOLIDWORKS Type Library

GetEllipses2 Method (View)



Visual Basic for Applications (VBA)

```
Public Function GetEllipses2() As Variant
```

SOLIDWORKS Type Library

GetEllipses3 Method (View)



Visual Basic for Applications (VBA)

```
Public Function GetEllipses3() As Variant
```

SOLIDWORKS Type Library

GetEllipses4 Method (View)



Visual Basic for Applications (VBA)

```
Public Function GetEllipses4() As Variant
```

SOLIDWORKS Type Library

GetEllipses5 Method (View)



Visual Basic for Applications (VBA)

```
Public Function GetEllipses5() As Variant
```

SOLIDWORKS Type Library

GetFaceHatchCount Method (View)



Visual Basic for Applications (VBA)

```
Public Function GetFaceHatchCount() As Long
```

SOLIDWORKS Type Library

GetFaceHatches Method (View)



Visual Basic for Applications (VBA)

```
Public Function GetFaceHatches() As Variant
```

SOLIDWORKS Type Library

GetFacettedHlrDisplay Method (View)



Visual Basic for Applications (VBA)

```
Public Function GetFacettedHlrDisplay() As Boolean
```

SOLIDWORKS Type Library

GetFirstAnnotation Method (View)



Visual Basic for Applications (VBA)

```
Public Function GetFirstAnnotation() As Object
```

SOLIDWORKS Type Library

GetFirstAnnotation2 Method (View)



Visual Basic for Applications (VBA)

```
Public Function GetFirstAnnotation2() As Object
```

SOLIDWORKS Type Library

GetFirstAnnotation3 Method (View)



Visual Basic for Applications (VBA)

```
Public Function GetFirstAnnotation3() As Annotation
```

SOLIDWORKS Type Library

GetFirstBlockInstance Method (View)



Visual Basic for Applications (VBA)

```
Public Function GetFirstBlockInstance() As BlockInstance
```

SOLIDWORKS Type Library

GetFirstCenterLine Method (View)



Visual Basic for Applications (VBA)

```
Public Function GetFirstCenterLine() As Centerline
```

SOLIDWORKS Type Library

GetFirstCenterMark Method (View)



Visual Basic for Applications (VBA)

```
Public Function GetFirstCenterMark() As CenterMark
```

SOLIDWORKS Type Library

GetFirstCenterMark2 Method (View)



Visual Basic for Applications (VBA)

```
Public Function GetFirstCenterMark2() As Object
```

SOLIDWORKS Type Library

GetFirstCenterOfMass Method (View)



Visual Basic for Applications (VBA)

```
Public Function GetFirstCenterOfMass() As Object
```

SOLIDWORKS Type Library

GetFirstCThread Method (View)



Visual Basic for Applications (VBA)

```
Public Function GetFirstCThread() As Object
```

SOLIDWORKS Type Library

GetFirstCustomSymbol Method (View)



Visual Basic for Applications (VBA)

```
Public Function GetFirstCustomSymbol() As Object
```

SOLIDWORKS Type Library

GetFirstDatumOrigin Method (View)



Visual Basic for Applications (VBA)

```
Public Function GetFirstDatumOrigin() As DatumOrigin
```

SOLIDWORKS Type Library

GetFirstDatumTag Method (View)



Visual Basic for Applications (VBA)

```
Public Function GetFirstDatumTag() As Object
```

SOLIDWORKS Type Library

GetFirstDatumTargetSym Method (View)



Visual Basic for Applications (VBA)

```
Public Function GetFirstDatumTargetSym() As Object
```

SOLIDWORKS Type Library

GetFirstDisplayDimension Method (View)



Visual Basic for Applications (VBA)

```
Public Function GetFirstDisplayDimension() As Object
```

SOLIDWORKS Type Library

GetFirstDisplayDimension2 Method (View)



Visual Basic for Applications (VBA)

```
Public Function GetFirstDisplayDimension2() As Object
```

SOLIDWORKS Type Library

GetFirstDisplayDimension3 Method (View)



Visual Basic for Applications (VBA)

```
Public Function GetFirstDisplayDimension3() As Object
```

SOLIDWORKS Type Library

GetFirstDisplayDimension4 Method (View)



Visual Basic for Applications (VBA)

```
Public Function GetFirstDisplayDimension4() As DisplayDimension
```

SOLIDWORKS Type Library

GetFirstDisplayDimension5 Method (View)



Visual Basic for Applications (VBA)

```
Public Function GetFirstDisplayDimension5() As DisplayDimension
```

SOLIDWORKS Type Library

GetFirstDisplayDimension6 Method (View)



Visual Basic for Applications (VBA)

```
Public Function GetFirstDisplayDimension6() As Object
```

SOLIDWORKS Type Library

GetFirstDowelSymbol Method (View)



Visual Basic for Applications (VBA)

```
Public Function GetFirstDowelSymbol() As Object
```

SOLIDWORKS Type Library

GetFirstGTOL Method (View)



Visual Basic for Applications (VBA)

```
Public Function GetFirstGTOL() As Object
```

SOLIDWORKS Type Library

GetFirstMultiJogLeader Method (View)



Visual Basic for Applications (VBA)

```
Public Function GetFirstMultiJogLeader() As Object
```

SOLIDWORKS Type Library

GetFirstMultiJogLeader2 Method (View)



Visual Basic for Applications (VBA)

```
Public Function GetFirstMultiJogLeader2() As Object
```

SOLIDWORKS Type Library

GetFirstNote Method (View)



Visual Basic for Applications (VBA)

```
Public Function GetFirstNote() As Object
```

SOLIDWORKS Type Library

GetFirstNote2 Method (View)



Visual Basic for Applications (VBA)

```
Public Function GetFirstNote2() As Object
```

SOLIDWORKS Type Library

GetFirstRevisionCloud Method (View)



Visual Basic for Applications (VBA)

```
Public Function GetFirstRevisionCloud() As Object
```

SOLIDWORKS Type Library

GetFirstRevisionCloud2 Method (View)



Visual Basic for Applications (VBA)

```
Public Function GetFirstRevisionCloud2() As Object
```

SOLIDWORKS Type Library

GetFirstSFSymbol Method (View)



Visual Basic for Applications (VBA)

```
Public Function GetFirstSFSymbol() As Object
```

SOLIDWORKS Type Library

GetFirstTableAnnotation Method (View)



Visual Basic for Applications (VBA)

```
Public Function GetFirstTableAnnotation() As TableAnnotation
```

SOLIDWORKS Type Library

GetFirstTableAnnotation2 Method (View)



Visual Basic for Applications (VBA)

```
Public Function GetFirstTableAnnotation2() As Object
```

SOLIDWORKS Type Library

GetFirstWeldBead Method (View)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetFirstWeldBead() As WeldBead
```

SOLIDWORKS Type Library

GetFirstWeldSymbol Method (View)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetFirstWeldSymbol() As Object
```

SOLIDWORKS Type Library

GetGTolCount Method (View)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetGTolCount() As Long
```

SOLIDWORKS Type Library

GetGTols Method (View)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetGTols() As Variant
```

SOLIDWORKS Type Library

GetHiddenComponents Method (View)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetHiddenComponents() As Variant
```

SOLIDWORKS Type Library

GetHiddenEdgeCount Method (View)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetHiddenEdgeCount() As Long
```

SOLIDWORKS Type Library

GetKeepLinkedToBOM Method (View)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetKeepLinkedToBOM() As Boolean
```

SOLIDWORKS Type Library

GetKeepLinkedToBOMName Method (View)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetKeepLinkedToBOMName() As String
```



Visual Basic for Applications (VBA)

```
Public Function GetLineCount() As Long
```



Visual Basic for Applications (VBA)

```
Public Function GetLineCount2( _  
    ByVal CrossHatchOption As Integer _  
    ) As Long
```