

SOLIDWORKS Enumerations (swconst) — Reference (3/17)

swBOMControlMissingRowDisplay_e swComponentSolvingOption_e

SOLIDWORKS API Documentation (converted from CHM)

swBOMControlMissingRowDisplay_e (Type)

SOLIDWORKS API Enumerations

swBOMControlMissingRowDisplay_e Enumeration

See Also

 

[SolidWorks.Interop.swconst Namespace](#) : swBOMControlMissingRowDisplay_e Enumeration

How to handle empty rows in BOM tables.

[Send comments on this topic.](#)

Syntax

Visual Basic (Declaration)

Public Enum swBOMControlMissingRowDisplay_e
Inherits System.Enum

Visual Basic (Usage)

Dim instance As [swBOMControlMissingRowDisplay_e](#)

C#

public enum swBOMControlMissingRowDisplay_e : System.Enum

C++/CLI

public enum class swBOMControlMissingRowDisplay_e : public System.Enum

Members

Member	Description
swBOMControlHideMissingRow	2 = Hide the empty row
swBOMControlShowMissingRow	1 = Show the empty row
swBOMControlStrikeMissingRow	3 = Show the empty row with strike through te

See Also

[SolidWorks.Interop.swconst Namespace](#)

swBOMControlSplitDirection_e (Type)

SOLIDWORKS API Enumerations

swBOMControlSplitDirection_e Enumeration

See Also

[Send comments on this topic.](#)

 

[SolidWorks.Interop.swconst Namespace](#) : swBOMControlSplitDirection_e Enumeration

Direction where to split new sections in BOM tables.

 Syntax

Visual Basic (Declaration)

```
Public Enum swBOMControlSplitDirection_e
    Inherits System.Enum
```

Visual Basic (Usage)  Copy Code

```
Dim instance As swBOMControlSplitDirection\_e
```

C#

```
public enum swBOMControlSplitDirection_e : System.Enum
```

C++/CLI

```
public enum class swBOMControlSplitDirection_e : public System.Enum
```

 Members

Member	Description
swBOMControlSplitLeft	2
swBOMControlSplitRight	1

 See Also

[SolidWorks.Interop.swconst Namespace](#)

swBOMPartNumberSource_e (Type)

SOLIDWORKS API Enumerations

swBOMPartNumberSource_e Enumeration

See Also

 

SolidWorks.Interop.swconst Namespace : swBOMPartNumberSource_e Enumeration

Sources from numbers in BOM tables. [Bitmask](#).

[Send comments on this topic.](#)

Syntax

Visual Basic (Declaration)

```
Public Enum swBOMPartNumberSource_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swBOMPartNumberSource\_e
```

C#

```
public enum swBOMPartNumberSource_e : System.Enum
```

C++/CLI

```
public enum class swBOMPartNumberSource_e : public System.Enum
```

Members

Member	Description
swBOMPartNumber_ConfigurationName	2 or 0x2
swBOMPartNumber_DocumentName	1 or 0x1
swBOMPartNumber_ParentName	4 or 0x4
swBOMPartNumber_UserSpecified	8 or 0x8

See Also

[SolidWorks.Interop.swconst Namespace](#)

swBOMTableObjectType_e (Type)

SOLIDWORKS API Enumerations

swBOMTableObjectType_e Enumeration

See Also

 

[SolidWorks.Interop.swconst Namespace](#) : swBOMTableObjectType_e Enumeration

Types of BOM table items to expand and collapse.

[Send comments on this topic.](#)

 Syntax

Visual Basic (Declaration)

```
Public Enum swBOMTableObjectType_e
    Inherits System.Enum
```

Visual Basic (Usage)  Copy Code

```
Dim instance As swBOMTableObjectType\_e
```

C#

```
public enum swBOMTableObjectType_e : System.Enum
```

C++/CLI

```
public enum class swBOMTableObjectType_e : public System.Enum
```

 Members

Member	Description
swBOMTableObjectType_CutList	2
swBOMTableObjectType_RowIndex	1

 See Also

[SolidWorks.Interop.swconst Namespace](#)

swBomTableSortItemGroup_e (Type)

SOLIDWORKS API Enumerations

swBomTableSortItemGroup_e Enumeration

See Also

 

[SolidWorks.Interop.swconst Namespace](#) : swBomTableSortItemGroup_e Enumeration

Categories for sorting bill of material table rows.

[Send comments on this topic.](#)

Syntax

Visual Basic (Declaration)

```
Public Enum swBomTableSortItemGroup_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swBomTableSortItemGroup\_e
```

C#

```
public enum swBomTableSortItemGroup_e : System.Enum
```

C++/CLI

```
public enum class swBomTableSortItemGroup_e : public System.Enum
```

Members

Member	Description
swBomTableSortItemGroup_Assemblies	1 = Group table rows containing assemblies
swBomTableSortItemGroup_None	DO NOT USE
swBomTableSortItemGroup_Other	3 = Group table rows containing user-defined items
swBomTableSortItemGroup_Parts	2 = Group table rows containing parts

Remarks

These enumerator options are used by [IBomTableSortData::ItemGroups](#) to set the groupings for table sorting.

For example, when you set IBomTableSortData::ItemGroups to the following array, assemblies are grouped first, parts are grouped second, and other categories are grouped last:

1. [swBomTableSortItemGroup_e](#).swBomTableSortItemGroup_Assemblies
2. [swBomTableSortItemGroup_e](#).swBomTableSortItemGroup_Parts
3. [swBomTableSortItemGroup_e](#).swBomTableSortItemGroup_Other

See Also

[SolidWorks.Interop.swconst Namespace](#)

swBomTableSortMethod_e (Type)

SOLIDWORKS API Enumerations

swBomTableSortMethod_e Enumeration

See Also

 

SolidWorks.Interop.swconst Namespace : swBomTableSortMethod_e Enumeration

Bill of Materials table sorting methods.

[Send comments on this topic.](#)

Syntax

Visual Basic (Declaration)

```
Public Enum swBomTableSortMethod_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swBomTableSortMethod\_e
```

C#

```
public enum swBomTableSortMethod_e : System.Enum
```

C++/CLI

```
public enum class swBomTableSortMethod_e : public System.Enum
```

Members

Member	Description
swBomTableSortMethod_Literal	0
swBomTableSortMethod_Numeric	1

See Also

[SolidWorks.Interop.swconst Namespace](#)

swBomType_e (Type)

 

[SolidWorks.Interop.swconst Namespace](#) : swBomType_e Enumeration

Types of BOM tables.

Syntax

Visual Basic (Declaration)

Public Enum swBomType_e
Inherits System.Enum

Visual Basic (Usage)  Copy Code

Dim instance As [swBomType_e](#)

C#

public enum swBomType_e : System.Enum

C++/CLI

public enum class swBomType_e : public System.Enum

Members

Member	Description
swBomType_Flattened	4
swBomType_Indented	3
swBomType_PartsOnly	1
swBomType_TopLevelOnly	2

See Also

[SolidWorks.Interop.swconst Namespace](#)

swBoundaryBossAlignment_e (Type)

SOLIDWORKS API Enumerations

swBoundaryBossAlignment_e Enumeration

See Also

 

[SolidWorks.Interop.swconst Namespace](#) : swBoundaryBossAlignment_e Enumeration

Boundary feature alignments.

[Send comments on this topic.](#)

Syntax

Visual Basic (Declaration)

```
Public Enum swBoundaryBossAlignment_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swBoundaryBossAlignment\_e
```

C#

```
public enum swBoundaryBossAlignment_e : System.Enum
```

C++/CLI

```
public enum class swBoundaryBossAlignment_e : public System.Enum
```

Members

Member	Description
swAlignWithIsoParameter	3
swAlignWithNextSection	1
swAlignWithOtherGeometry	2
swAlignWithSectionNormal	0

See Also

[SolidWorks.Interop.swconst Namespace](#)

swBoundaryBossCurveInfluenceType_e (Type)

SOLIDWORKS API Enumerations

swBoundaryBossCurveInfluenceType_e Enumeration

See Also

[SolidWorks.Interop.swconst Namespace](#) : swBoundaryBossCurveInfluenceType_e Enumeration

Boundary feature curve influence types. [Bitmask](#).

Syntax

Visual Basic (Declaration)

```
Public Enum swBoundaryBossCurveInfluenceType_e
    Inherits System.Enum
```

Visual Basic (Usage)

Copy Code

```
Dim instance As swBoundaryBossCurveInfluenceType\_e
```

C#

```
public enum swBoundaryBossCurveInfluenceType_e : System.Enum
```

C++/CLI

```
public enum class swBoundaryBossCurveInfluenceType_e : public System.Enum
```

Members

Member	Description
swBoundaryBossCurve_GlobalInfluence	32 or 0x20
swBoundaryBossCurve_LinearInfluence	144 or 0x90
swBoundaryBossCurve_ToEdgeInfluence	64 or 0x40
swBoundaryBossCurve_ToNextCurveInfluence	0 or 0x0
swBoundaryBossCurve_ToNextSharpInfluence	16 or 0x10

See Also

[SolidWorks.Interop.swconst Namespace](#)

swBoundaryBossDirection_e (Type)

SOLIDWORKS API Enumerations

swBoundaryBossDirection_e Enumeration

See Also

[Send comments on this topic.](#)

 

[SolidWorks.Interop.swconst Namespace](#) : swBoundaryBossDirection_e Enumeration

Boundary feature directions.

 Syntax

Visual Basic (Declaration)

```
Public Enum swBoundaryBossDirection_e
    Inherits System.Enum
```

Visual Basic (Usage)  Copy Code

```
Dim instance As swBoundaryBossDirection\_e
```

C#

```
public enum swBoundaryBossDirection_e : System.Enum
```

C++/CLI

```
public enum class swBoundaryBossDirection_e : public System.Enum
```

 Members

Member	Description
swBoundaryBossDirection_Both	2
swBoundaryBossDirection_First	0
swBoundaryBossDirection_Second	1

 See Also

[SolidWorks.Interop.swconst Namespace](#)

swBoundaryBossTangencyType_e (Type)

SOLIDWORKS API Enumerations

swBoundaryBossTangencyType_e Enumeration

[See Also](#)

 

[SolidWorks.Interop.swconst Namespace](#) : swBoundaryBossTangencyType_e Enumeration

Send comments on this topic.

Tangency types for curves in boundary features.

 Syntax

Visual Basic (Declaration)

Public Enum swBoundaryBossTangencyType_e
Inherits System.Enum

Visual Basic (Usage)

Dim instance As [swBoundaryBossTangencyType_e](#)

 [Copy Code](#)

C#

public enum swBoundaryBossTangencyType_e : System.Enum

C++/CLI

public enum class swBoundaryBossTangencyType_e : public System.Enum

 Members

Member	Description
swBoundaryBossTangency_CurvatureToFace	4
swBoundaryBossTangency_Default	6
swBoundaryBossTangency_DirectionVector	2
swBoundaryBossTangency_None	0
swBoundaryBossTangency_NormalToProfile	1
swBoundaryBossTangency_TangencyToFace	3

 See Also

[SolidWorks.Interop.swconst Namespace](#)

swBoundingBoxOptions_e (Type)

SOLIDWORKS API Enumerations

swBoundingBoxOptions_e Enumeration

See Also

 

[SolidWorks.Interop.swconst Namespace](#) : swBoundingBoxOptions_e Enumeration

Bounding box options. [Bitmask](#).

[Send comments on this topic.](#)

 Syntax

Visual Basic (Declaration)

Public Enum swBoundingBoxOptions_e
Inherits System.Enum

Visual Basic (Usage)

Dim instance As [swBoundingBoxOptions_e](#)

C#

public enum swBoundingBoxOptions_e : System.Enum

C++/CLI

public enum class swBoundingBoxOptions_e : public System.Enum

 Members

Member	Description
swBoundingBoxIncludeRefPlanes	1 or 0x1
swBoundingBoxIncludeSketches	2 or 0x2

 See Also

[SolidWorks.Interop.swconst Namespace](#)

swBoundType_e (Type)

[SolidWorks.Interop.swconst Namespace](#) : swBoundType_e Enumeration

Boundary behaviors at the start and end of UV parameter ranges.

Syntax

Visual Basic (Declaration)

```
Public Enum swBoundType_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swBoundType\_e
```

C#

```
public enum swBoundType_e : System.Enum
```

C++/CLI

```
public enum class swBoundType_e : public System.Enum
```

Members

Member	Description
swBoundType_Degenerate	13741 (see Remarks)
swBoundType_Extendable	13734
swBoundType_Infinite	13733
swBoundType_NotExtendable	13735
swBoundType_Periodic	13701
swBoundType_PeriodicNotDifferentiable	13736 = Not continuously differentiable across the boundary.

Remarks

If the behavior at the start of the U range is 'Degenerate', then the V parameter is degenerate when $U = \text{urange}[0]$. The derivative of the parameterization function with respect to v is 0 whenever $u = \text{urange}[0]$, for all values of v, and the parameter curve corresponding to $u = \text{urange}[0]$ degenerates to a single point. A parameterization can only degenerate at the end of its range, unless the surface is a B-spline surface.

See Also

[SolidWorks.Interop.swconst Namespace](#)

swBreakCornerTypes_e (Type)

SOLIDWORKS API Enumerations

swBreakCornerTypes_e Enumeration

See Also

[Send comments on this topic.](#)

 

[SolidWorks.Interop.swconst Namespace](#) : swBreakCornerTypes_e Enumeration

Types of break corners.

 Syntax

Visual Basic (Declaration)

Public Enum swBreakCornerTypes_e
Inherits System.Enum

Visual Basic (Usage)  Copy Code

Dim instance As [swBreakCornerTypes_e](#)

C#

public enum swBreakCornerTypes_e : System.Enum

C++/CLI

public enum class swBreakCornerTypes_e : public System.Enum

 Members

Member	Description
swBreakCornerTypeChamfer	2
swBreakCornerTypeFillet	1

 See Also

[SolidWorks.Interop.swconst Namespace](#)

swBreakLineOrientation_e (Type)

SOLIDWORKS API Enumerations

swBreakLineOrientation_e Enumeration

See Also

 

[SolidWorks.Interop.swconst Namespace](#) : swBreakLineOrientation_e Enumeration

Break lines orientation.

[Send comments on this topic.](#)

Syntax

Visual Basic (Declaration)

Public Enum swBreakLineOrientation_e
Inherits System.Enum

Visual Basic (Usage)

Dim instance As [swBreakLineOrientation_e](#)

C#

public enum swBreakLineOrientation_e : System.Enum

C++/CLI

public enum class swBreakLineOrientation_e : public System.Enum

Members

Member	Description
swBreakLineHorizontal	1
swBreakLineVertical	2

See Also

[SolidWorks.Interop.swconst Namespace](#)

swBreakLineStyle_e (Type)

SOLIDWORKS API Enumerations

swBreakLineStyle_e Enumeration

See Also

[Send comments on this topic.](#)

 

[SolidWorks.Interop.swconst Namespace](#) : swBreakLineStyle_e Enumeration

Break line styles.

 Syntax

Visual Basic (Declaration)

Public Enum swBreakLineStyle_e
Inherits System.Enum

Visual Basic (Usage)  [Copy Code](#)

Dim instance As [swBreakLineStyle_e](#)

C#

public enum swBreakLineStyle_e : System.Enum

C++/CLI

public enum class swBreakLineStyle_e : public System.Enum

 Members

Member	Description
swBreakLine_Curve	3
swBreakLine_Jagged	5
swBreakLine_SmallZigZag	4
swBreakLine_Straight	1
swBreakLine_ZigZag	2

 See Also

[SolidWorks.Interop.swconst Namespace](#)

swButtonSize_e (Type)

SOLIDWORKS API Enumerations

swButtonSize_e Enumeration

See Also

 

[SolidWorks.Interop.swconst Namespace](#) : swButtonSize_e Enumeration

Toolbar button sizes.

[Send comments on this topic.](#)

 Syntax

Visual Basic (Declaration)

Public Enum swButtonSize_e
Inherits System.Enum

Visual Basic (Usage)

Dim instance As [swButtonSize_e](#)

 [Copy Code](#)

C#

public enum swButtonSize_e : System.Enum

C++/CLI

public enum class swButtonSize_e : public System.Enum

 Members

Member	Description
swButtonSize_Large	2
swButtonSize_Medium	1
swButtonSize_Small	0

 See Also

[SolidWorks.Interop.swconst Namespace](#)

swCADFamilyCfgOptions_e (Type)

SOLIDWORKS API Enumerations

swCADFamilyCfgOptions_e Enumeration

See Also

[SolidWorks.Interop.swconst Namespace](#) : swCADFamilyCfgOptions_e Enumeration

SOLIDWORKS Design connected to the 3DEXPERIENCE platform family configuration options. [Bitmask](#).

Syntax

Visual Basic (Declaration)

```
Public Enum swCADFamilyCfgOptions_e
    Inherits System.Enum
```

Visual Basic (Usage)

```
Dim instance As swCADFamilyCfgOptions\_e
```

C#

```
public enum swCADFamilyCfgOptions_e : System.Enum
```

C++/CLI

```
public enum class swCADFamilyCfgOptions_e : public System.Enum
```

Members

Member	Description
swCADFamilyCfgOption_DontActivate	0x4 or 4
swCADFamilyCfgOption_SuppressNewComponents	0x2 or 2
swCADFamilyCfgOption_SuppressNewFeatures	0x1 or 1

See Also

[SolidWorks.Interop.swconst Namespace](#)

swCalloutTargetStyle_e (Type)

SOLIDWORKS API Enumerations

swCalloutTargetStyle_e Enumeration

[See Also](#)

[Send comments on this topic.](#)

 

SolidWorks.Interop.swconst Namespace : swCalloutTargetStyle_e Enumeration

Callout target styles.

 Syntax

Visual Basic (Declaration)

Public Enum swCalloutTargetStyle_e
Inherits System.Enum

Visual Basic (Usage)

Dim instance As [swCalloutTargetStyle_e](#)

C#

public enum swCalloutTargetStyle_e : System.Enum

C++/CLI

public enum class swCalloutTargetStyle_e : public System.Enum

 Members

Member	Description
swCalloutTargetStyle_Arrow	4
swCalloutTargetStyle_Circle	2
swCalloutTargetStyle_None	0
swCalloutTargetStyle_Square	1
swCalloutTargetStyle_Triangle	3

 See Also

[SolidWorks.Interop.swconst Namespace](#)

[SolidWorks.Interop.swconst Namespace](#)

swCalloutVariable_e (Type)

SOLIDWORKS API Enumerations

swCalloutVariable_e Enumeration

See Also

▼

SolidWorks.Interop.swconst Namespace : swCalloutVariable_e Enumeration

Types of specific hole callout variables.

[Send comments on this topic.](#)

Syntax

Visual Basic (Declaration)

```
Public Enum swCalloutVariable_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swCalloutVariable\_e
```

C#

```
public enum swCalloutVariable_e : System.Enum
```

C++/CLI

```
public enum class swCalloutVariable_e : public System.Enum
```

Members

Member	Description
swCalloutVariable_AH_Blind_Msg	86
swCalloutVariable_AH_Counterbore_Depth	52
swCalloutVariable_AH_Counterbore_Diameter	51
swCalloutVariable_AH_Counterbore_Farside_Msg	53
swCalloutVariable_AH_Counterbore_Nearside_Msg	54
swCalloutVariable_AH_Counterbore_Side	55
swCalloutVariable_AH_Countersink_Angle	57
swCalloutVariable_AH_Countersink_Depth	58
swCalloutVariable_AH_Countersink_Diameter	56
swCalloutVariable_AH_Countersink_Farside_Msg	60
swCalloutVariable_AH_Countersink_Nearside_Msg	59
swCalloutVariable_AH_Countersink_Side	61
swCalloutVariable_AH_Dowel_HoleFit	78
swCalloutVariable_AH_Dowel_ShaftFit	79
swCalloutVariable_AH_DrillPoint_Angle	83
swCalloutVariable_AH_DrillPoint_Msg	84
swCalloutVariable_AH_FlatBottom_Msg	85
swCalloutVariable_AH_OffsetFromSurface_Msg	90
swCalloutVariable_AH_Straight_Depth	77
swCalloutVariable_AH_Straight_Diameter	76
swCalloutVariable_AH_Straight_Farside_Msg	81
swCalloutVariable_AH_Straight_Nearside_Msg	80
swCalloutVariable_AH_Straight_Side	82
swCalloutVariable_AH_StraightThread_Depth	65
swCalloutVariable_AH_StraightThread_Farside_Msg	67
swCalloutVariable_AH_StraightThread_Major_Diameter	63
swCalloutVariable_AH_StraightThread_Nearside_Msg	66
swCalloutVariable_AH_StraightThread_Side	68
swCalloutVariable_AH_StraightThread_Size	64
swCalloutVariable_AH_StraightThread_Tap_Drill_Diameter	62
swCalloutVariable_AH_TaperedThread_Depth	71
swCalloutVariable_AH_TaperedThread_Farside_Msg	74
swCalloutVariable_AH_TaperedThread_Major_Diameter	70
swCalloutVariable_AH_TaperedThread_Nearside_Msg	73
swCalloutVariable_AH_TaperedThread_Side	75
swCalloutVariable_AH_TaperedThread_Size	72
swCalloutVariable_AH_TaperedThread_Tap_Drill_Diameter	69
swCalloutVariable_AH_Thread_Description	92
swCalloutVariable_AH_ThreadAdvance	93
swCalloutVariable_AH_ThroughAll_Msg	91
swCalloutVariable_AH_UptoNext_Msg	87
swCalloutVariable_AH_UptoNextElement_Msg	88
swCalloutVariable_AH_UptoSelection_Msg	89
swCalloutVariable_Counterbore	47
swCalloutVariable_Counterbore_Depth	7
swCalloutVariable_Counterbore_Diameter	8
swCalloutVariable_Counterdrill_Angle	9
swCalloutVariable_Counterdrill_Depth	10
swCalloutVariable_Counterdrill_Diameter	11
swCalloutVariable_Countersink_Angle	12
swCalloutVariable_Countersink_Diameter	13
swCalloutVariable_Depth	14
swCalloutVariable_Description	37
swCalloutVariable_Diameter	15
swCalloutVariable_Drill_Angle	16
swCalloutVariable_Far_Side_Countersink_Angle	17
swCalloutVariable_Far_Side_Countersink_Diameter	18

swCalloutVariable_Fastener_Size	6
swCalloutVariable_Fastener_Type	5
swCalloutVariable_Head_Clearance	19
swCalloutVariable_Hole_Depth	21
swCalloutVariable_Hole_Diameter	20
swCalloutVariable_Major_Diameter	22
swCalloutVariable_Middle_Countersink_Angle	23
swCalloutVariable_Middle_Countersink_Diameter	24
swCalloutVariable_Minor_Diameter	25
swCalloutVariable_Msg_Far_Side	40
swCalloutVariable_Msg_Mid_Side	39
swCalloutVariable_Msg_Near_Side	38
swCalloutVariable_Near_Side_Countersink_Angle	26
swCalloutVariable_Near_Side_Countersink_Diameter	27
swCalloutVariable_NUM_INST	45
swCalloutVariable_Slot_Length	49
swCalloutVariable_Slot_Width	50
swCalloutVariable_Standard	4
swCalloutVariable_Tap_Drill_Depth	28
swCalloutVariable_Tap_Drill_Diameter	29
swCalloutVariable_Thread_Angle	30
swCalloutVariable_Thread_Class	46
swCalloutVariable_Thread_Depth	32
swCalloutVariable_Thread_Description	41
swCalloutVariable_Thread_Diameter	31
swCalloutVariable_Thread_Diameter_Only	48
swCalloutVariable_Thread_Series	43
swCalloutVariable_Thread_Size	42
swCalloutVariable_Thru	44
swCalloutVariable_Thru_Hole_Depth	33
swCalloutVariable_Thru_Hole_Diameter	34
swCalloutVariable_Thru_Tap_Depth	35
swCalloutVariable_Thru_Tap_Drill_Diameter	36

 See Also

[SolidWorks.Interop.swconst Namespace](#)

swCalloutVariableType_e (Type)

SOLIDWORKS API Enumerations

swCalloutVariableType_e Enumeration

See Also

[Send comments on this topic.](#)

 

SolidWorks.Interop.swconst Namespace : swCalloutVariableType_e Enumeration

Types of general hole callout variables.

 Syntax

Visual Basic (Declaration)

Public Enum swCalloutVariableType_e
Inherits System.Enum

Visual Basic (Usage)  Copy Code

Dim instance As [swCalloutVariableType_e](#)

C#

public enum swCalloutVariableType_e : System.Enum

C++/CLI

public enum class swCalloutVariableType_e : public System.Enum

 Members

Member	Description
swCalloutVariableType_Angle	2
swCalloutVariableType_Length	1
swCalloutVariableType_String	3

 See Also

[SolidWorks.Interop.swconst Namespace](#)

swCameraPositionType_e (Type)

SOLIDWORKS API Enumerations

swCameraPositionType_e Enumeration

See Also

 

[SolidWorks.Interop.swconst Namespace](#) : swCameraPositionType_e Enumeration

Camera position styles.

[Send comments on this topic.](#)

Syntax

Visual Basic (Declaration)

```
Public Enum swCameraPositionType_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swCameraPositionType\_e
```

C#

```
public enum swCameraPositionType_e : System.Enum
```

C++/CLI

```
public enum class swCameraPositionType_e : public System.Enum
```

Members

Member	Description
swCameraPosition_Cartesian	1
swCameraPosition_Spherical	2

See Also

[SolidWorks.Interop.swconst Namespace](#)

swCameraType_e (Type)

SOLIDWORKS API Enumerations

swCameraType_e Enumeration

See Also

[Send comments on this topic.](#)

 

[SolidWorks.Interop.swconst Namespace](#) : swCameraType_e Enumeration

Camera types.

 Syntax

Visual Basic (Declaration)

```
Public Enum swCameraType_e
    Inherits System.Enum
```

Visual Basic (Usage)  Copy Code

```
Dim instance As swCameraType\_e
```

C#

```
public enum swCameraType_e : System.Enum
```

C++/CLI

```
public enum class swCameraType_e : public System.Enum
```

 Members

Member	Description
swCameraType_AimedAtTarget	1
swCameraType_Floating	2

 See Also

[SolidWorks.Interop.swconst Namespace](#)

swCamMateEntityType_e (Type)

SOLIDWORKS API Enumerations

swCamMateEntityType_e Enumeration

See Also

[Send comments on this topic.](#)

 

[SolidWorks.Interop.swconst Namespace](#) : swCamMateEntityType_e Enumeration

Cam-follower mate entity types.

 Syntax

Visual Basic (Declaration)

Public Enum swCamMateEntityType_e
Inherits System.Enum

Visual Basic (Usage)  Copy Code

Dim instance As [swCamMateEntityType_e](#)

C#

public enum swCamMateEntityType_e : System.Enum

C++/CLI

public enum class swCamMateEntityType_e : public System.Enum

 Members

Member	Description
swCamMateEntityType_CamFollower	1 = Follower component
swCamMateEntityType_CamPath	0 = Cam component

 See Also

[SolidWorks.Interop.swconst Namespace](#)

swCavityScaleType_e (Type)

SOLIDWORKS API Enumerations

swCavityScaleType_e Enumeration

[See Also](#)

[Send comments on this topic.](#)

 

SolidWorks.Interop.swconst Namespace : swCavityScaleType_e Enumeration

Cavity scale types.

Syntax

Visual Basic (Declaration)

```
Public Enum swCavityScaleType_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swCavityScaleType\_e
```

C#

```
public enum swCavityScaleType_e : System.Enum
```

C++/CLI

```
public enum class swCavityScaleType_e : public System.Enum
```

Members

Member	Description
swAboutCentroid	0
swAboutCoordinateSystem	3
swAboutMoldBaseOrigin	2
swAboutOrigin	1

See Also

[SolidWorks.Interop.swconst Namespace](#)

swCellEquationStatus_e (Type)

SOLIDWORKS API Enumerations

swCellEquationStatus_e Enumeration

See Also

[SolidWorks.Interop.swconst Namespace](#) : swCellEquationStatus_e Enumeration

Cell equation error codes.

[Send comments on this topic.](#)

Syntax

Visual Basic (Declaration)

```
Public Enum swCellEquationStatus_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swCellEquationStatus\_e
```

C#

```
public enum swCellEquationStatus_e : System.Enum
```

C++/CLI

```
public enum class swCellEquationStatus_e : public System.Enum
```

Members

Member	Description
swCellEquationStatus_InvalidEquation	2
swCellEquationStatus_InvalidIndex	1
swCellEquationStatus_Success	0

See Also

[SolidWorks.Interop.swconst Namespace](#)

swCenterLineMarkOrient_e (Type)

SOLIDWORKS API Enumerations

swCenterLineMarkOrient_e Enumeration

See Also

[Send comments on this topic.](#)

 

[SolidWorks.Interop.swconst Namespace](#) : swCenterLineMarkOrient_e Enumeration

Centerline mark orientation.

 Syntax

Visual Basic (Declaration)

```
Public Enum swCenterLineMarkOrient_e
    Inherits System.Enum
```

Visual Basic (Usage)  Copy Code

```
Dim instance As swCenterLineMarkOrient\_e
```

C#

```
public enum swCenterLineMarkOrient_e : System.Enum
```

C++/CLI

```
public enum class swCenterLineMarkOrient_e : public System.Enum
```

 Members

Member	Description
swCenterLineMarkOrientToSheet	1
swCenterLineMarkOrientToSlot	0

 See Also

[SolidWorks.Interop.swconst Namespace](#)

swCenterMarkConnectionLine_e (Type)

SOLIDWORKS API Enumerations

swCenterMarkConnectionLine_e Enumeration

See Also

 

[SolidWorks.Interop.swconst Namespace](#) : swCenterMarkConnectionLine_e Enumeration

Visibility options for connection lines of center marks. [Bitmask](#).

[Send comments on this topic.](#)

Syntax

Visual Basic (Declaration)

Public Enum swCenterMarkConnectionLine_e
Inherits System.Enum

Visual Basic (Usage)

Dim instance As [swCenterMarkConnectionLine_e](#)

C#

public enum swCenterMarkConnectionLine_e : System.Enum

C++/CLI

public enum class swCenterMarkConnectionLine_e : public System.Enum

Members

Member	Description
swCenterMark_ShowBaseCenterMarkLines	8 or 0x8
swCenterMark_ShowCircularConnectLines	2 or 0x2
swCenterMark_ShowLinearConnectLines	1 or 0x1
swCenterMark_ShowNoConnectLines	0 or 0x0
swCenterMark_ShowRadialConnectLines	4 or 0x4

See Also

[SolidWorks.Interop.swconst Namespace](#)

swCenterMarkHandle_e (Type)

SOLIDWORKS API Enumerations

swCenterMarkHandle_e Enumeration

[See Also](#)

[Send comments on this topic.](#)

 

SolidWorks.Interop.swconst Namespace : swCenterMarkHandle_e Enumeration

Direction of center mark handle.

Syntax

Visual Basic (Declaration)

Public Enum swCenterMarkHandle_e
Inherits System.Enum

Visual Basic (Usage)

Dim instance As [swCenterMarkHandle_e](#)

C#

public enum swCenterMarkHandle_e : System.Enum

C++/CLI

public enum class swCenterMarkHandle_e : public System.Enum

Members

Member	Description
swCenterMarkHandle_Down	2
swCenterMarkHandle_Left	1
swCenterMarkHandle_Right	3
swCenterMarkHandle_Up	0

See Also

[SolidWorks.Interop.swconst Namespace](#)

swCenterMarkStyle_e (Type)

SOLIDWORKS API Enumerations

swCenterMarkStyle_e Enumeration

[See Also](#)

[Send comments on this topic.](#)

 

SolidWorks.Interop.swconst Namespace : swCenterMarkStyle_e Enumeration

Center mark styles.

Syntax

Visual Basic (Declaration)

```
Public Enum swCenterMarkStyle_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swCenterMarkStyle\_e
```

C#

```
public enum swCenterMarkStyle_e : System.Enum
```

C++/CLI

```
public enum class swCenterMarkStyle_e : public System.Enum
```

Members

Member	Description
swCenterMark_CircularGroup	4
swCenterMark_LinearGroup	3
swCenterMark_NonAnnotation	1
swCenterMark_Single	2

See Also

[SolidWorks.Interop.swconst Namespace](#)

swChainPatternAlignment_e (Type)

SOLIDWORKS API Enumerations

swChainPatternAlignment_e Enumeration

See Also

 

SolidWorks.Interop.swconst Namespace : swChainPatternAlignment_e Enumeration

Chain pattern alignments.

[Send comments on this topic.](#)

 Syntax

Visual Basic (Declaration)

Public Enum swChainPatternAlignment_e
Inherits System.Enum

Visual Basic (Usage)

Dim instance As [swChainPatternAlignment_e](#)

C#

public enum swChainPatternAlignment_e : System.Enum

C++/CLI

public enum class swChainPatternAlignment_e : public System.Enum

 Members

Member	Description
swChainPatternAlignToSeed	0
swChainPatternTangentToCurve	1

 See Also

[SolidWorks.Interop.swconst Namespace](#)

swChainPatternOptions_e (Type)

SOLIDWORKS API Enumerations

swChainPatternOptions_e Enumeration

See Also

[Send comments on this topic.](#)

 

[SolidWorks.Interop.swconst Namespace](#) : swChainPatternOptions_e Enumeration

Chain pattern options.

 Syntax

Visual Basic (Declaration)

```
Public Enum swChainPatternOptions_e
    Inherits System.Enum
```

Visual Basic (Usage)  Copy Code

```
Dim instance As swChainPatternOptions\_e
```

C#

```
public enum swChainPatternOptions_e : System.Enum
```

C++/CLI

```
public enum class swChainPatternOptions_e : public System.Enum
```

 Members

Member	Description
swChainPatternDynamic	1 = Calculates the mates between each pattern instance
swChainPatternStatic	0 = Copies each pattern instance without creating mates

 See Also

[SolidWorks.Interop.swconst Namespace](#)

swChainPatternPitchMethod_e (Type)

SOLIDWORKS API Enumerations

swChainPatternPitchMethod_e Enumeration

See Also

 

[SolidWorks.Interop.swconst Namespace](#) : swChainPatternPitchMethod_e Enumeration

Chain pattern pitch methods.

[Send comments on this topic.](#)

Syntax

Visual Basic (Declaration)

Public Enum swChainPatternPitchMethod_e
Inherits System.Enum

Visual Basic (Usage)

Dim instance As [swChainPatternPitchMethod_e](#)

C#

public enum swChainPatternPitchMethod_e : System.Enum

C++/CLI

public enum class swChainPatternPitchMethod_e : public System.Enum

Members

Member	Description
swChainPatternConnectedLinkage	2
swChainPatternDistance	0
swChainPatternDistanceLinkage	1

See Also

[SolidWorks.Interop.swconst Namespace](#)

swChamferType_e (Type)

SOLIDWORKS API Enumerations

swChamferType_e Enumeration

See Also

[Send comments on this topic.](#)

 [SolidWorks.Interop.swconst Namespace](#) : swChamferType_e Enumeration

Chamfer types.

Syntax

Visual Basic (Declaration)

```
Public Enum swChamferType_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swChamferType\_e
```

C#

```
public enum swChamferType_e : System.Enum
```

C++/CLI

```
public enum class swChamferType_e : public System.Enum
```

Members

Member	Description
swChamferAngleDistance	1
swChamferDistanceDistance	2
swChamferEqualDistance	16
swChamferVertex	3

Remarks

These values can be bitwise OR'd to get the desired chamfer type.

See Also

[SolidWorks.Interop.swconst Namespace](#)

swCheckClearanceBetween_e (Type)

SOLIDWORKS API Enumerations

swCheckClearanceBetween_e Enumeration

See Also

 

[SolidWorks.Interop.swconst Namespace](#) : swCheckClearanceBetween_e Enumeration

Between options for clearance verification.

[Send comments on this topic.](#)

Syntax

Visual Basic (Declaration)

```
Public Enum swCheckClearanceBetween_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swCheckClearanceBetween\_e
```

C#

```
public enum swCheckClearanceBetween_e : System.Enum
```

C++/CLI

```
public enum class swCheckClearanceBetween_e : public System.Enum
```

Members

Member	Description
swCheckClearanceBetweenSelectedItems	0
swCheckClearanceBetweenSelectedItemsAndRestAssembly	1

See Also

[SolidWorks.Interop.swconst Namespace](#)

swCheckInterferenceOption_e (Type)

SOLIDWORKS API Enumerations

swCheckInterferenceOption_e Enumeration

See Also

[SolidWorks.Interop.swconst Namespace](#) : swCheckInterferenceOption_e Enumeration

Check interference options. [Bitmask](#).

Syntax

Visual Basic (Declaration)

```
Public Enum swCheckInterferenceOption_e
    Inherits System.Enum
```

Visual Basic (Usage)

Copy Code

```
Dim instance As swCheckInterferenceOption\_e
```

C#

```
public enum swCheckInterferenceOption_e : System.Enum
```

C++/CLI

```
public enum class swCheckInterferenceOption_e : public System.Enum
```

Members

Member	Description
swBodyInterference_IncludeCoincidentFaces	2 or 0x2; Abutment (i.e., faces touching each other) type of clash
swBodyInterference_OptionDefault	1 or 0x1; If this option specified, then swBodyInterference_IncludeCoincidentFaces and swBodyInterference_ReturnInterferingObject are set to false
swBodyInterference_ReturnInterferingObject	4 or 0x4; Return face and body arrays

See Also

[SolidWorks.Interop.swconst Namespace](#)

swCheckOutOfDate_e (Type)

SOLIDWORKS API Enumerations

swCheckOutOfDate_e Enumeration

[See Also](#)

[Send comments on this topic.](#)

 

[SolidWorks.Interop.swconst Namespace](#) : swCheckOutOfDate_e Enumeration

Check for out-of-date lightweight components options.

 Syntax

Visual Basic (Declaration)

Public Enum swCheckOutOfDate_e
Inherits System.Enum

Visual Basic (Usage)

Dim instance As [swCheckOutOfDate_e](#)

 [Copy Code](#)

C#

public enum swCheckOutOfDate_e : System.Enum

C++/CLI

public enum class swCheckOutOfDate_e : public System.Enum

 Members

Member	Description
swCheckOutOfDate_AlwaysResolve	Resolve out-of-date components; other lightweight components are not resolved
swCheckOutOfDate_DoNotCheck	Do not check
swCheckOutOfDate_Indicate	Mark out-of-date components with a broken feather; good lightweight models are not marked with the broken feather; instead, they are marked with the regular feather

 See Also

[SolidWorks.Interop.swconst Namespace](#)

swCheckSpellingOptions_e (Type)

SOLIDWORKS API Enumerations

swCheckSpellingOptions_e Enumeration

See Also

 

[SolidWorks.Interop.swconst Namespace](#) : swCheckSpellingOptions_e Enumeration

Spell check options. [Bitmask](#).

[Send comments on this topic.](#)

 Syntax

Visual Basic (Declaration)

Public Enum swCheckSpellingOptions_e
Inherits System.Enum

Visual Basic (Usage)

Dim instance As [swCheckSpellingOptions_e](#)

C#

public enum swCheckSpellingOptions_e : System.Enum

C++/CLI

public enum class swCheckSpellingOptions_e : public System.Enum

 Members

Member	Description
swSpellingIgnoreCapitalizedWords	8 or 0x8; Capitalized words are not checked
swSpellingIgnoreInternetAndFiles	16 or 0x10; Words containing a web address are not checked
swSpellingIgnoreMixedCase	2 or 0x2; Words that are mixed-case (upper case and lowercase, e.g., eDrawings) are not checked
swSpellingIgnoreUpperCase	1 or 0x1; Words that are all uppercase are not checked
swSpellingIgnoreWordsWithNumbers	4 or 0x4; Words containing both letters and numbers are not checked
swSpellingLeaveEngineRunning	32 or 0x20; Do not stop Microsoft Word, which is the spell-check engine, after checking the first and any subsequent annotations if you have a significant number of annotations to spell check; however, on the last use of IAnnotation.CheckSpelling , you must disable this flag so that Microsoft Word is shut down after that call

 See Also

[SolidWorks.Interop.swconst Namespace](#)

[SolidWorks.Interop.swconst Namespace](#)

swChildComponentInBOMOption_e (Type)

SOLIDWORKS API Enumerations

swChildComponentInBOMOption_e Enumeration

See Also

 

[SolidWorks.Interop.swconst Namespace](#) : swChildComponentInBOMOption_e Enumeration

Child component display options in Bills of Materials (BOM) for assemblies and for parts that have weldment/sheet metal cut lists.

[Send comments on this topic.](#)

Syntax

Visual Basic (Declaration)

```
Public Enum swChildComponentInBOMOption_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swChildComponentInBOMOption\_e
```

C#

```
public enum swChildComponentInBOMOption_e : System.Enum
```

C++/CLI

```
public enum class swChildComponentInBOMOption_e : public System.Enum
```

Members

Member	Description
swChildComponent_Hide	1 = Child components might be listed individually, depending on the properties that you selected when you created the BOM
swChildComponent_Promote	3 = The model's configuration dissolves when it appears in a BOM; all of its child components are promoted one level
swChildComponent_Show	2 = Child components appear as single items in the BOM

See Also

[SolidWorks.Interop.swconst Namespace](#)

swClearanceType_e (Type)

SOLIDWORKS API Enumerations

swClearanceType_e Enumeration

See Also

[Send comments on this topic.](#)

 

[SolidWorks.Interop.swconst Namespace](#) : swClearanceType_e Enumeration

Clearance verification types.

 Syntax

Visual Basic (Declaration)

Public Enum swClearanceType_e
Inherits System.Enum

Visual Basic (Usage)  [Copy Code](#)

Dim instance As [swClearanceType_e](#)

C#

public enum swClearanceType_e : System.Enum

C++/CLI

public enum class swClearanceType_e : public System.Enum

 Members

Member	Description
swClearanceType_Coincident	1
swClearanceType_Distance	0

 See Also

[SolidWorks.Interop.swconst Namespace](#)

swClearanceVerificationSetEntityErrors_e (Type)

SOLIDWORKS API Enumerations

swClearanceVerificationSetEntityErrors_e Enumeration

[See Also](#)

[Send comments on this topic.](#)

 

[SolidWorks.Interop.swconst Namespace](#) : swClearanceVerificationSetEntityErrors_e Enumeration

Error codes when setting entities for clearance verification.

Syntax

Visual Basic (Declaration)

```
Public Enum swClearanceVerificationSetEntityErrors_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swClearanceVerificationSetEntityErrors\_e
```

C#

```
public enum swClearanceVerificationSetEntityErrors_e : System.Enum
```

C++/CLI

```
public enum class swClearanceVerificationSetEntityErrors_e : public System.Enum
```

Members

Member	Description
swClearanceVerification_swComponentAlreadySelected	2 = Same component added twice or component added whose face is in face array
swClearanceVerification_swFacesAlreadySelected	1 = Same face added twice
swClearanceVerification_swInsufficientEntities	5 = Face and component arrays are empty
swClearanceVerification_swInvalidComponent	3 = Not a valid SOLIDWORKS component
swClearanceVerification_swInvalidFace	4 = Not a valid SOLIDWORKS face
swClearanceVerification_swSuccess	0
swClearanceVerification_Unknown	-1

See Also

[SolidWorks.Interop.swconst Namespace](#)

swClosedCornerTypes_e (Type)

SOLIDWORKS API Enumerations

swClosedCornerTypes_e Enumeration

[See Also](#)

[Send comments on this topic.](#)

 

[SolidWorks.Interop.swconst Namespace](#) : swClosedCornerTypes_e Enumeration

Closed corner types.

Syntax

Visual Basic (Declaration)

```
Public Enum swClosedCornerTypes_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swClosedCornerTypes\_e
```

C#

```
public enum swClosedCornerTypes_e : System.Enum
```

C++/CLI

```
public enum class swClosedCornerTypes_e : public System.Enum
```

Members

Member	Description
swClosedCornerTypeButt	1
swClosedCornerTypeOverlap	2
swClosedCornerTypeUnderlap	3

See Also

[SolidWorks.Interop.swconst Namespace](#)

swCloseReopenError_e (Type)

SOLIDWORKS API Enumerations

swCloseReopenError_e Enumeration

See Also

 SolidWorks.Interop.swconst Namespace : swCloseReopenError_e Enumeration

Close and reopen errors.

[Send comments on this topic.](#)

Syntax

Visual Basic (Declaration)

```
Public Enum swCloseReopenError_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swCloseReopenError\_e
```

C#

```
public enum swCloseReopenError_e : System.Enum
```

C++/CLI

```
public enum class swCloseReopenError_e : public System.Enum
```

Members

Member	Description
swCloseReopenCloseDocError	5; error occurred during close
swCloseReopenInvalidDocError	4; document is not a drawing
swCloseReopenLoadFileNotFoundError	7; file path specified for document to reopen does not exist
swCloseReopenLoadFilePathEmptyError	13; file path of document to reopen is empty
swCloseReopenLoadFilePathNonDrawingError	14; file to reopen is not a drawing
swCloseReopenLoadFutureVersionError	9; file to reopen is a future version
swCloseReopenLoadGenericError	6; error occurred during reopen
swCloseReopenLoadInvalidFileTypeError	8; file type is not valid
swCloseReopenLoadLiquidMachineDocError	11; LiquidMachine document error
swCloseReopenLoadSameTitleAlreadyOpenError	10; file with the same title is already open
swCloseReopenModifiedError	12; unable to close the document because changes were made to the document, and swCloseReopenOption_e.swCloseReopenOption_DiscardChanges was not set
swCloseReopenNoError	0; no error
swCloseReopenNoInputDocError	2; input document is null
swCloseReopenOutputDocPointerError	3; output document is null
swCloseReopenUnknownError	1; unknown error

See Also

[SolidWorks.Interop.swconst Namespace](#)

swCloseReopenOption_e (Type)

SOLIDWORKS API Enumerations

swCloseReopenOption_e Enumeration

See Also

SolidWorks.Interop.swconst Namespace : swCloseReopenOption_e Enumeration

File close and reopen options. [Bitmask](#).

[Send comments on this topic.](#)

Syntax

Visual Basic (Declaration)

Public Enum swCloseReopenOption_e
Inherits System.Enum

Visual Basic (Usage)

Dim instance As [swCloseReopenOption_e](#)

C#

public enum swCloseReopenOption_e : System.Enum

C++/CLI

public enum class swCloseReopenOption_e : public System.Enum

Members

Member	Description
swCloseReopenOption_DiscardChanges	2 or 0x2; include this option to discard any changes to the document before reopening it; if you exclude this option and there are changes, ISldWorks::CloseAndReopen fails and returns swCloseReopenError_e.swCloseReopenModifiedError
swCloseReopenOption_ExitDetailingMode	8 or 0x8; include this option to reopen model drawings as resolved; if excluded by ISldWorks::CloseAndReopen2 , keeps a model drawing in detailing mode on reopen
swCloseReopenOption_MatchSheet	4 or 0x4; include this option to open the same sheet that was active during closing
swCloseReopenOption_ReadOnly	1 or 0x1; include this option to open the drawing document in read-only mode

See Also

[SolidWorks.Interop.swconst Namespace](#)

swCollabCheckReadOnlyModifiedInterval_e (Type)

SOLIDWORKS API Enumerations

swCollabCheckReadOnlyModifiedInterval_e Enumeration

[Send comments on this topic.](#)

[See Also](#)

 

[SolidWorks.Interop.swconst Namespace](#) : swCollabCheckReadOnlyModifiedInterval_e Enumeration

Intervals when to check files for modifications that were opened read-only in a multi-user environment.

Syntax

Visual Basic (Declaration)

```
Public Enum swCollabCheckReadOnlyModifiedInterval_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swCollabCheckReadOnlyModifiedInterval\_e
```

C#

```
public enum swCollabCheckReadOnlyModifiedInterval_e : System.Enum
```

C++/CLI

```
public enum class swCollabCheckReadOnlyModifiedInterval_e : public System.Enum
```

Members

Member	Description
swCollabCheckReadOnlyModifiedInterval_10min	5
swCollabCheckReadOnlyModifiedInterval_15min	6
swCollabCheckReadOnlyModifiedInterval_1min	1
swCollabCheckReadOnlyModifiedInterval_20min	7
swCollabCheckReadOnlyModifiedInterval_2min	2
swCollabCheckReadOnlyModifiedInterval_30min	8
swCollabCheckReadOnlyModifiedInterval_3min	3
swCollabCheckReadOnlyModifiedInterval_45min	9
swCollabCheckReadOnlyModifiedInterval_5min	4
swCollabCheckReadOnlyModifiedInterval_60min	10

See Also

[SolidWorks.Interop.swconst Namespace](#)

swCollinearChainDimArrowHeadStyle_e (Type)

SOLIDWORKS API Enumerations

swCollinearChainDimArrowHeadStyle_e Enumeration

[Send comments on this topic.](#)

[See Also](#)



[SolidWorks.Interop.swconst Namespace](#) : swCollinearChainDimArrowHeadStyle_e Enumeration

Collinear chain dimension arrow head styles.

Syntax

Visual Basic (Declaration)

```
Public Enum swCollinearChainDimArrowHeadStyle_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swCollinearChainDimArrowHeadStyle\_e
```

C#

```
public enum swCollinearChainDimArrowHeadStyle_e : System.Enum
```

C++/CLI

```
public enum class swCollinearChainDimArrowHeadStyle_e : public System.Enum
```

Members

Member	Description
swCollinearChainDimArrowHeadStyle_Oblique	1
swCollinearChainDimArrowHeadStyle_Point	0

See Also

[SolidWorks.Interop.swconst Namespace](#)

swCollisionDetectionResults_e (Type)

SOLIDWORKS API Enumerations

swCollisionDetectionResults_e Enumeration

See Also

[Send comments on this topic.](#)

 [SolidWorks.Interop.swconst Namespace](#) : swCollisionDetectionResults_e Enumeration

Collision detection results.

 Syntax

Visual Basic (Declaration)

```
Public Enum swCollisionDetectionResults_e
    Inherits System.Enum
```

Visual Basic (Usage)  Copy Code

```
Dim instance As swCollisionDetectionResults\_e
```

C#

```
public enum swCollisionDetectionResults_e : System.Enum
```

C++/CLI

```
public enum class swCollisionDetectionResults_e : public System.Enum
```

 Members

Member	Description
swCollisionDetectionResult_CollisionDetected	1
swCollisionDetectionResult_FailedNotEnoughGroups	-1 = You must define more than one collision group containing two or more unsuppressed components in different collision groups
swCollisionDetectionResult_NoCollision	0

 See Also

[SolidWorks.Interop.swconst Namespace](#)

swCollisionGroupApplyTransformErrors_e (Type)

SOLIDWORKS API Enumerations

swCollisionGroupApplyTransformErrors_e Enumeration

See Also

[SolidWorks.Interop.swconst Namespace](#) : swCollisionGroupApplyTransformErrors_e Enumeration

Errors when applying transforms to collision groups.

Syntax

Visual Basic (Declaration)

Public Enum swCollisionGroupApplyTransformErrors_e
Inherits System.Enum

Visual Basic (Usage)

Dim instance As [swCollisionGroupApplyTransformErrors_e](#)

C#

public enum swCollisionGroupApplyTransformErrors_e : System.Enum

C++/CLI

public enum class swCollisionGroupApplyTransformErrors_e : public System.Enum

Members

Member	Description
swCollisionGroupApplyTransformErrors_GroupRemoved	3 = The specified collision group is no longer available
swCollisionGroupApplyTransformErrors_InvalidTransforms	2 = Array of transforms contains a null pointer for one or more elements or a pointer to an object other than an IMathTransform
swCollisionGroupApplyTransformErrors_None	0
swCollisionGroupApplyTransformErrors_SizeMismatch	1 = Array of transforms does not contain one IMathTransform for each component in the collision group

See Also

[SolidWorks.Interop.swconst Namespace](#)

swCollisionGroupSetComponentsErrors_e (Type)

SOLIDWORKS API Enumerations

swCollisionGroupSetComponentsErrors_e Enumeration

See Also

 

[SolidWorks.Interop.swconst Namespace](#) : swCollisionGroupSetComponentsErrors_e Enumeration

Errors when setting components in collision groups.

[Send comments on this topic.](#)

Syntax

Visual Basic (Declaration)

```
Public Enum swCollisionGroupSetComponentsErrors_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swCollisionGroupSetComponentsErrors\_e
```

C#

```
public enum swCollisionGroupSetComponentsErrors_e : System.Enum
```

C++/CLI

```
public enum class swCollisionGroupSetComponentsErrors_e : public System.Enum
```

Members

Member	Description
swCollisionGroupSetComponentsErrors.ComponentsAddedElsewhere	2 = One or more components have already been added to a different collision group
swCollisionGroupSetComponentsErrors.GroupRemoved	3 = The specified collision group is no longer available
swCollisionGroupSetComponentsErrors.InvalidComponents	1 = Components from a different assembly cannot be included in this collision detection
swCollisionGroupSetComponentsErrors.None	0

See Also

[SolidWorks.Interop.swconst Namespace](#)

swCollisionManagerSetAssemblyErrors_e (Type)

SOLIDWORKS API Enumerations

swCollisionManagerSetAssemblyErrors_e Enumeration

See Also

[Send comments on this topic.](#)

 

[SolidWorks.Interop.swconst Namespace](#) : swCollisionManagerSetAssemblyErrors_e Enumeration

Return codes when setting the assembly for the collision detection manager.

 Syntax

Visual Basic (Declaration)

```
Public Enum swCollisionManagerSetAssemblyErrors_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swCollisionManagerSetAssemblyErrors\_e
```

C#

```
public enum swCollisionManagerSetAssemblyErrors_e : System.Enum
```

C++/CLI

```
public enum class swCollisionManagerSetAssemblyErrors_e : public System.Enum
```

 Members

Member	Description
swCollisionManagerSetAssemblyErrors_InvalidModelDocument	1
swCollisionManagerSetAssemblyErrors_OtherAssemblyActive	2
swCollisionManagerSetAssemblyErrors_Success	0

 See Also

[SolidWorks.Interop.swconst Namespace](#)

swColorsBackgroundAppearance_e (Type)

SOLIDWORKS API Enumerations

swColorsBackgroundAppearance_e Enumeration

See Also

▼

[SolidWorks.Interop.swconst Namespace](#) : swColorsBackgroundAppearance_e Enumeration

Backgrounds for graphics area.

[Send comments on this topic.](#)

Syntax

Visual Basic (Declaration)

```
Public Enum swColorsBackgroundAppearance_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swColorsBackgroundAppearance\_e
```

C#

```
public enum swColorsBackgroundAppearance_e : System.Enum
```

C++/CLI

```
public enum class swColorsBackgroundAppearance_e : public System.Enum
```

Members

Member	Description
swColorsBackgroundAppearance_DocumentScene	3
swColorsBackgroundAppearance_Gradient	1
swColorsBackgroundAppearance_Image	2
swColorsBackgroundAppearance_Plain	0

Remarks

Use with [swUserPreferenceIntegerValue_e.swColorsBackgroundAppearance](#).

Use the system-level string [swUserPreferenceStringValue_e.swColorsBackgroundImageFile](#) to set the name of the file containing the image to display as the background of the SOLIDWORKS graphics area.

See Also

[SolidWorks.Interop.swconst Namespace](#)

swColumnTypeStatus_e (Type)

SOLIDWORKS API Enumerations

swColumnTypeStatus_e Enumeration

See Also

[Send comments on this topic.](#)

 

[SolidWorks.Interop.swconst Namespace](#) : swColumnTypeStatus_e Enumeration

Table column error codes.

 Syntax

Visual Basic (Declaration)

```
Public Enum swColumnTypeStatus_e
    Inherits System.Enum
```

Visual Basic (Usage)  Copy Code

```
Dim instance As swColumnTypeStatus\_e
```

C#

```
public enum swColumnTypeStatus_e : System.Enum
```

C++/CLI

```
public enum class swColumnTypeStatus_e : public System.Enum
```

 Members

Member	Description
swColumnTypeStatus_InvalidIndex	1
swColumnTypeStatus_InvalidPropertyType	2
swColumnTypeStatus_Success	0

 See Also

[SolidWorks.Interop.swconst Namespace](#)

swCombineBodiesOperationType_e (Type)

SOLIDWORKS API Enumerations

swCombineBodiesOperationType_e Enumeration

[See Also](#)

 

[SolidWorks.Interop.swconst Namespace](#) : swCombineBodiesOperationType_e Enumeration

Combine bodies operation types.

[Send comments on this topic.](#)

Syntax

Visual Basic (Declaration)

```
Public Enum swCombineBodies0perationType_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swCombineBodies0perationType\_e
```

C#

```
public enum swCombineBodies0perationType_e : System.Enum
```

C++/CLI

```
public enum class swCombineBodies0perationType_e : public System.Enum
```

Members

Member	Description
swCombineBodiesOperationAdd	0
swCombineBodiesOperationCommon	2
swCombineBodiesOperationSubtract	1

See Also

[SolidWorks.Interop.swconst Namespace](#)

swCommand_e (Type)

SOLIDWORKS API Enumerations

swCommand_e Enumeration

See Also

Send comments on this topic.

SolidWorks.Interop.swconst Namespace : swCommand_e Enumeration

Dialog or file to display.

Syntax

Visual Basic (Declaration)

Public Enum swCommand_e
Inherits System.Enum

Visual Basic (Usage)

Dim instance As [swCommand_e](#)

C#

public enum swCommand_e : System.Enum

C++/CLI

public enum class swCommand_e : public System.Enum

Members

Member	Description
swCurrentTipOfDayString	8
swFileNew	1 = Display the File, New dialog
swFileOpen	0 = Display the File, Open dialog
swFontSize	10 = Reserved; not in use
swInterfaceBrightnessTheme	11 = Get current user-interface brightness theme
swNextTipOfDayString	7
swOpenHTMLHelp	3 = Given the path and compiled HTML filename (has .chm file name extension), this option opens the HTML Help file in a new window; if no path is given, the current language folder below the folder in which sldworks.exe exists is used
swOpenRecentFile	2 = Given a number between ID_FILE_MRU_FILE1 and ID_FILE_MRU_FILE1 + 9, this option opens the matching file from the list of most recently used files
swPrevTipOfDayString	9
swReserved	4 = Reserved; not in use
swUserExperienceLevel	6 = User experience level: new user, existing user to this revision, or existing user but new to this revision
swVerticalMkt	5 = Current vertical market user-interface sett

See Also

[SolidWorks.Interop.swconst Namespace](#)

swCommandFlyoutStyle_e (Type)

SOLIDWORKS API Enumerations

swCommandFlyoutStyle_e Enumeration

[See Also](#)

 

[SolidWorks.Interop.swconst Namespace](#) : swCommandFlyoutStyle_e Enumeration

Types of FlyoutGroup.

[Send comments on this topic.](#)

Syntax

Visual Basic (Declaration)

```
Public Enum swCommandFlyoutStyle_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swCommandFlyoutStyle\_e
```

C#

```
public enum swCommandFlyoutStyle_e : System.Enum
```

C++/CLI

```
public enum class swCommandFlyoutStyle_e : public System.Enum
```

Members

Member	Description
swCommandFlyoutStyle_Favorite	1 = the first command in the menu list is the immediate action for the main button
swCommandFlyoutStyle_LastUsed	2 = the last used command in the menu list is the immediate action for the main button
swCommandFlyoutStyle_Simple	0 = no immediate action is available for the main button

Remarks

Context-sensitive menus support only the swCommandFlyoutStyle_Simple flyout style.

See Also

[SolidWorks.Interop.swconst Namespace](#)

swCommandItemType_e (Type)

SOLIDWORKS API Enumerations

swCommandItemType_e Enumeration

See Also

 

[SolidWorks.Interop.swconst Namespace](#) : swCommandItemType_e Enumeration

Types of command items. [Bitmask](#).

[Send comments on this topic.](#)

Syntax

Visual Basic (Declaration)

```
Public Enum swCommandItemType_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swCommandItemType\_e
```

C#

```
public enum swCommandItemType_e : System.Enum
```

C++/CLI

```
public enum class swCommandItemType_e : public System.Enum
```

Members

Member	Description
swMenuItem	1
swToolBarItem	2

See Also

[SolidWorks.Interop.swconst Namespace](#)

swCommandTabButtonFlyoutStyle_e (Type)

SOLIDWORKS API Enumerations

swCommandTabButtonFlyoutStyle_e Enumeration

[See Also](#)

[Send comments on this topic.](#)

 

[SolidWorks.Interop.swconst Namespace](#) : swCommandTabButtonFlyoutStyle_e Enumeration

CommandManager tab button flyout styles. [Bitmask](#).

 Syntax

Visual Basic (Declaration)

Public Enum swCommandTabButtonFlyoutStyle_e
Inherits System.Enum

Visual Basic (Usage)

Dim instance As [swCommandTabButtonFlyoutStyle_e](#)

 [Copy Code](#)

C#

public enum swCommandTabButtonFlyoutStyle_e : System.Enum

C++/CLI

public enum class swCommandTabButtonFlyoutStyle_e : public System.Enum

 Members

Member	Description
swCommandTabButton_ActionFlyout	32 or 0x20
swCommandTabButton_NoFlyout	8 or 0x8
swCommandTabButton_SimpleFlyout	16 or 0x10

 See Also

[SolidWorks.Interop.swconst Namespace](#)

swCommandTabButtonTextDisplay_e (Type)

SOLIDWORKS API Enumerations

swCommandTabButtonTextDisplay_e Enumeration

See Also

 

[SolidWorks.Interop.swconst Namespace](#) : swCommandTabButtonTextDisplay_e Enumeration

CommandManager tab button text display. [Bitmask](#).

[Send comments on this topic.](#)

Syntax

Visual Basic (Declaration)

Public Enum swCommandTabButtonTextDisplay_e
Inherits System.Enum

Visual Basic (Usage)

Dim instance As [swCommandTabButtonTextDisplay_e](#)

C#

public enum swCommandTabButtonTextDisplay_e : System.Enum

C++/CLI

public enum class swCommandTabButtonTextDisplay_e : public System.Enum

Members

Member	Description
swCommandTabButton_NoText	1 or 0x1
swCommandTabButton_TextBelow	2 or 0x2
swCommandTabButton_TextHorizontal	4 or 0x4

See Also

[SolidWorks.Interop.swconst Namespace](#)

swCompatibilityDialogOptions_e (Type)

SOLIDWORKS API Enumerations

swCompatibilityDialogOptions_e Enumeration

[Send comments on this topic.](#)

[See Also](#)

 

[SolidWorks.Interop.swconst Namespace](#) : swCompatibilityDialogOptions_e Enumeration

Options for displaying the previous file format version compatibility check results dialog.

 Syntax

Visual Basic (Declaration)

Public Enum swCompatibilityDialogOptions_e
Inherits System.Enum

Visual Basic (Usage)

Dim instance As [swCompatibilityDialogOptions_e](#)

 [Copy Code](#)

C#

public enum swCompatibilityDialogOptions_e : System.Enum

C++/CLI

public enum class swCompatibilityDialogOptions_e : public System.Enum

 Members

Member	Description
swCompatibilityDialogOptions_AlwaysShow	0 = Always show the dialog regardless of the outcome of the compatibility check.
swCompatibilityDialogOptions_NeverShow	2 = Never show the dialog regardless of the outcome of the compatibility check.
swCompatibilityDialogOptions_ShowOnIncompatible	1 = Only show the dialog when incompatibilities are found.

 See Also

[SolidWorks.Interop.swconst Namespace](#)

swComponentIdentifier_e (Type)

SOLIDWORKS API Enumerations

swComponentIdentifier_e Enumeration

See Also

 

[SolidWorks.Interop.swconst Namespace](#) : swComponentIdentifier_e Enumeration

Component display options for the FeatureManager design tree. [Bitmask](#).

[Send comments on this topic.](#)

Syntax

Visual Basic (Declaration)

```
Public Enum swComponentIdentifier_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swComponentIdentifier\_e
```

C#

```
public enum swComponentIdentifier_e : System.Enum
```

C++/CLI

```
public enum class swComponentIdentifier_e : public System.Enum
```

Members

Member	Description
swComponentIdentifier_ComponentDescription	4
swComponentIdentifier_ComponentName	2
swComponentIdentifier_ConfigurationDescription	64
swComponentIdentifier_ConfigurationName	32
swComponentIdentifier_DisplayStateName	128
swComponentIdentifier_EnterpriseItemNumber	8 (valid only in SOLIDWORKS Design connected to the 3DEXPERIENCE platform)
swComponentIdentifier_FileTitle	256 (valid only in SOLIDWORKS Design connected to the 3DEXPERIENCE platform)
swComponentIdentifier_None	0
swComponentIdentifier_PhysicalProductDescription	16 (valid only in SOLIDWORKS Design connected to the 3DEXPERIENCE platform)
swComponentIdentifier_PhysicalProductTitle	1 (valid only in SOLIDWORKS Design connected to the 3DEXPERIENCE platform)
swComponentIdentifier_PLMRevision	512 (valid only in SOLIDWORKS Design connected to the 3DEXPERIENCE platform)

See Also

[SolidWorks.Interop.swconst Namespace](#)

swComponentLoadStatus_e (Type)

SOLIDWORKS API Enumerations

swComponentLoadStatus_e Enumeration

[See Also](#)

 

[SolidWorks.Interop.swconst Namespace](#) : swComponentLoadStatus_e Enumeration

Load status of component.

[Send comments on this topic.](#)

Syntax

Visual Basic (Declaration)

```
Public Enum swComponentLoadStatus_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swComponentLoadStatus\_e
```

C#

```
public enum swComponentLoadStatus_e : System.Enum
```

C++/CLI

```
public enum class swComponentLoadStatus_e : public System.Enum
```

Members

Member	Description
swComponentLoadStatus_Hidden	1
swComponentLoadStatus_Suppressed	2
swComponentLoadStatus_Unknown	0

See Also

[SolidWorks.Interop.swconst Namespace](#)

swComponentReloadError_e (Type)

SOLIDWORKS API Enumerations

swComponentReloadError_e Enumeration

See Also

 

[SolidWorks.Interop.swconst Namespace](#) : swComponentReloadError_e Enumeration

Codes returned when reloading components in assemblies.

[Send comments on this topic.](#)

Syntax

Visual Basic (Declaration)

```
Public Enum swComponentReloadError_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swComponentReloadError\_e
```

C#

```
public enum swComponentReloadError_e : System.Enum
```

C++/CLI

```
public enum class swComponentReloadError_e : public System.Enum
```

Members

Member	Description
swComponentLightWeightError	8
swDocumentAlreadyOpenedError	12
swDocumentEventError	13
swDocumentHasNoView	11
swDocumentNotChanged	14
swFileDoesntExistError	9
swFileInvalidOrSameNameError	10
swFileNotSavedError	5
swFutureVersionError	2
swInvalidComponentError	6
swInvalidOption	4
swModifiedNotReloadedError	3
swReadOnlyChanged	16
swReloadCancel	15
swReloadOkay	0
swUnexpectedError	7
swWriteAccessError	1

See Also

[SolidWorks.Interop.swconst Namespace](#)

swComponentReloadOption_e (Type)

SOLIDWORKS API Enumerations

swComponentReloadOption_e Enumeration

[See Also](#)

 

[SolidWorks.Interop.swconst Namespace](#) : swComponentReloadOption_e Enumeration

Options for reloading components in assemblies.

[Send comments on this topic.](#)

Syntax

Visual Basic (Declaration)

```
Public Enum swComponentReloadOption_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swComponentReloadOption\_e
```

C#

```
public enum swComponentReloadOption_e : System.Enum
```

C++/CLI

```
public enum class swComponentReloadOption_e : public System.Enum
```

Members

Member	Description
swAlwaysReload	0
swDontReloadOldComponents	1

See Also

[SolidWorks.Interop.swconst Namespace](#)

swComponentResolveStatus_e (Type)

SOLIDWORKS API Enumerations

swComponentResolveStatus_e Enumeration

See Also

▼

SolidWorks.Interop.swconst Namespace : swComponentResolveStatus_e Enumeration

States for resolving components.

[Send comments on this topic.](#)

Syntax

Visual Basic (Declaration)

```
Public Enum swComponentResolveStatus_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swComponentResolveStatus\_e
```

C#

```
public enum swComponentResolveStatus_e : System.Enum
```

C++/CLI

```
public enum class swComponentResolveStatus_e : public System.Enum
```

Members

Member	Description
swResolveAbortedByUser	1 = User aborted resolving the components
swResolveError	3 = Not used
swResolveNotPerformed	2 = Some of the components did not get resolved despite the user requesting it
swResolveOk	0 = Components resolved okay

See Also

[SolidWorks.Interop.swconst Namespace](#)

swComponentSolvingOption_e (Type)

SOLIDWORKS API Enumerations

swComponentSolvingOption_e Enumeration

See Also

[Send comments on this topic.](#)

 [SolidWorks.Interop.swconst Namespace](#) : swComponentSolvingOption_e Enumeration

Options for resolving components.

 Syntax

Visual Basic (Declaration)

Public Enum swComponentSolvingOption_e
Inherits System.Enum

Visual Basic (Usage)  Copy Code

Dim instance As [swComponentSolvingOption_e](#)

C#

public enum swComponentSolvingOption_e : System.Enum

C++/CLI

public enum class swComponentSolvingOption_e : public System.Enum

 Members

Member	Description
swComponentFlexibleSolving	1
swComponentRigidSolving	0

 See Also

[SolidWorks.Interop.swconst Namespace](#)