

SOLIDWORKS Enumerations (swconst) — Reference (7/17): swFeatureError_e- swHlrQuality_e

SOLIDWORKS API Documentation (converted from CHM)

swFeatureError_e (Type)

SOLIDWORKS API Enumerations

swFeatureError_e Enumeration

See Also

▼

SolidWorks.Interop.swconst Namespace : swFeatureError_e Enumeration

Feature error codes.

[Send comments on this topic.](#)

 Syntax

Visual Basic (Declaration)

```
Public Enum swFeatureError_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swFeatureError\_e
```

C#

```
public enum swFeatureError_e : System.Enum
```

C++/CLI

```
public enum class swFeatureError_e : public System.Enum
```

 Members

Member	Description
swFeatureErrorCutNotIntersectModel	71
swFeatureErrorExtrusionBadGeometricConditions	32 = Unable to create this extruded feature due to geometric conditions
swFeatureErrorExtrusionBossContourInvalid	37 = Bosses require one or more closed contours that do not self-intersect
swFeatureErrorExtrusionBossContourOpenAndClosed	36 = Bosses cannot have both open and closed contours
swFeatureErrorExtrusionCutContourInvalid	34 = Extruded cuts require at least one closed or open contour that does not self-intersect
swFeatureErrorExtrusionCutContourOpenAndClosed	33 = Extruded cuts cannot have both open and closed contours
swFeatureErrorExtrusionDisjoint	30 = Feature would create a disjoint body; direction may be wrong
swFeatureErrorExtrusionNoEndFound	31 = Cannot locate end of feature
swFeatureErrorExtrusionOpenCutContourInvalid	35 = Open extruded cuts require a single open contour that does not self-intersect
swFeatureErrorFeatureDeprecated	49
swFeatureErrorFeatureObsolete	50
swFeatureErrorFilletCannotExtend	16 = Selected elements cannot be extended to intersect
swFeatureErrorFilletInvalidRadius	12 = Invalid fillet radius or a face blend fillet recommended
swFeatureErrorFilletModelGeometry	14 = Failed to create fillet due to model geometry
swFeatureErrorFilletNoEdge	13 = Edge for fillet/chamfer does not exist
swFeatureErrorFilletNoFace	11 = Face for fillet/chamfer does not exist
swFeatureErrorFilletNoLoop	10 = Loop for fillet/chamfer does not exist
swFeatureErrorFilletRadiusEliminateElement	17 = Specified radius would eliminate one of the elements
swFeatureErrorFilletRadiusTooBig	18 = Radius is too big or the elements are tangent or nearly tangent
swFeatureErrorFilletRadiusTooBig2	19 = Not used
swFeatureErrorFilletRadiusTooSmall	15 = Radius too small
swFeatureErrorMateBroken	48 = One or more mate entities were suppressed
swFeatureErrorMateDanglingGeometry	43 = Mate points to dangling geometry
swFeatureErrorMateEntityFailed	45 = Mating is not supported for one of the components or one of the components cannot currently be modified
swFeatureErrorMateEntityNotLinear	44 = Non-linear edges cannot be used for mating
swFeatureErrorMateFailedCreatingSurface	40 = Mating surface type is not supported
swFeatureErrorMateIldefined	47 = This mate cannot be solved. Consider: • Deleting this mate. • Moving the assembly closer to the desired solution with dragging. • Adding more mates to further define the assembly. • Changing the mating scheme
swFeatureErrorMateInvalidEdge	38 = One of the edges of this mate is suppressed, invalid, or no longer present
swFeatureErrorMateInvalidEntity	41 = One of the entities of this mate is suppressed, invalid, or no longer present
swFeatureErrorMateInvalidFace	39 = One of the faces of this mate is suppressed, invalid, or no longer present
swFeatureErrorMateOverdefined	46 = This mate is over-defining the assembly; consider deleting some of the over-defining mates
swFeatureErrorMateUnknownTangent	42 = Tangent not satisfied
swFeatureErrorMissingItemsInFeature	73 = There are missing items in the feature; reselect the correct references
swFeatureErrorNone	0 = No error
swFeatureErrorPartialEdgeFilletCrossOverEndCondition	62 = End points cross over and result in a zero thickness fillet
swFeatureErrorPartialEdgeFilletFailedToRepair	68 = There are no references to repair
swFeatureErrorPartialEdgeFilletInvalidOffsetValue	61 = Total offset from start point and end point must be less than 100%
swFeatureErrorPartialEdgeFilletInvalidReferenceEntity	64 = Reference entity is invalid
swFeatureErrorPartialEdgeFilletMissingReferenceEntity	63 = Reference entity is missing
swFeatureErrorPartialEdgeFilletMultiProjectionPoint	67 = Failed to find a unique point for projection of reference offset
swFeatureErrorPartialEdgeFilletNoEndEdge	56 = Failed to find end edge
swFeatureErrorPartialEdgeFilletNoIntersection	52 = No intersection between reference entity and fillet edge
swFeatureErrorPartialEdgeFilletNoMainEdge	57 = Failed to find the fillet/chamfer edge
swFeatureErrorPartialEdgeFilletNoPropagateEdges	54 = Failed to find propagate edges
swFeatureErrorPartialEdgeFilletNoReferenceEntity	59 = Select a sketch point, reference point, reference plane, or planar face
swFeatureErrorPartialEdgeFilletNoStartEdge	55 = Failed to find a start edge
swFeatureErrorPartialEdgeFilletNotSupported	65 = Partial edge fillet is not supported
swFeatureErrorPartialEdgeFilletNotSupportedForClosedLoop	66 = Some edges form closed loops; partial edge fillet does not support closed loops
swFeatureErrorPartialEdgeFilletOffsetTooBig	58 = The fillet offset is too large
swFeatureErrorPartialEdgeFilletTooManyRefEntities	60 = Too many reference entities selected
swFeatureErrorPartialEdgeFilletUpdateFailed	53 = Failed to update the partial edge data
swFeatureErrorSketchContainsSelfIntersectingContour	72
swFeatureErrorSweptFlangeInvalidProfileOrPath	69
swFeatureErrorSweptFlangeSelfIntersectingGeometry	70
swFeatureErrorUnknown	1 = Unknown error

 See Also

[SolidWorks.Interop.swconst Namespace](#)

swFeatureFilletOptions_e (Type)

SOLIDWORKS API Enumerations

swFeatureFilletOptions_e Enumeration

See Also

▼

SolidWorks.Interop.swconst Namespace : swFeatureFilletOptions_e Enumeration

Fillet/chamfer options. Bitmask.

[Send comments on this topic.](#)

Syntax

Visual Basic (Declaration)

Public Enum swFeatureFilletOptions_e
Inherits System.Enum

Visual Basic (Usage)

Dim instance As [swFeatureFilletOptions_e](#)

C#

public enum swFeatureFilletOptions_e : System.Enum

C++/CLI

public enum class swFeatureFilletOptions_e : public System.Enum



Members

Member	Description
swFeatureFilletAsymmetric	16384 or 0x4000; requires that you specify Direction 1 and Direction 2 radii for the asymmetric sides of the fillet/chamfer
swFeatureFilletAttachEdges	64 or 0x40; set to fillet attached edges between intersecting features; you must pre-select the features
swFeatureFilletConstantWidth	512 or 0x200; set to create a face fillet of constant width
swFeatureFilletCornerType	32 or 0x20
swFeatureFilletCurvatureContinuous	256 or 0x100; set to create a smoother curvature between adjacent surfaces; overrides any other cross-sectional profile setting
swFeatureFilletKeepFeatures	128 or 0x80; set to keep cut or boss features visible if you apply a fillet radius large enough to cover them
swFeatureFilletNoTrimNoAttached	1024 or 0x400; set to trim the filleted faces and knit the surfaces into one surface body
swFeatureFilletPropagate	1 or 0x1; set to extend the fillet to all faces that are tangent to the selected face
swFeatureFilletPropagateFeatToParts	8192 or 0x2000
swFeatureFilletReverseFace1Dir	2048 or 0x800
swFeatureFilletReverseFace2Dir	4096 or 0x1000
swFeatureFilletUniformRadius	2 or 0x2; set for a uniform radius; do not set for multiple radii
swFeatureFilletUseHelpPoint	8 or 0x8; valid only for face fillets/chamfers, set to disambiguate placement of the face fillet/chamfer; requires that you specify a vertex close to where the face blend should occur
swFeatureFilletUseTangentHoldLine	16 or 0x10; set to create a face hold line fillet whose shape is to be determined by a specified part edge or a face projected split line; the radius of the fillet is driven by the distance between the hold line and edge fo fillet
swFeatureFilletVarRadiusType	4 or 0x4; set to create a straight transition fillet that changes from one radius to another linearly while matching edge tangency to an adjacent fillet; do not set to create a smooth transition fillet that changes smoothly from one radius to another when matching edge tangency to an adjacent fillet

See Also

[SolidWorks.Interop.swconst Namespace](#)

swFeatureFilletProfileType_e (Type)

SOLIDWORKS API Enumerations

swFeatureFilletProfileType_e Enumeration

See Also

 

SolidWorks.Interop.swconst Namespace : swFeatureFilletProfileType_e Enumeration

Fillet cross-sectional profile shapes.

[Send comments on this topic.](#)

Syntax

Visual Basic (Declaration)

```
Public Enum swFeatureFilletProfileType_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swFeatureFilletProfileType\_e
```

C#

```
public enum swFeatureFilletProfileType_e : System.Enum
```

C++/CLI

```
public enum class swFeatureFilletProfileType_e : public System.Enum
```

Members

Member	Description
swFeatureFilletCircular	0 = Circular for symmetric fillets; elliptical for asymmetric fillets
swFeatureFilletConicRadius	2 = Requires that you set the radius of curvature at the shoulder point along the fillet's cross section
swFeatureFilletConicRho	1 = Requires that you set a ratio in the range [0.5, 0.95] which indicates the weight of the cross-section
swFeatureFilletConicRhoZeroChamfer	3 = Chamfer cross section

See Also

[SolidWorks.Interop.swconst Namespace](#)

swFeatureFilletType_e (Type)

SOLIDWORKS API Enumerations

swFeatureFilletType_e Enumeration

See Also

[Send comments on this topic.](#)

 

[SolidWorks.Interop.swconst Namespace](#) : swFeatureFilletType_e Enumeration

Feature fillet types.

 Syntax

Visual Basic (Declaration)

```
Public Enum swFeatureFilletType_e
    Inherits System.Enum
```

Visual Basic (Usage)  Copy Code

```
Dim instance As swFeatureFilletType\_e
```

C#

```
public enum swFeatureFilletType_e : System.Enum
```

C++/CLI

```
public enum class swFeatureFilletType_e : public System.Enum
```

 Members

Member	Description
swFeatureFilletType_Face	2
swFeatureFilletType_FullRound	3
swFeatureFilletType_Simple	0
swFeatureFilletType_VariableRadius	1

 See Also

[SolidWorks.Interop.swconst Namespace](#)

swFeatureFillSurfaceOptions_e (Type)

SOLIDWORKS API Enumerations

swFeatureFillSurfaceOptions_e Enumeration

See Also

 [SolidWorks.Interop.swconst Namespace](#) : swFeatureFillSurfaceOptions_e Enumeration

Feature fill surface options. [Bitmask](#).

[Send comments on this topic.](#)

 Syntax

Visual Basic (Declaration)

```
Public Enum swFeatureFillSurfaceOptions_e
    Inherits System.Enum
```

Visual Basic (Usage) 

```
Dim instance As swFeatureFillSurfaceOptions\_e
```

C#

```
public enum swFeatureFillSurfaceOptions_e : System.Enum
```

C++/CLI

```
public enum class swFeatureFillSurfaceOptions_e : public System.Enum
```

 Members

Member	Description
swMergeResult	4 or 0x4; Corresponds to IFillSurfaceFeatureData::Merge
swOptimizeSurface	1 or 0x1; Optimize surface
swReverseDirection	8 or 0x8; Corresponds to IFillSurfaceFeatureData::ReverseDirection
swReverseSurface	16 or 0x10; Corresponds to IFillSurfaceFeatureData::ReverseSurface
swTryToFormSolid	2 or 0x2; Corresponds to IFillSurfaceFeatureData::TryToFormSolid

 Remarks

Some options might not work because the topology of the surface fill to be created might not permit them. In these cases, the options are ignored.

 See Also

[SolidWorks.Interop.swconst Namespace](#)

swFeatureManagerDisplayWarnings_e (Type)

SOLIDWORKS API Enumerations

swFeatureManagerDisplayWarnings_e Enumeration

[Send comments on this topic.](#)

[See Also](#)

 

[SolidWorks.Interop.swconst Namespace](#) : swFeatureManagerDisplayWarnings_e Enumeration

FeatureManager design tree display warnings.

Syntax

Visual Basic (Declaration)

```
Public Enum swFeatureManagerDisplayWarnings_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swFeatureManagerDisplayWarnings\_e
```

C#

```
public enum swFeatureManagerDisplayWarnings_e : System.Enum
```

C++/CLI

```
public enum class swFeatureManagerDisplayWarnings_e : public System.Enum
```

Members

Member	Description
swFeatureManagerDisplayAllWarnings	0
swFeatureManagerDisplayNoWarnings	1
swFeatureManagerDisplayWarningsExceptTopLevel	2

See Also

[SolidWorks.Interop.swconst Namespace](#)

swFeatureManagerTreeViewCADFamily_e (Type)

SOLIDWORKS API Enumerations

swFeatureManagerTreeViewCADFamily_e Enumeration

See Also

[Send comments on this topic.](#)

[SolidWorks.Interop.swconst Namespace](#) : swFeatureManagerTreeViewCADFamily_e Enumeration

SOLIDWORKS Design connected to the 3DEXPERIENCE platform only. **Tools > System Options > FeatureManager > Select a configuration view for the FeatureManager Tree Area.**

Syntax

Visual Basic (Declaration)

Public Enum swFeatureManagerTreeViewCADFamily_e
Inherits System.Enum

Visual Basic (Usage)

Dim instance As [swFeatureManagerTreeViewCADFamily_e](#)

C#

public enum swFeatureManagerTreeViewCADFamily_e : System.Enum

C++/CLI

public enum class swFeatureManagerTreeViewCADFamily_e : public System.Enum

Members

Member	Description
swFeatureManagerTreeViewCADFamily_CADFamilyAndConfiguration	1
swFeatureManagerTreeViewCADFamily_CADFamilyOnly	0

See Also

[SolidWorks.Interop.swconst Namespace](#)

swFeatureModifier_e (Type)

SOLIDWORKS API Enumerations

swFeatureModifier_e Enumeration

[See Also](#)

 

[SolidWorks.Interop.swconst Namespace](#) : swFeatureModifier_e Enumeration

Material conditions for PMI Gtol frames.

[Send comments on this topic.](#)

Syntax

Visual Basic (Declaration)

```
Public Enum swFeatureModifier_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swFeatureModifier\_e
```

C#

```
public enum swFeatureModifier_e : System.Enum
```

C++/CLI

```
public enum class swFeatureModifier_e : public System.Enum
```

Members

Member	Description
swGeometricFeatureModifier_FreeState	5
swGeometricFeatureModifier_LeastMaterialCondition	2
swGeometricFeatureModifier_MaximumMaterialCondition	1
swGeometricFeatureModifier_None	0
swGeometricFeatureModifier_ProjectedTolerance	3
swGeometricFeatureModifier_TangentPlane	4
swGeometricFeatureModifier_ToleranceAsDiameter	6
swGeometricFeatureModifier_Unknown	7

See Also

[SolidWorks.Interop.swconst Namespace](#)

swFeatureNameID_e (Type)

SOLIDWORKS API Enumerations

swFeatureNameID_e Enumeration

See Also

▼

[SolidWorks.Interop.swconst Namespace](#) : swFeatureNameID_e Enumeration

Feature name IDs.

[Send comments on this topic.](#)

Syntax

Visual Basic (Declaration)

Public Enum swFeatureNameID_e
Inherits System.Enum

Visual Basic (Usage)

Dim instance As [swFeatureNameID_e](#)

C#

public enum swFeatureNameID_e : System.Enum

C++/CLI

public enum class swFeatureNameID_e : public System.Enum

Members

Member	Description
swFmAbsoluteView	Absolute view
swFmAEM3DContact	3D contact
swFmAEMGravity	Gravity
swFmAEMLinearDamper	Linear damper
swFmAEMLinearForce	Linear force
swFmAEMLinearMotionSpring	Linear motion spring
swFmAEMLinearMotor	Linear motor
swFmAEMLinearSpring	Linear spring
swFmAEMRotationalMotor	Rotational motor
swFmAEMTorque	Torque
swFmAEMTorsionalDamper	Torsional damper
swFmAEMTorsionalMotionSpring	Torsional motion spring
swFmAEMTorsionalSpring	Torsional spring
swFmAttribute	Attribute
swFmAuxiliaryView	Auxiliary view
swFmBaseBody	Base body
swFmBaseFlange	Base flange
swFmBeltAndChain	Belt
swFmBlend	Blend
swFmBlendCut	Blend cut
swFmBomTableFeature	BOM table feature
swFmBoss	Boss
swFmBoundingBox	BoundingBox
swFmBreakCorner	Break corner
swFmCavity	Cavity
swFmCenterMark	Center mark
swFmChamfer	Chamfer
swFmCirPattern	Circular pattern
swFmCoordinateSystem	Coordinate system
swFmCornerRelief	Sheet metal corner relief
swFmCornerTrim	Corner trim
swFmCosmeticThread	Cosmetic thread
swFmCrossBreak	Cross break
swFmCurvePattern	CurvePattern
swFmCut	Cut
swFmDerivedLPattern	Derived pattern
swFmDetailCircle	Detail circle
swFmDetailView	Detail view
swFmDimPattern	DimPattern
swFmDraft	Draft
swFmDrSectionLine	Section line
swFmDrSheet	Drawing sheet
swFmEdgeFlange	Edge flange
swFmExtrusion	Extrusion
swFmFamilyTableFeature	Family table feature
swFmFeatureFolder	Feature folder
swFmFillet	Fillet
swFmFillPattern	APattern
swFmFlatPattern	Flat pattern
swFmFlattenBends	Flatten bends
swFmFormToolInstance	Form tool instance
swFmGroundPlane	GroundPlane
swFmHoleTableFeature	Hole table feature
swFmHoleWzd	Hole wizard
swFmImported	Imported
swFmLibraryFeature	Library feature
swFmLocalChainPattern	LocalChainPattern

swFmLocalCirPattern	LocalCirPattern
swFmLocalCurvePattern	LocalCurvePattern
swFmLocalLPattern	LocalLPattern
swFmLocalSketchPattern	LocalSketchPattern
swFmLPattern	Linear pattern
swFmMateCamTangent	Tangent mate
swFmMateCoincident	Coincident mate
swFmMateConcentric	Concentric mate
swFmMateController	Mate controller
swFmMateDistanceDim	Distance mate
swFmMateGearDim	Gear mate
swFmMateHinge	Hinge mate
swFmMateLinearCoupler	Linear coupler mate
swFmMateLock	Lock mate
swFmMateParallel	Parallel mate
swFmMatePerpendicular	Perpendicular mate
swFmMatePlanarAngleDim	Angle mate
swFmMateProfileCenter	Profile center mate
swFmMateRackPinionDim	Rack and pinion mate
swFmMateScrew	Screw mate
swFmMateSlot	Slot mate
swFmMateSymmetric	Symmetric mate
swFmMateTangent	Tangent mate
swFmMateUniversalJoint	Universal joint mate
swFmMateWidth	Width mate
swFmMirrorComponent	Mirror component
swFmMirrorPattern	Mirror pattern
swFmMirrorSolid	Mirror solid
swFmNormalCut	Sheet metal normal cut
swFmOneBend	One bend
swFmProcessBends	Process bends
swFmProfileFeature	Profile feature
swFmRefAxis	Reference axis
swFmRefCurve	Reference curve
swFmReference	Reference
swFmReferenceCurve	Reference curve
swFmRefPlane	Reference plane
swFmRefSurface	Reference or sweep surface
swFmRelativeView	Relative view
swFmRevCut	Reference cut
swFmRevisionTableFeature	Revision table feature
swFmRevolution	Revolve
swFmSectionAssemView	Section view of assembly
swFmSectionPartView	Section view of part
swFmSheetMetal	Sheet metal
swFmShell	Shell
swFmSketchBend	Sketch bend
swFmSketchHole	Sketch hole
swFmSketchPattern	SketchPattern
swFmSM3dBend	Sheet metal 3D bend
swFmSMGusset	Sheet metal gusset
swFmSolidBodyFolder	Solid body folder
swFmSolidToSheetMetal	Convert-Solid feature
swFmStock	Stock
swFmStrctSysCnrFeat	Structure system corner feature
swFmStrctSysCnrGrpFeat	Structure system corner group feature
swFmStrctSysCnrMgmtFeat	Structure system corner management feature
swFmStrctSysFeat	Structure system feature
swFmStrctSysGrpFeat	Structure system group feature
swFmStrctSysMbrFeat	Structure system member feature
swFmSurfaceBodyFolder	Surface body folder
swFmSurfCut	Surface cut
swFmSweep	Sweep boss
swFmSweepCut	Sweep cut
swFmSweepThread	Sweep thread
swFmSweptFlange	Swept flange
swFmTabAndSlot	Tab and Slot
swFmTablePattern	TablePattern
swFmThicken	Thicken
swFmThickenCut	Thicken cut
swFmUnfoldedView	Unfolded view
swFmVarFillet	Variable fillet
swFmWeldMemberFeat	Weldment feature

 See Also

[SolidWorks.Interop.swconst Namespace](#)

swFeatureScope_e (Type)

SOLIDWORKS API Enumerations

swFeatureScope_e Enumeration

[See Also](#)

[Send comments on this topic.](#)

 

SolidWorks.Interop.swconst Namespace : swFeatureScope_e Enumeration

Feature scope options.

Syntax

Visual Basic (Declaration)

```
Public Enum swFeatureScope_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swFeatureScope\_e
```

C#

```
public enum swFeatureScope_e : System.Enum
```

C++/CLI

```
public enum class swFeatureScope_e : public System.Enum
```

Members

Member	Description
swFeatureScope_AllBodies	0 = All of the bodies in the multibody part are affected by the Mirror feature.
swFeatureScope_SelectedBodiesWithAutoSelect	1 = Only the specified bodies in the multibody part are affected by the Mirror feature when AutoSelect is true.
swFeatureScope_SelectedBodiesWithOutAutoSelect	2 = Only the specified bodies in the multibody part are affected by the Mirror feature when AutoSelect is false.

See Also

[SolidWorks.Interop.swconst Namespace](#)

swFeaturesToPatternType_e (Type)

SOLIDWORKS API Enumerations

swFeaturesToPatternType_e Enumeration

See Also

 

SolidWorks.Interop.swconst Namespace : swFeaturesToPatternType_e Enumeration

Seed instance types for patterns.

[Send comments on this topic.](#)

Syntax

Visual Basic (Declaration)

```
Public Enum swFeaturesToPatternType_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swFeaturesToPatternType\_e
```

C#

```
public enum swFeaturesToPatternType_e : System.Enum
```

C++/CLI

```
public enum class swFeaturesToPatternType_e : public System.Enum
```

Members

Member	Description
swFeaturesToPatternCreateSeedCut	1 = Pattern using seed cuts defined by swCreateSeedCutType_e
swFeaturesToPatternSelectedFeatures	0 = Pattern using selected features, bodies, and faces

See Also

[SolidWorks.Interop.swconst Namespace](#)

swFeatureSuppressionAction_e (Type)

SOLIDWORKS API Enumerations

swFeatureSuppressionAction_e Enumeration

See Also

 

SolidWorks.Interop.swconst Namespace : swFeatureSuppressionAction_e Enumeration

Feature suppression actions.

[Send comments on this topic.](#)

Syntax

Visual Basic (Declaration)

Public Enum swFeatureSuppressionAction_e
Inherits System.Enum

Visual Basic (Usage)

Dim instance As [swFeatureSuppressionAction_e](#)

C#

public enum swFeatureSuppressionAction_e : System.Enum

C++/CLI

public enum class swFeatureSuppressionAction_e : public System.Enum

Members

Member	Description
swSuppressFeature	0 = Suppress the feature
swUnSuppressDependent	2 = Unsuppress the children of the feature
swUnSuppressFeature	1 = Unsuppress the feature

See Also

[SolidWorks.Interop.swconst Namespace](#)

swFeatureTreeFolderType_e (Type)

SOLIDWORKS API Enumerations

swFeatureTreeFolderType_e Enumeration

See Also

[Send comments on this topic.](#)

 

[SolidWorks.Interop.swconst Namespace](#) : swFeatureTreeFolderType_e Enumeration

Ways to insert feature folders for selected features or components in the FeatureManager design tree.

 Syntax

Visual Basic (Declaration)

```
Public Enum swFeatureTreeFolderType_e
    Inherits System.Enum
```

Visual Basic (Usage)  Copy Code

```
Dim instance As swFeatureTreeFolderType\_e
```

C#

```
public enum swFeatureTreeFolderType_e : System.Enum
```

C++/CLI

```
public enum class swFeatureTreeFolderType_e : public System.Enum
```

 Members

Member	Description
swFeatureTreeFolder_Containing	2 = Create and insert a folder to contain the pre-selected features
swFeatureTreeFolder_EmptyBefore	1 = Create and insert an empty folder before the pre-selected features
swFeatureTreeFolder_Mold	3 = Create and insert a Surface Bodies folder containing three folders: Cavity Surface Bodies, Core Surface Bodies, and Parting Surface Bodies for a pre-selected surface feature

 See Also

[SolidWorks.Interop.swconst Namespace](#)

swFeatureTreeState_e (Type)

SOLIDWORKS API Enumerations

swFeatureTreeState_e Enumeration

See Also

 

SolidWorks.Interop.swconst Namespace : swFeatureTreeState_e Enumeration

Flyout FeatureManager design tree states.

[Send comments on this topic.](#)

Syntax

Visual Basic (Declaration)

```
Public Enum swFeatureTreeState_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swFeatureTreeState\_e
```

C#

```
public enum swFeatureTreeState_e : System.Enum
```

C++/CLI

```
public enum class swFeatureTreeState_e : public System.Enum
```

Members

Member	Description
swFlyoutFeatureTree_Hidden	0
swFlyoutFeatureTree_ShownExpanded	2
swFlyoutFeatureTree_ShownUnExpanded	1

See Also

[SolidWorks.Interop.swconst Namespace](#)

swFileCloseNotifyReason_e (Type)

SOLIDWORKS API Enumerations

swFileCloseNotifyReason_e Enumeration

See Also

Send comments on this topic.

 

SolidWorks.Interop.swconst Namespace : swFileCloseNotifyReason_e Enumeration

Reasons for the [FileCloseNotify](#) event.

 Syntax

Visual Basic (Declaration)

```
Public Enum swFileCloseNotifyReason_e
    Inherits System.Enum
```

Visual Basic (Usage)  Copy Code

```
Dim instance As swFileCloseNotifyReason\_e
```

C#

```
public enum swFileCloseNotifyReason_e : System.Enum
```

C++/CLI

```
public enum class swFileCloseNotifyReason_e : public System.Enum
```

 Members

Member	Description
swFileCloseNotifyReason_CloseForReload	1 = ISldWorks::CloseAndReopen was called
swFileCloseNotifyReason_Unknown	0 = unknown reason

 See Also

[SolidWorks.Interop.swconst Namespace](#)

swFileFormatType_e (Type)

SOLIDWORKS API Enumerations

swFileFormatType_e Enumeration

See Also

[Send comments on this topic.](#)

 

SolidWorks.Interop.swconst Namespace : swFileFormatType_e Enumeration

STEP file formats/editions.

 Syntax

Visual Basic (Declaration)

Public Enum swFileFormatType_e
Inherits System.Enum

Visual Basic (Usage)

Dim instance As [swFileFormatType_e](#)

 [Copy Code](#)

C#

public enum swFileFormatType_e : System.Enum

C++/CLI

public enum class swFileFormatType_e : public System.Enum

 Members

Member	Description
swFileFormatType_STEP	0
swFileFormatType_STEP_ED1	1
swFileFormatType_STEP_ED2	2
swFileFormatType_STEP_ED3	3

 See Also

[SolidWorks.Interop.swconst Namespace](#)

[SolidWorks.Interop.swconst Namespace](#)

swFileLoadError_e (Type)

SOLIDWORKS API Enumerations

swFileLoadError_e Enumeration

See Also

SolidWorks.Interop.swconst Namespace : swFileLoadError_e Enumeration

File load errors. [Bitmask](#).

[Send comments on this topic.](#)

Syntax

Visual Basic (Declaration)

```
Public Enum swFileLoadError_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swFileLoadError\_e
```

C#

```
public enum swFileLoadError_e : System.Enum
```

C++/CLI

```
public enum class swFileLoadError_e : public System.Enum
```

Members

Member	Description
swAddinInterruptError	1048576 or 0x100000: The user attempted to open a file, and then interrupted the open-file routine to open a different file
swApplicationBusy	8388608 or 0x800000: File open is blocked when application is busy
swBasePartNotLoadedWarn	Obsolete; see swFileLoadWarning_e
swConnectedIsOffline	16777216 or 0x1000000
swDrawingANSIUpdateWarn	Obsolete; see swFileLoadWarning_e
swDrawingSFSymbolConvertWarn	Obsolete; see swFileLoadWarning_e
swDrawingsOnlyRapidDraftWarn	Obsolete; see swFileLoadWarning_e
swFileAlreadyOpenWarn	Obsolete; see swFileLoadWarning_e
swFileCriticalDataRepairError	4194304 or 0x400000 = A document has critical data corruption
swFileNotFound	2 or 0x2 = Unable to locate the file; the file is not loaded or the referenced file (that is, component) is suppressed
swFileRequiresRepairError	2097152 or 0x200000 = A document has non-critical custom property data corruption
swFileWithSameTitleAlreadyOpen	65536 or 0x10000 = A document with the same name is already open
swFutureVersion	8192 or 0x2000 = The document was saved in a future version of SOLIDWORKS
swGenericError	1 or 0x1 = Another error was encountered
swIdMatchError	Obsolete; see swFileLoadWarning_e
swInvalidFileTypeError	1024 or 0x400 = File type argument is not valid
swLiquidMachineDoc	131072 or 0x20000 = File encrypted by Liquid Machines
swLowResourcesError	262144 or 0x40000 = File is open and blocked because the system memory is low, or the number of GDI handles has exceeded the allowed maximum
swNeedsRegenWarn	Obsolete; see swFileLoadWarning_e
swNoDisplayData	524288 or 0x80000 = File contains no display data
swReadOnlyWarn	Obsolete; see swFileLoadWarning_e
swSharingViolationWarn	Obsolete; see swFileLoadWarning_e
swSheetScaleUpdateWarn	Obsolete; see swFileLoadWarning_e
swViewMissingReferencedConfig	Obsolete; see swFileLoadWarning_e
swViewOnlyRestrictions	Obsolete; see swFileLoadWarning_e

See Also

[SolidWorks.Interop.swconst Namespace](#)

swFileLoadWarning_e (Type)

SOLIDWORKS API Enumerations

swFileLoadWarning_e Enumeration

See Also

▼

[SolidWorks.Interop.swconst Namespace](#) : swFileLoadWarning_e Enumeration

File load warnings for [ISldWorks::OpenDoc6](#), [Bitmask](#).

[Send comments on this topic.](#)

Syntax

Visual Basic (Declaration)

Public Enum swFileLoadWarning_e
Inherits System.Enum

Visual Basic (Usage)

Dim instance As [swFileLoadWarning_e](#)

C#

public enum swFileLoadWarning_e : System.Enum

C++/CLI

public enum class swFileLoadWarning_e : public System.Enum

Members

Member	Description
swFileLoadWarning_AlreadyOpen	128 or 0x80 = Warning appears because the document is already open.
swFileLoadWarning_AutomaticRepair	262144 or 0x40000 = Warning appears that non-critical data in the document was automatically repaired.
swFileLoadWarning_BasePartNotLoaded	64 or 0x40 = Warning appears because the document was defined in the context of another existing document that is not loaded.
swFileLoadWarning_ComponentMissingReferencedConfig	32768 or 0x8000 = Warning appears if document is opened silently and swOpenDocOptions_AutoMissingConfig is specified.
swFileLoadWarning_CriticalDataRepair	524288 or 0x80000 = Warning appears that critical data in the document was automatically repaired.
swFileLoadWarning_DimensionsReferencedIncorrectlyToModels	16384 or 0x4000 = Warning appears because some dimensions are referenced to the models incorrectly; these dimensions are highlighted in red in the drawing.
swFileLoadWarning_DrawingANSIUpdate	8 or 0x8 = Warning appears because radial dimension arrows now displayed outside when the dimension text is outside of the arc or circle.
swFileLoadWarning_DrawingSFSymbolConvert	2048 or 0x800Warning appears asking the user if he or she wants to convert this drawing's surface finish symbols to the sizes specified in ANSI Y14.36M-1996 and ISO 1302-1978.
swFileLoadWarning_DrawingsOnlyRapidDraft	256 or 0x100 = Warning appears because the only RapidDraft format conversion that can take place is a drawing document that is not Detached.
swFileLoadWarning_IdMismatch	1 or 0x1 = Warning appears if the internal ID of the document does not match the internal ID saved with the referencing document.
swFileLoadWarning_InvisibleDoc_LinkedDesignTableUpdateFail	65536 or 0x10000 = Warning issued because an attempt has been made to open an invisible document with a linked design table that was modified externally, and the design table cannot be updated because the document cannot be displayed; you must make the document visible to open it and update the design table.
swFileLoadWarning_MissingDesignTable	131072 or 0x20000 = Warning appears because the design table is missing.
swFileLoadWarning_MissingExternalReferences	1048576 or 0x100000 = Warning appears if one or more references are missing when loading a file.
swFileLoadWarning_ModelOutOfDate	8192 or 0x2000 = Warning appears because some sheets contain drawing views that are out of date with their external models.
swFileLoadWarning_NeedsRegen	32 or 0x20 = Warning appears because the document needs to be rebuilt.
swFileLoadWarning_ReadOnly	2 or 0x2 = Warning appears because the document is read only.
swFileLoadWarning_RevolveDimTolerance	4096 or 0x1000 = Warning appears because some of the tolerances of the revolved feature dimensions were created in SOLIDWORKS 99 or earlier and are not synchronized with their corresponding dimensions in the sketch.
swFileLoadWarning_SharingViolation	4 or 0x4 = Warning appears if the document is being used by another user.
swFileLoadWarning_SheetScaleUpdate	16 or 0x10 = Warning appears because SOLIDWORKS now applies the scale of the sheet to the sketch entities on the sheet, which means that the sheet looks the same but dimension values are scaled.
swFileLoadWarning_ViewMissingReferencedConfig	1024 or 0x400 = Warning appears because a configuration that a drawing view is referencing no longer exists in the model (part or assembly); the active configuration is used.
swFileLoadWarning_ViewOnlyRestrictions	512 or 0x200 = Warning appears because the document is view only and a configuration other than the default configuration is set.

See Also

[SolidWorks.Interop.swconst Namespace](#)

swFileSaveError_e (Type)

SOLIDWORKS API Enumerations

swFileSaveError_e Enumeration

See Also

 SolidWorks.Interop.swconst Namespace : swFileSaveError_e Enumeration

File save errors. [Bitmask](#).

[Send comments on this topic.](#)

Syntax

Visual Basic (Declaration)

```
Public Enum swFileSaveError_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swFileSaveError\_e
```

C#

```
public enum swFileSaveError_e : System.Enum
```

C++/CLI

```
public enum class swFileSaveError_e : public System.Enum
```

Members

Member	Description
swFileLockError	16 or 0x10
swFileNameContainsAtSign	8 or 0x8 = File name cannot contain the at symbol (@)
swFileNameEmpty	4 or 0x4 = File name cannot be empty
swFileSaveAsBadEDrawingsVersion	1024 or 0x400
swFileSaveAsDetachedDrawingsNotSupported	16384 or 0x4000 = Detached drawing save as options is not supported
swFileSaveAsDoNotOverwrite	128 or 0x80 = Do not overwrite an existing file
swFileSaveAsInvalidFileExtension	256 or 0x100 = File name extension does not match the SOLIDWORKS document type
swFileSaveAsNameExceedsMaxPathLength	2048 or 0x800 = File name cannot exceed 255 characters
swFileSaveAsNoSelection	512 or 0x200 = Save the selected bodies in a part document. Valid option for IPartDoc::SaveToFile2 ; however, not a valid option for IModelDocExtension::SaveAs
swFileSaveAsNotSupported	4096 or 0x1000 = Save As operation: - is not supported - was executed in such a way that the resulting file might not be complete, possibly because SOLIDWORKS is hidden; if the error persists after setting SOLIDWORKS to visible and re-attempting the Save As operation, contact SOLIDWORKS API support.
swFileSaveDoNotUpgradeError	32768 or 0x8000 = Attempt to save a file too many versions behind with "Do Not Upgrade" enabled.
swFileSaveFormatNotAvailable	32 or 0x20 = Save As file type is not valid
swFileSaveIncompatibleItemsError	65536 or 0x10000 = Cannot save to previous version due to incompatible features.
swFileSaveRequiresSavingReferences	8192 or 0x2000 = Saving an assembly with renamed components requires saving the references
swFileSaveWithRebuildError	Obsolete = See swFileSaveWarning_e
swGenericSaveError	1 or 0x1
swReadOnlySaveError	2 or 0x2

Remarks

Not all of these return codes are fatal errors. The return code is a bitmask of different conditions that can occur during the operation, some of which are fatal and some are informational or warnings.

See Also

[SolidWorks.Interop.swconst Namespace](#)

swFileSaveTo3DExperienceError_e (Type)

SOLIDWORKS API Enumerations

swFileSaveTo3DExperienceError_e Enumeration

[See Also](#)

 

[SolidWorks.Interop.swconst Namespace](#) : swFileSaveTo3DExperienceError_e Enumeration

Errors when saving files in SOLIDWORKS Design connected to the 3DEXPERIENCE platform.

[Send comments on this topic.](#)

Syntax

Visual Basic (Declaration)

```
Public Enum swFileSaveTo3DExperienceError_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swFileSaveTo3DExperienceError\_e
```

C#

```
public enum swFileSaveTo3DExperienceError_e : System.Enum
```

C++/CLI

```
public enum class swFileSaveTo3DExperienceError_e : public System.Enum
```

Members

Member	Description
swFileSaveTo3DExperienceError_swConnectedIsOffline	2
swFileSaveTo3DExperienceError_swFileAlreadyExists	3 = File already in cache folder
swFileSaveTo3DExperienceError_swGenericError	1

See Also

[SolidWorks.Interop.swconst Namespace](#)

swFileSaveTypes_e (Type)

SOLIDWORKS API Enumerations

swFileSaveTypes_e Enumeration

See Also

[Send comments on this topic.](#)

 

[SolidWorks.Interop.swconst Namespace](#) : swFileSaveTypes_e Enumeration

File save types.

 Syntax

Visual Basic (Declaration)

Public Enum swFileSaveTypes_e
Inherits System.Enum

Visual Basic (Usage)  Copy Code

Dim instance As [swFileSaveTypes_e](#)

C#

public enum swFileSaveTypes_e : System.Enum

C++/CLI

public enum class swFileSaveTypes_e : public System.Enum

 Members

Member	Description
swFileSave	1
swFileSaveAs	2
swFileSaveAsCopy	3
swFileSaveAsCopyAndOpen	4

 See Also

[SolidWorks.Interop.swconst Namespace](#)

swFileSaveWarning_e (Type)

SOLIDWORKS API Enumerations

swFileSaveWarning_e Enumeration

See Also

Send comments on this topic.

 

SolidWorks.Interop.swconst Namespace : swFileSaveWarning_e Enumeration

Values for **File, Save** warnings that can be returned from the [IModelDoc2](#) Save methods. These warnings do not cause the **File, Save** operation to fail. [Bitmask](#).

 Syntax

Visual Basic (Declaration)

Public Enum swFileSaveWarning_e
Inherits System.Enum

Visual Basic (Usage)  Copy Code

Dim instance As [swFileSaveWarning_e](#)

C#

public enum swFileSaveWarning_e : System.Enum

C++/CLI

public enum class swFileSaveWarning_e : public System.Enum

 Members

Member	Description
swFileSaveWarning_AnimatorCameraViews	128 or 0x80
swFileSaveWarning_AnimatorFeatureEdits	16 or 0x10
swFileSaveWarning_AnimatorLightEdits	64 or 0x40
swFileSaveWarning_AnimatorNeedToSolve	8 or 0x8
swFileSaveWarning_AnimatorSectionViews	256 or 0x100
swFileSaveWarning_EdrrwingsBadSelection	32 or 0x20
swFileSaveWarning_MissingOLEObjects	512 or 0x200
swFileSaveWarning_NeedsRebuild	2 or 0x2
swFileSaveWarning_OpenedViewOnly	1024 or 0x400
swFileSaveWarning_RebuildError	1 or 0x1
swFileSaveWarning_VIEWSNeedUpdate	4 or 0x4
swFileSaveWarning_XmlInvalid	2048 or 0x800

 See Also

[SolidWorks.Interop.swconst Namespace](#)

swFilletOverFlowType_e (Type)

SOLIDWORKS API Enumerations

swFilletOverFlowType_e Enumeration

See Also

[Send comments on this topic.](#)

 

SolidWorks.Interop.swconst Namespace : swFilletOverFlowType_e Enumeration

Fillet overflow types.

 Syntax

Visual Basic (Declaration)

```
Public Enum swFilletOverFlowType_e
    Inherits System.Enum
```

Visual Basic (Usage)  Copy Code

```
Dim instance As swFilletOverFlowType\_e
```

C#

```
public enum swFilletOverFlowType_e : System.Enum
```

C++/CLI

```
public enum class swFilletOverFlowType_e : public System.Enum
```

 Members

Member	Description
swFilletOverFlowType_Default	0 = Default; system picks the appropriate method to create a fillet when the fillet surface overflows to adjacent surfaces; it either smoothly blends with adjacent surfaces or limits the fillet surface with the adjacent edges, thereby not changing the edge, or trims the fillet surface by the adjacent surface onto which the fillet overflows; the method actually used by default depending on the geometric condition; this option always tries to create a fillet if possible
swFilletOverFlowType_KeepEdge	1 = Edges that are overflowed by the fillet are not modified; the fillet surface is trimmed by all the adjacent edges; as a result, an additional transition fillet surface might be needed to complete the fillet
swFilletOverFlowType_KeepSurface	2 = Fillet surface is either merged with the adjacent surfaces smoothly or trimmed by the adjacent surfaces; as a result, it is unlikely that an additional transition fillet surface is created

 See Also

[SolidWorks.Interop.swconst Namespace](#)

swFitTolDisplay_e (Type)

SOLIDWORKS API Enumerations

swFitTolDisplay_e Enumeration

See Also

[Send comments on this topic.](#)

 [SolidWorks.Interop.swconst Namespace](#) : swFitTolDisplay_e Enumeration

Fit tolerance display styles.

Syntax

Visual Basic (Declaration)

```
Public Enum swFitTolDisplay_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swFitTolDisplay\_e
```

C#

```
public enum swFitTolDisplay_e : System.Enum
```

C++/CLI

```
public enum class swFitTolDisplay_e : public System.Enum
```

Members

Member	Description
swFitTolDisplay_Linear	3
swFitTolDisplay_Stacked	2
swFitTolDisplay_StackedWithLine	1

See Also

[SolidWorks.Interop.swconst Namespace](#)

swFitType_e (Type)

SOLIDWORKS API Enumerations

swFitType_e Enumeration

See Also

[Send comments on this topic.](#)

 

[SolidWorks.Interop.swconst Namespace](#) : swFitType_e Enumeration

Fit types.

 Syntax

Visual Basic (Declaration)

```
Public Enum swFitType_e
    Inherits System.Enum
```

Visual Basic (Usage)  Copy Code

```
Dim instance As swFitType\_e
```

C#

```
public enum swFitType_e : System.Enum
```

C++/CLI

```
public enum class swFitType_e : public System.Enum
```

 Members

Member	Description
swFitCLEARANCE	1
swFitPRESS	3
swFitTRANSITIONAL	2
swFitUSER	0

 See Also

[SolidWorks.Interop.swconst Namespace](#)

swFlangeDimTypes_e (Type)

 

SolidWorks.Interop.swconst Namespace : swFlangeDimTypes_e Enumeration

Origins for dimensioning Blind or Up To Edge And Merge flange length end conditions in edge flanges.

 Syntax

Visual Basic (Declaration)

Public Enum swFlangeDimTypes_e
Inherits System.Enum

Visual Basic (Usage)  Copy Code

Dim instance As [swFlangeDimTypes_e](#)

C#

public enum swFlangeDimTypes_e : System.Enum

C++/CLI

public enum class swFlangeDimTypes_e : public System.Enum

 Members

Member	Description
swFlangeDimTypeBendTangentArc	3 = Flange length is measured from the edge flange face to a line that is tangent to the bend; not valid for the Up To Edge And Merge length end condition
swFlangeDimTypeInnerVirtualSharp	2 = Flange length is measured from the edge flange face to an inner virtual sharp (sketch point at the virtual intersection point of two sketch entities)
swFlangeDimTypeOuterVirtualSharp	1 = Flange length is measured from the edge flange face to an outer virtual sharp (sketch point at the virtual intersection point of two sketch entities)

 See Also

[SolidWorks.Interop.swconst Namespace](#)

swFlangeOffsetTypes_e (Type)

SOLIDWORKS API Enumerations

swFlangeOffsetTypes_e Enumeration

See Also

[Send comments on this topic.](#)

[SolidWorks.Interop.swconst Namespace](#) : swFlangeOffsetTypes_e Enumeration

End conditions for both flange length and flange position offset for sheet metal edge and base flanges.

Syntax

Visual Basic (Declaration)

```
Public Enum swFlangeOffsetTypes_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swFlangeOffsetTypes\_e
```

C#

```
public enum swFlangeOffsetTypes_e : System.Enum
```

C++/CLI

```
public enum class swFlangeOffsetTypes_e : public System.Enum
```

Members

Member	Description
swFlangeOffsetBlind	1 = Positions the edge flange based on the length and direction you specify
swFlangeOffsetFromSurface	4
swFlangeOffsetMidPlane	5
swFlangeOffsetUpToEdgeAndMerge	6 = Creates the edge flange in a multibody part by merging a selected edge on one body with an Up To reference edge on the second body
swFlangeOffsetUpToSurface	3
swFlangeOffsetUpToVertex	2 = Positions the edge flange up to a specified vertex; for flange length, the selected vertex may be either on a plane that is normal to the end face of the edge flange or on a plane that is parallel to the face of the base flange

See Also

[SolidWorks.Interop.swconst Namespace](#)

swFlangePositionTypes_e (Type)

SOLIDWORKS API Enumerations

swFlangePositionTypes_e Enumeration

See Also

[SolidWorks.Interop.swconst Namespace](#) : swFlangePositionTypes_e Enumeration

Position types for sheet metal edge flanges.

Syntax

Visual Basic (Declaration)

```
Public Enum swFlangePositionTypes_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swFlangePositionTypes\_e
```

C#

```
public enum swFlangePositionTypes_e : System.Enum
```

C++/CLI

```
public enum class swFlangePositionTypes_e : public System.Enum
```

Members

Member	Description
swFlangePositionTypeBendCenterLine	4
swFlangePositionTypeBendOutside	3
swFlangePositionTypeBendSharp	5 = Bend from virtual sharp
swFlangePositionTypeBendTangent	6 = The flange position will always be tangent to the side face attached to the selected edge, and the flange length will always maintain the exact length; not valid for the Up To Edge And Merge length end condition
swFlangePositionTypeMaterialInside	1
swFlangePositionTypeMaterialOutside	2

See Also

[SolidWorks.Interop.swconst Namespace](#)

swFMViewNotify_e (Type)

SOLIDWORKS API Enumerations

swFMViewNotify_e Enumeration

See Also

▼

SolidWorks.Interop.swconst Namespace : swFMViewNotify_e Enumeration

FeatureManager design tree notifications.

[Send comments on this topic.](#)

 Syntax

Visual Basic (Declaration)

```
Public Enum swFMViewNotify_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swFMViewNotify\_e
```

C#

```
public enum swFMViewNotify_e : System.Enum
```

C++/CLI

```
public enum class swFMViewNotify_e : public System.Enum
```

 Members

Member	Description
swFMViewActivateNotify	1 = ActivateNotify
swFMViewDeactivateNotify	2 = DeactivateNotify
swFMViewDestroyNotify	3 = DestroyNotify

 Remarks

To receive notifications, a DLL application must register for the notifications by object type. This registration must be done for each instance of a particular object.

For example, in the file in the Visual C++ 6.0 wizard-generated add-in that supports FeatureManager design tree events (e.g., FeatMgrView.h), include:

```
DECLARE_REGISTRY_RESOURCEID(IDR_FeatMgrView)

BEGIN_SINK_MAP(CFeatMgrView)

    SINK_ENTRY_EX(ID_FEATMGRVIEW_EVENTS, DIID_DFeatMgrViewEvents,
        swFMViewDestroyNotify , DestroyNotify)

    SINK_ENTRY_EX(ID_FEATMGRVIEW_EVENTS, DIID_DFeatMgrViewEvents,
        swFMViewActivateNotify, ActivateNotify)

    SINK_ENTRY_EX(ID_FEATMGRVIEW_EVENTS, DIID_DFeatMgrViewEvents,
        swFMViewDeactivateNotify , DeActivateNotify)

END_SINK_MAP()
```

If developing a C++ application, use these enumerators to [register for notifications](#) for [IFeatMgrView](#) events.

 See Also

[SolidWorks.Interop.swconst Namespace](#)

swFractionDisplay_e (Type)

SOLIDWORKS API Enumerations

swFractionDisplay_e Enumeration

See Also

[Send comments on this topic.](#)

 

[SolidWorks.Interop.swconst Namespace](#) : swFractionDisplay_e Enumeration

Fraction display types.

 Syntax

Visual Basic (Declaration)

```
Public Enum swFractionDisplay_e
    Inherits System.Enum
```

Visual Basic (Usage)  Copy Code

```
Dim instance As swFractionDisplay\_e
```

C#

```
public enum swFractionDisplay_e : System.Enum
```

C++/CLI

```
public enum class swFractionDisplay_e : public System.Enum
```

 Members

Member	Description
swDECIMAL	1
swFRACTION	2
swNONE	0

 See Also

[SolidWorks.Interop.swconst Namespace](#)

swGeneralImportFreePointCurveEntityOptions_e (Type)

SOLIDWORKS API Enumerations

swGeneralImportFreePointCurveEntityOptions_e Enumeration

[Send comments on this topic.](#)

[See Also](#)

 

[SolidWorks.Interop.swconst Namespace](#) : swGeneralImportFreePointCurveEntityOptions_e Enumeration

Import free curve entity options.

Syntax

Visual Basic (Declaration)

```
Public Enum swGeneralImportFreePointCurveEntityOptions_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swGeneralImportFreePointCurveEntityOptions\_e
```

C#

```
public enum swGeneralImportFreePointCurveEntityOptions_e : System.Enum
```

C++/CLI

```
public enum class swGeneralImportFreePointCurveEntityOptions_e : public System.Enum
```

Members

Member	Description
swGeneralImportAs3dCurves	1
swGeneralImportAsSketches	0

See Also

[SolidWorks.Interop.swconst Namespace](#)

swGeneralImportSurfaceSolidEntityOptions_e (Type)

SOLIDWORKS API Enumerations

swGeneralImportSurfaceSolidEntityOptions_e Enumeration

[Send comments on this topic.](#)

[See Also](#)

 

[SolidWorks.Interop.swconst Namespace](#) : swGeneralImportSurfaceSolidEntityOptions_e Enumeration

Import surface solid entity options.

Syntax

Visual Basic (Declaration)

```
Public Enum swGeneralImportSurfaceSolidEntityOptions_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swGeneralImportSurfaceSolidEntityOptions\_e
```

C#

```
public enum swGeneralImportSurfaceSolidEntityOptions_e : System.Enum
```

C++/CLI

```
public enum class swGeneralImportSurfaceSolidEntityOptions_e : public System.Enum
```

Members

Member	Description
swGeneralImportByBrep	3
swGeneralImportDoNotKnit	2
swGeneralImportKnitSurfaces	1
swGeneralImportTryFormingSolids	0

See Also

[SolidWorks.Interop.swconst Namespace](#)

swGeneralImportUnitsOptions_e (Type)

SOLIDWORKS API Enumerations

swGeneralImportUnitsOptions_e Enumeration

See Also

 

[SolidWorks.Interop.swconst Namespace](#) : swGeneralImportUnitsOptions_e Enumeration

Import unit options.

[Send comments on this topic.](#)

Syntax

Visual Basic (Declaration)

```
Public Enum swGeneralImportUnitsOptions_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swGeneralImportUnitsOptions\_e
```

C#

```
public enum swGeneralImportUnitsOptions_e : System.Enum
```

C++/CLI

```
public enum class swGeneralImportUnitsOptions_e : public System.Enum
```

Members

Member	Description
swGeneralImportDocumentTemplateSpeciedUnit	1
swGeneralImportFileSpecifiedUnit	0

See Also

[SolidWorks.Interop.swconst Namespace](#)

swGeometricCharacteristic_e (Type)

SOLIDWORKS API Enumerations

swGeometricCharacteristic_e Enumeration

See Also

 SolidWorks.Interop.swconst Namespace : swGeometricCharacteristic_e Enumeration

Geometric characteristics for Gtol frames.

[Send comments on this topic.](#)

Syntax

Visual Basic (Declaration)

```
Public Enum swGeometricCharacteristic_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swGeometricCharacteristic\_e
```

C#

```
public enum swGeometricCharacteristic_e : System.Enum
```

C++/CLI

```
public enum class swGeometricCharacteristic_e : public System.Enum
```

Members

Member	Description
swGeometricCharacteristic_Angularity	7
swGeometricCharacteristic_Circularity	3
swGeometricCharacteristic_CircularRunout	13
swGeometricCharacteristic_Concentricity	11
swGeometricCharacteristic_Cylindricity	4
swGeometricCharacteristic_Flatness	2
swGeometricCharacteristic_LineProfile	5
swGeometricCharacteristic_None	0
swGeometricCharacteristic_Parallelism	8
swGeometricCharacteristic_Perpendicularity	9
swGeometricCharacteristic_Position	10
swGeometricCharacteristic_Straightness	1
swGeometricCharacteristic_SurfaceProfile	6
swGeometricCharacteristic_Symmetry	12
swGeometricCharacteristic_TotalRunout	14
swGeometricCharacteristic_Unknown	15

See Also

[SolidWorks.Interop.swconst Namespace](#)

swGeometryToSave_e (Type)

SOLIDWORKS API Enumerations

swGeometryToSave_e Enumeration

[See Also](#)

[Send comments on this topic.](#)

 

[SolidWorks.Interop.swconst Namespace](#) : swGeometryToSave_e Enumeration

Geometry to save options for [AdvancedSaveAsOptions::GeometryToSave](#).

 Syntax

Visual Basic (Declaration)

Public Enum swGeometryToSave_e
Inherits System.Enum

Visual Basic (Usage)

Dim instance As [swGeometryToSave_e](#)

 [Copy Code](#)

C#

public enum swGeometryToSave_e : System.Enum

C++/CLI

public enum class swGeometryToSave_e : public System.Enum

 Members

Member	Description
swGeometryToSave_AllComponents	0
swGeometryToSave_ExteriorFaces	1
swGeometryToSave_IncludeSpecificComponents	2

 See Also

[SolidWorks.Interop.swconst Namespace](#)

swGeomType_e (Type)

SOLIDWORKS API Enumerations

swGeomType_e Enumeration

See Also

 

[SolidWorks.Interop.swconst Namespace](#) : swGeomType_e Enumeration

Geometry types.

[Send comments on this topic.](#)

 Syntax

Visual Basic (Declaration)

```
Public Enum swGeomType_e
    Inherits System.Enum
```

Visual Basic (Usage)

  Copy Code

```
Dim instance As swGeomType\_e
```

C#

```
public enum swGeomType_e : System.Enum
```

C++/CLI

```
public enum class swGeomType_e : public System.Enum
```

 Members

Member	Description
sw3DCYLINDER	9
sw3DPARAMETRICSURFACE	11
sw3DPLANE	8
sw3DSPHERE	10
swARC	2
swDIM	12
swELLIPSE	4
swHATCH	6
swINVALIDGTYPE	99
swLINE	1
swPARABOLA	7
swPOINT	0
swSPLINECURVE	3
swSUBSKETCH	13
swTEXT	5

 See Also

[SolidWorks.Interop.swconst Namespace](#)

swGetOpenFileNameOptions_e (Type)

SOLIDWORKS API Enumerations

swGetOpenFileNameOptions_e Enumeration

See Also

 

SolidWorks.Interop.swconst Namespace : swGetOpenFileNameOptions_e Enumeration

Options for opening a file returned by [ISldWorks::GetOpenFileName2](#), [Bitmask](#).

[Send comments on this topic.](#)

Syntax

Visual Basic (Declaration)

```
Public Enum swGetOpenFileNameOptions_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swGetOpenFileNameOptions\_e
```

C#

```
public enum swGetOpenFileNameOptions_e : System.Enum
```

C++/CLI

```
public enum class swGetOpenFileNameOptions_e : public System.Enum
```

Members

Member	Description
swGetOpenFileNameOptions_AdvancedConfig	0x2000; "<Advanced>" selected in configuration dropdown
swGetOpenFileNameOptions_AutoMissingConfig	0x20; Reserved for internal use
swGetOpenFileNameOptions_DontLoadHiddenComponents	0x100; Does not load hidden components (assemblies only)
swGetOpenFileNameOptions_LDR_EditAssembly	0x800; Reserved for internal use
swGetOpenFileNameOptions_LoadExternalReferencesInMemory	0x200; Reserved for internal use
swGetOpenFileNameOptions_LoadLightweight	0x80; Opens the document in lightweight mode
swGetOpenFileNameOptions_LoadModel	0x10; Reserved for internal use
swGetOpenFileNameOptions_OpenDetailingMode	0x400; Opens the document in detailing mode without part and assembly data (drawings only)
swGetOpenFileNameOptions_OverrideDefaultLoadLightweight	0x40; Reserved for internal use
swGetOpenFileNameOptions_RapidDraft	0x8; Reserved for internal use
swGetOpenFileNameOptions_ReadOnly	0x2; Opens the document read only
swGetOpenFileNameOptions_SelectedSheets	0x8000; "Selected" is checked in Select Sheet to load dialog
swGetOpenFileNameOptions_Silent	0x1; Reserved for internal use
swGetOpenFileNameOptions_SpeedPak	0x1000; Uses Speedpak (assemblies only)
swGetOpenFileNameOptions_UseLargeAssemblySettings	0x4000; Uses large assembly settings (assemblies only)
swGetOpenFileNameOptions_ViewOnly	0x4; Opens the document view only; returned if "None" is selected in Select Sheet to load dialog

See Also

[SolidWorks.Interop.swconst Namespace](#)

swGlobalBBoxLWTADirectionType_e (Type)

SOLIDWORKS API Enumerations

[Send comments on this topic.](#)

swGlobalBBoxLWTADirectionType_e Enumeration

[See Also](#)



[SolidWorks.Interop.swconst Namespace](#) : swGlobalBBoxLWTADirectionType_e Enumeration

Length, width, and thickness directions for a rectangular bounding box and axis directions for a cylindrical bounding box.

Syntax

Visual Basic (Declaration)

```
Public Enum swGlobalBBoxLWTADirectionType_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swGlobalBBoxLWTADirectionType\_e
```

C#

```
public enum swGlobalBBoxLWTADirectionType_e : System.Enum
```

C++/CLI

```
public enum class swGlobalBBoxLWTADirectionType_e : public System.Enum
```

Members

Member	Description
swBBox_AxisDir_X	7 = Axis direction is the X direction of the coordinate system
swBBox_AxisDir_Y	8 = Axis direction is the Y direction of the coordinate system
swBBox_AxisDir_Z	9 = Axis direction is the Z direction of the coordinate system
swBBox_LWTADir_Unspecified	0 = Length, width, thickness, and axis directions are not fixed. Length is the longest and thickness is the shortest direction
swBBox_LWTDir_XYZ	1 = LWT directions map to XYZ coordinates
swBBox_LWTDir_XZY	6 = LWT directions map to XZY coordinates
swBBox_LWTDir_YXZ	2 = LWT directions map to YXZ coordinates
swBBox_LWTDir_YZX	3 = LWT directions map to YZX coordinates
swBBox_LWTDir_ZXY	5 = LWT directions map to ZXY coordinates
swBBox_LWTDir_ZYX	4 = LWT directions map to ZYX coordinates

See Also

[SolidWorks.Interop.swconst Namespace](#)

swGlobalBoundingBoxFitOptions_e (Type)

SOLIDWORKS API Enumerations

swGlobalBoundingBoxFitOptions_e Enumeration

See Also

 

[SolidWorks.Interop.swconst Namespace](#) : swGlobalBoundingBoxFitOptions_e Enumeration

Global bounding box fit types.

[Send comments on this topic.](#)

 Syntax

Visual Basic (Declaration)

Public Enum swGlobalBoundingBoxFitOptions_e
Inherits System.Enum

Visual Basic (Usage)

Dim instance As [swGlobalBoundingBoxFitOptions_e](#)



C#

public enum swGlobalBoundingBoxFitOptions_e : System.Enum

C++/CLI

public enum class swGlobalBoundingBoxFitOptions_e : public System.Enum

 Members

Member	Description
swBoundingBoxType_BestFit	1 = Orientation of the bounding box is based on the X-Y plane
swBoundingBoxType_CustomCoordSys	3 = Use coordinate system to define bounding box
swBoundingBoxType_CustomPlane	2 = Specify the orientation plane or planar face on which to base the bounding box

 See Also

[SolidWorks.Interop.swconst Namespace](#)

swGlobalBoundingBoxResult_e (Type)

SOLIDWORKS API Enumerations

swGlobalBoundingBoxResult_e Enumeration

See Also

[SolidWorks.Interop.swconst Namespace](#) : swGlobalBoundingBoxResult_e Enumeration

Global bounding box insertion results.

Syntax

Visual Basic (Declaration)

```
Public Enum swGlobalBoundingBoxResult_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swGlobalBoundingBoxResult\_e
```

C#

```
public enum swGlobalBoundingBoxResult_e : System.Enum
```

C++/CLI

```
public enum class swGlobalBoundingBoxResult_e : public System.Enum
```

Members

Member	Description
swGlobalBoundingBoxResult_NonPlanarFaceSelected	2
swGlobalBoundingBoxResult_NoValidBodiesFound	1
swGlobalBoundingBoxResult_Success	0

See Also

[SolidWorks.Interop.swconst Namespace](#)

swGtolDecimalSeparatorType_e (Type)

SOLIDWORKS API Enumerations

swGtolDecimalSeparatorType_e Enumeration

See Also

[SolidWorks.Interop.swconst Namespace](#) : swGtolDecimalSeparatorType_e Enumeration

Gtol decimal separator types.

[Send comments on this topic.](#)

Syntax

Visual Basic (Declaration)

```
Public Enum swGtolDecimalSeparatorType_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swGtolDecimalSeparatorType\_e
```

C#

```
public enum swGtolDecimalSeparatorType_e : System.Enum
```

C++/CLI

```
public enum class swGtolDecimalSeparatorType_e : public System.Enum
```

Members

Member	Description
swGeometricTolerance_Decimal_Separator_Comma	1
swGeometricTolerance_Decimal_Separator_Period	0

See Also

[SolidWorks.Interop.swconst Namespace](#)

swGtolFormatConversionError_e (Type)

SOLIDWORKS API Enumerations

swGtolFormatConversionError_e Enumeration

See Also

 [SolidWorks.Interop.swconst Namespace](#) : swGtolFormatConversionError_e Enumeration

Gtol format conversion errors.

[Send comments on this topic.](#)

 Syntax

Visual Basic (Declaration)

Public Enum swGtolFormatConversionError_e
Inherits System.Enum

Visual Basic (Usage)

Dim instance As [swGtolFormatConversionError_e](#)

C#

public enum swGtolFormatConversionError_e : System.Enum

C++/CLI

public enum class swGtolFormatConversionError_e : public System.Enum

 Members

Member	Description
swGtolFormatConversionFail	1

 See Also

[SolidWorks.Interop.swconst Namespace](#)

swGtolFormatSchemaVersion_e (Type)

SOLIDWORKS API Enumerations

swGtolFormatSchemaVersion_e Enumeration

See Also

 

[SolidWorks.Interop.swconst Namespace](#) : swGtolFormatSchemaVersion_e Enumeration

Gtol format schema versions.

[Send comments on this topic.](#)

 Syntax

Visual Basic (Declaration)

```
Public Enum swGtolFormatSchemaVersion_e
    Inherits System.Enum
```

Visual Basic (Usage)  Copy Code

```
Dim instance As swGtolFormatSchemaVersion\_e
```

C#

```
public enum swGtolFormatSchemaVersion_e : System.Enum
```

C++/CLI

```
public enum class swGtolFormatSchemaVersion_e : public System.Enum
```

 Members

Member	Description
swGtolFormatSchemaVersion_SW2023	1

 See Also

[SolidWorks.Interop.swconst Namespace](#)

swGtolFormatType_e (Type)

SOLIDWORKS API Enumerations

swGtolFormatType_e Enumeration

See Also

[Send comments on this topic.](#)

 

[SolidWorks.Interop.swconst Namespace](#) : swGtolFormatType_e Enumeration

Gtol format types.

 Syntax

Visual Basic (Declaration)

Public Enum swGtolFormatType_e
Inherits System.Enum

Visual Basic (Usage)  [Copy Code](#)

Dim instance As [swGtolFormatType_e](#)

C#

public enum swGtolFormatType_e : System.Enum

C++/CLI

public enum class swGtolFormatType_e : public System.Enum

 Members

Member	Description
GTOL_SW2021	1
GTOL_SW2022	2

 See Also

[SolidWorks.Interop.swconst Namespace](#)

swGtolGeomCharSymbol_e (Type)

SOLIDWORKS API Enumerations

swGtolGeomCharSymbol_e Enumeration

See Also

 

SolidWorks.Interop.swconst Namespace : swGtolGeomCharSymbol_e Enumeration

Gtol geometric character symbols.

[Send comments on this topic.](#)

Syntax

Visual Basic (Declaration)

```
Public Enum swGtolGeomCharSymbol_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swGtolGeomCharSymbol\_e
```

C#

```
public enum swGtolGeomCharSymbol_e : System.Enum
```

C++/CLI

```
public enum class swGtolGeomCharSymbol_e : public System.Enum
```

Members

Member	Description
swGcsANG	20
swGcsCIRCOPENRUNOUT	27
swGcsCIRC RUNOUT	25
swGcsCONC	24
swGcsCYL	17
swGcsFLAT	15
swGcsLINEPROF	18
swGcsNONE	12
swGcsPARALLEL	22
swGcsPERP	21
swGcsPOSITION	23
swGcsROUND	16
swGcsSQUARE	30
swGcsSTRAIGHT	14
swGcsSURFPROF	19
swGcsSYMMETRY	13
swGcsTOTALOPENRUNOUT	28
swGcsTOTAL RUNOUT	26
swGcsUBUTTON	29

See Also

[SolidWorks.Interop.swconst Namespace](#)

swGtolIndicatorBorderType_e (Type)

SOLIDWORKS API Enumerations

swGtolIndicatorBorderType_e Enumeration

See Also

 

[SolidWorks.Interop.swconst Namespace](#) : swGtolIndicatorBorderType_e Enumeration

Gtol indicator border types.

[Send comments on this topic.](#)

Syntax

Visual Basic (Declaration)

```
Public Enum swGtolIndicatorBorderType_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swGtolIndicatorBorderType\_e
```

C#

```
public enum swGtolIndicatorBorderType_e : System.Enum
```

C++/CLI

```
public enum class swGtolIndicatorBorderType_e : public System.Enum
```

Members

Member	Description
swGtolIndicatorBorderType_CollectionPlane	2
swGtolIndicatorBorderType_DirectionFeature	3
swGtolIndicatorBorderType_IntersectionPlane	1
swGtolIndicatorBorderType_OrientationPlane	0

See Also

[SolidWorks.Interop.swconst Namespace](#)

swGtolMatCondition_e (Type)

SOLIDWORKS API Enumerations

swGtolMatCondition_e Enumeration

See Also

[SolidWorks.Interop.swconst Namespace](#) : swGtolMatCondition_e Enumeration

Gtol material condition types.

Syntax

Visual Basic (Declaration)

Public Enum swGtolMatCondition_e
Inherits System.Enum

Visual Basic (Usage)

Dim instance As [swGtolMatCondition_e](#)

C#

public enum swGtolMatCondition_e : System.Enum

C++/CLI

public enum class swGtolMatCondition_e : public System.Enum

Members

Member	Description
swMcLMC	3
swMcMMC	1
swMcNONE	0
swMcRFS	2
swMsARCLEN	11
swMsDIA	6
swMsNONE	4
swMsPROJTOLZONE	5
swMsRAD	8
swMsREF	10
swMsSPHDIA	7
swMsSPHRAD	9

See Also

[SolidWorks.Interop.swconst Namespace](#)

swGTolTextParts_e (Type)

SOLIDWORKS API Enumerations

swGTolTextParts_e Enumeration

See Also

[Send comments on this topic.](#)

 

[SolidWorks.Interop.swconst Namespace](#) : swGTolTextParts_e Enumeration

Text parts of GTols.

 Syntax

Visual Basic (Declaration)

```
Public Enum swGTolTextParts_e
    Inherits System.Enum
```

Visual Basic (Usage)  Copy Code

```
Dim instance As swGTolTextParts\_e
```

C#

```
public enum swGTolTextParts_e : System.Enum
```

C++/CLI

```
public enum class swGTolTextParts_e : public System.Enum
```

 Members

Member	Description
swGTolTextCalloutAbove	3
swGTolTextCalloutBelow	4
swGTolTextPrefix	1
swGTolTextSuffix	2

 See Also

[SolidWorks.Interop.swconst Namespace](#)

swGtolTolType_e (Type)

SOLIDWORKS API Enumerations

swGtolTolType_e Enumeration

See Also

Send comments on this topic.

 

SolidWorks.Interop.swconst Namespace : swGtolTolType_e Enumeration

Tolerance zone types in Gtol frame boxes.

 Syntax

Visual Basic (Declaration)

Public Enum swGtolTolType_e
Inherits System.Enum

Visual Basic (Usage)  Copy Code

Dim instance As [swGtolTolType_e](#)

C#

public enum swGtolTolType_e : System.Enum

C++/CLI

public enum class swGtolTolType_e : public System.Enum

 Members

Member	Description
swGtolTolType_MAX	5 = Specifies a maximum value for a material condition that has already been specified as a modifier of the tolerance in the Gtol; this maximum upper tolerance is typically specified in the Tolerance 2 box with "MAX"
swGtolTolType_None	0
swGtolTolType_ProjectedTolerance	2 = Applies to holes in which a pin, stud, or screw is to be inserted; controls the perpendicularity of the hole to the extent of the projection from the hole; specified with a circle-P symbol; typically a height is also specified in a separate field
swGtolTolType_Square	3
swGtolTolType_UnequallyDisposedProfile	4 = Indicates that the profile of a surface tolerance is not symmetrical about the true profile; the value following the circle-U symbol is the amount of the tolerance that is in a direction that would allow additional material to be added to the true profile
swGtolTolType_Unknown	1

 See Also

[SolidWorks.Interop.swconst Namespace](#)

swGuideCurveInfluence_e (Type)

SOLIDWORKS API Enumerations

swGuideCurveInfluence_e Enumeration

[See Also](#)

 

[SolidWorks.Interop.swconst Namespace](#) : swGuideCurveInfluence_e Enumeration

Guide curve influence types.

[Send comments on this topic.](#)

Syntax

Visual Basic (Declaration)

```
Public Enum swGuideCurveInfluence_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swGuideCurveInfluence\_e
```

C#

```
public enum swGuideCurveInfluence_e : System.Enum
```

C++/CLI

```
public enum class swGuideCurveInfluence_e : public System.Enum
```

Members

Member	Description
swGuideCurveInfluenceNextEdge	2
swGuideCurveInfluenceNextGlobal	3
swGuideCurveInfluenceNextGuide	0
swGuideCurveInfluenceNextSharp	1

See Also

[SolidWorks.Interop.swconst Namespace](#)

swGussetProfileLocationType_e (Type)

SOLIDWORKS API Enumerations

swGussetProfileLocationType_e Enumeration

See Also

[SolidWorks.Interop.swconst Namespace](#) : swGussetProfileLocationType_e Enumeration

Gussett profile location types.

Syntax

Visual Basic (Declaration)

```
Public Enum swGussetProfileLocationType_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swGussetProfileLocationType\_e
```

C#

```
public enum swGussetProfileLocationType_e : System.Enum
```

C++/CLI

```
public enum class swGussetProfileLocationType_e : public System.Enum
```

Members

Member	Description
swGussetProfileLocationCenter	1
swGussetProfileLocationEnd	2
swGussetProfileLocationStart	0

See Also

[SolidWorks.Interop.swconst Namespace](#)

swGussetProfileType_e (Type)

SOLIDWORKS API Enumerations

swGussetProfileType_e Enumeration

See Also

 

[SolidWorks.Interop.swconst Namespace](#) : swGussetProfileType_e Enumeration

Gusset profile types.

[Send comments on this topic.](#)

 Syntax

Visual Basic (Declaration)

```
Public Enum swGussetProfileType_e
    Inherits System.Enum
```

Visual Basic (Usage)

 Copy Code

```
Dim instance As swGussetProfileType\_e
```

C#

```
public enum swGussetProfileType_e : System.Enum
```

C++/CLI

```
public enum class swGussetProfileType_e : public System.Enum
```

 Members

Member	Description
swGussetProfilePolygon	0
swGussetProfileTriangle	1

 See Also

[SolidWorks.Interop.swconst Namespace](#)

swGussetThicknessType_e (Type)

SOLIDWORKS API Enumerations

swGussetThicknessType_e Enumeration

See Also

[Send comments on this topic.](#)

 

[SolidWorks.Interop.swconst Namespace](#) : swGussetThicknessType_e Enumeration

Gusset thickness types.

 Syntax

Visual Basic (Declaration)

Public Enum swGussetThicknessType_e
Inherits System.Enum

Visual Basic (Usage)  Copy Code

Dim instance As [swGussetThicknessType_e](#)

C#

public enum swGussetThicknessType_e : System.Enum

C++/CLI

public enum class swGussetThicknessType_e : public System.Enum

 Members

Member	Description
swGussetThicknessBothSides	1
swGussetThicknessInner	0
swGussetThicknessOuter	2

 See Also

[SolidWorks.Interop.swconst Namespace](#)

swHandleActiveXCreationFailure_e (Type)

SOLIDWORKS API Enumerations

swHandleActiveXCreationFailure_e Enumeration

See Also

[Send comments on this topic.](#)

                                                                      

[SolidWorks.Interop.swconst Namespace](#) : swHandleActiveXCreationFailure_e Enumeration

Actions on failure to create an ActiveX control on a PropertyManager page.

Syntax

Visual Basic (Declaration)

```
Public Enum swHandleActiveXCreationFailure_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swHandleActiveXCreationFailure\_e
```

C#

```
public enum swHandleActiveXCreationFailure_e : System.Enum
```

C++/CLI

```
public enum class swHandleActiveXCreationFailure_e : public System.Enum
```

Members

Member	Description
swHandleActiveXCreationFailure_Cancel	1
swHandleActiveXCreationFailure_Continue	3
swHandleActiveXCreationFailure_Retry	2

See Also

[SolidWorks.Interop.swconst Namespace](#)

swHandleWindowFromHandleCreationFailure_e (Type)

SOLIDWORKS API Enumerations

swHandleWindowFromHandleCreationFailure_e Enumeration

See Also

 

[SolidWorks.Interop.swconst Namespace](#) : swHandleWindowFromHandleCreationFailure_e Enumeration

Actions on failure to create a .NET control on a PropertyManager page.

[Send comments on this topic.](#)

 Syntax

Visual Basic (Declaration)

Public Enum swHandleWindowFromHandleCreationFailure_e
Inherits System.Enum

Visual Basic (Usage)

Dim instance As [swHandleWindowFromHandleCreationFailure_e](#)



C#

public enum swHandleWindowFromHandleCreationFailure_e : System.Enum

C++/CLI

public enum class swHandleWindowFromHandleCreationFailure_e : public System.Enum

 Members

Member	Description
swHandleWindowFromHandleCreationFailure_Cancel	1 = Create the PropertyManager page without the .NET control. (default)
swHandleWindowFromHandleCreationFailure_Continue	3 = Cancel the creation of the PropertyManager page.
swHandleWindowFromHandleCreationFailure_Retry	2 = Try to create the .NET control again.

 See Also

[SolidWorks.Interop.swconst Namespace](#)

swHealActionType_e (Type)

SOLIDWORKS API Enumerations

swHealActionType_e Enumeration

[See Also](#)

 

[SolidWorks.Interop.swconst Namespace](#) : swHealActionType_e Enumeration

Healing actions.

[Send comments on this topic.](#)

 Syntax

Visual Basic (Declaration)

Public Enum swHealActionType_e
Inherits System.Enum

Visual Basic (Usage)

Dim instance As [swHealActionType_e](#)

 [Copy Code](#)

C#

public enum swHealActionType_e : System.Enum

C++/CLI

public enum class swHealActionType_e : public System.Enum

 Members

Member	Description
swHealAction_Cap	2 = Finds a surface where all edges of the wound lie and attaches this to a face and covers the wound; SOLIDWORKS creates a new face to cover the wound
swHealAction_GrowParent	1 = Extends the parent faces around the wound to cover it
swHealAction_Shrink	0 = If extending faces does not yield a solution, then SOLIDWORKS tries to shrink the faces

 See Also

[SolidWorks.Interop.swconst Namespace](#)

swHelixDefinedBy_e (Type)

SOLIDWORKS API Enumerations

swHelixDefinedBy_e Enumeration

See Also

[Send comments on this topic.](#)

 

[SolidWorks.Interop.swconst Namespace](#) : swHelixDefinedBy_e Enumeration

Helix definitions.

 Syntax

Visual Basic (Declaration)

Public Enum swHelixDefinedBy_e
Inherits System.Enum

Visual Basic (Usage)  Copy Code

Dim instance As [swHelixDefinedBy_e](#)

C#

public enum swHelixDefinedBy_e : System.Enum

C++/CLI

public enum class swHelixDefinedBy_e : public System.Enum

 Members

Member	Description
swHelixDefinedByHeightAndPitch	2
swHelixDefinedByHeightAndRevolution	1
swHelixDefinedByPitchAndRevolution	0
swHelixDefinedBySpiral	3

 See Also

[SolidWorks.Interop.swconst Namespace](#)

swHemPositionTypes_e (Type)

SOLIDWORKS API Enumerations

swHemPositionTypes_e Enumeration

See Also

[Send comments on this topic.](#)

 

[SolidWorks.Interop.swconst Namespace](#) : swHemPositionTypes_e Enumeration

Hem position types.

 Syntax

Visual Basic (Declaration)

Public Enum swHemPositionTypes_e
Inherits System.Enum

Visual Basic (Usage)  Copy Code

Dim instance As [swHemPositionTypes_e](#)

C#

public enum swHemPositionTypes_e : System.Enum

C++/CLI

public enum class swHemPositionTypes_e : public System.Enum

 Members

Member	Description
swHemPositionTypeInside	1
swHemPositionTypeOutside	2

 See Also

[SolidWorks.Interop.swconst Namespace](#)

swHemTypes_e (Type)

SOLIDWORKS API Enumerations

swHemTypes_e Enumeration

See Also

[Send comments on this topic.](#)

 

[SolidWorks.Interop.swconst Namespace](#) : swHemTypes_e Enumeration

Hem types.

Syntax

Visual Basic (Declaration)

Public Enum swHemTypes_e
Inherits System.Enum

Visual Basic (Usage)

Dim instance As [swHemTypes_e](#)

C#

public enum swHemTypes_e : System.Enum

C++/CLI

public enum class swHemTypes_e : public System.Enum

Members

Member	Description
swHemTypeClosed	1
swHemTypeDouble	4
swHemTypeOpen	0
swHemTypeRolled	3
swHemTypeTearDrop	2

See Also

[SolidWorks.Interop.swconst Namespace](#)

swHingeMateEntityType_e (Type)

SOLIDWORKS API Enumerations

swHingeMateEntityType_e Enumeration

See Also

[Send comments on this topic.](#)

 

[SolidWorks.Interop.swconst Namespace](#) : swHingeMateEntityType_e Enumeration

Hinge mate entity types.

 Syntax

Visual Basic (Declaration)

Public Enum swHingeMateEntityType_e
Inherits System.Enum

Visual Basic (Usage)  Copy Code

Dim instance As [swHingeMateEntityType_e](#)

C#

public enum swHingeMateEntityType_e : System.Enum

C++/CLI

public enum class swHingeMateEntityType_e : public System.Enum

 Members

Member	Description
swHingeMateEntityType_Angle	2 = Select two faces to define the extent of angular rotation
swHingeMateEntityType_Coincident	1 = Select two coincident entities: - a plane or planar face - another plane, planar face, edge, or point
swHingeMateEntityType_Concentric	0 = Select two concentric entities; valid selections are the same as for concentric mates

 See Also

[SolidWorks.Interop.swconst Namespace](#)

swHlrQuality_e (Type)

SOLIDWORKS API Enumerations

swHlrQuality_e Enumeration

See Also

[Send comments on this topic.](#)

 

SolidWorks.Interop.swconst Namespace : swHlrQuality_e Enumeration

HLR types.

 Syntax

Visual Basic (Declaration)

Public Enum swHlrQuality_e
Inherits System.Enum

Visual Basic (Usage)  Copy Code

Dim instance As [swHlrQuality_e](#)

C#

public enum swHlrQuality_e : System.Enum

C++/CLI

public enum class swHlrQuality_e : public System.Enum

 Members

Member	Description
swFastHlr	1
swPreciseHlr	0

 See Also

[SolidWorks.Interop.swconst Namespace](#)