

SOLIDWORKS Enumerations (swconst) — Reference (10/17): swMoveFaceType_e- swPMUnit_e

SOLIDWORKS API Documentation (converted from CHM)

swMoveFaceType_e (Type)

SOLIDWORKS API Enumerations

swMoveFaceType_e Enumeration

See Also

 

[SolidWorks.Interop.swconst Namespace](#) : swMoveFaceType_e Enumeration

Face move types.

[Send comments on this topic.](#)

Syntax

Visual Basic (Declaration)

```
Public Enum swMoveFaceType_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swMoveFaceType\_e
```

C#

```
public enum swMoveFaceType_e : System.Enum
```

C++/CLI

```
public enum class swMoveFaceType_e : public System.Enum
```

Members

Member	Description
swMoveFaceTypeOffset	0
swMoveFaceTypeRotate	2
swMoveFaceTypeTranslate	1

See Also

[SolidWorks.Interop.swconst Namespace](#)

swMoveFreezeBarTo_e (Type)

SOLIDWORKS API Enumerations

swMoveFreezeBarTo_e Enumeration

See Also

▼

SolidWorks.Interop.swconst Namespace : swMoveFreezeBarTo_e Enumeration

Move options for freeze bar.

[Send comments on this topic.](#)

Syntax

Visual Basic (Declaration)

```
Public Enum swMoveFreezeBarTo_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swMoveFreezeBarTo\_e
```

C#

```
public enum swMoveFreezeBarTo_e : System.Enum
```

C++/CLI

```
public enum class swMoveFreezeBarTo_e : public System.Enum
```

Members

Member	Description
swMoveFreezeBarToAfterFeature	3 = Move freeze bar after the feature
swMoveFreezeBarToBeforeFeature	2 = Move freeze bar before the feature
swMoveFreezeBarToEnd	1 = Move freeze bar to the end of the FeatureManager design tree
swMoveFreezeBarToTop	4 = Move freeze bar to the top of the FeatureManager design tree

See Also

[SolidWorks.Interop.swconst Namespace](#)

swMoveLocation_e (Type)

SOLIDWORKS API Enumerations

swMoveLocation_e Enumeration

See Also

[Send comments on this topic.](#)

 [SolidWorks.Interop.swconst Namespace](#) : swMoveLocation_e Enumeration

Options for moving features in parts and assemblies.

Syntax

Visual Basic (Declaration)

Public Enum swMoveLocation_e
Inherits System.Enum

Visual Basic (Usage)

Dim instance As [swMoveLocation_e](#)

C#

public enum swMoveLocation_e : System.Enum

C++/CLI

public enum class swMoveLocation_e : public System.Enum

Members

Member	Description
swMoveAfter	3
swMoveBefore	2
swMoveToEnd	1
swMoveToFolder	5
swMoveToTop	4

See Also

[SolidWorks.Interop.swconst Namespace](#)

swMoveRollbackBarTo_e (Type)

SOLIDWORKS API Enumerations

swMoveRollbackBarTo_e Enumeration

See Also

[Send comments on this topic.](#)

 

[SolidWorks.Interop.swconst Namespace](#) : swMoveRollbackBarTo_e Enumeration

Position to move rollback bar.

 Syntax

Visual Basic (Declaration)

```
Public Enum swMoveRollbackBarTo_e
    Inherits System.Enum
```

Visual Basic (Usage)  Copy Code

```
Dim instance As swMoveRollbackBarTo\_e
```

C#

```
public enum swMoveRollbackBarTo_e : System.Enum
```

C++/CLI

```
public enum class swMoveRollbackBarTo_e : public System.Enum
```

 Members

Member	Description
swMoveRollbackBarToAfterFeature	4
swMoveRollbackBarToBeforeFeature	3
swMoveRollbackBarToEnd	1
swMoveRollbackBarToPreviousPosition	2

 See Also

[SolidWorks.Interop.swconst Namespace](#)

swNameType_e (Type)

SOLIDWORKS API Enumerations

swNameType_e Enumeration

See Also

Send comments on this topic.

 

SolidWorks.Interop.swconst Namespace : swNameType_e Enumeration

Names of types of entities. [Bitmask](#).

 Syntax

Visual Basic (Declaration)

```
Public Enum swNameType_e
    Inherits System.Enum
```

Visual Basic (Usage)  [Copy Code](#)

```
Dim instance As swNameType\_e
```

C#

```
public enum swNameType_e : System.Enum
```

C++/CLI

```
public enum class swNameType_e : public System.Enum
```

 Members

Member	Description
swBodyName	0
swFeatureName	1

 See Also

[SolidWorks.Interop.swconst Namespace](#)

swNonInterferingComponentDisplay_e (Type)

SOLIDWORKS API Enumerations

swNonInterferingComponentDisplay_e Enumeration

See Also

[Send comments on this topic.](#)

 

[SolidWorks.Interop.swconst Namespace](#) : swNonInterferingComponentDisplay_e Enumeration

Modes to display non-interfering components.

 Syntax

Visual Basic (Declaration)

```
Public Enum swNonInterferingComponentDisplay_e
    Inherits System.Enum
```

Visual Basic (Usage)  Copy Code

```
Dim instance As swNonInterferingComponentDisplay\_e
```

C#

```
public enum swNonInterferingComponentDisplay_e : System.Enum
```

C++/CLI

```
public enum class swNonInterferingComponentDisplay_e : public System.Enum
```

 Members

Member	Description
swNonInterferingComponentDisplay_Current	3
swNonInterferingComponentDisplay_Hidden	1
swNonInterferingComponentDisplay_Transparent	2
swNonInterferingComponentDisplay_Wireframe	0

 See Also

[SolidWorks.Interop.swconst Namespace](#)

swNormalCutErrors_e (Type)

SOLIDWORKS API Enumerations

swNormalCutErrors_e Enumeration

See Also

[Send comments on this topic.](#)

 

[SolidWorks.Interop.swconst Namespace](#) : swNormalCutErrors_e Enumeration

Error codes when creating a sheet metal Normal Cut cut-extrude face group.

 Syntax

Visual Basic (Declaration)

Public Enum swNormalCutErrors_e
Inherits System.Enum

Visual Basic (Usage)

Dim instance As [swNormalCutErrors_e](#)



C#

public enum swNormalCutErrors_e : System.Enum

C++/CLI

public enum class swNormalCutErrors_e : public System.Enum

 Members

Member	Description
swAddNormalCutGroup_Failed	1
swAddNormalCutGroup_Success	0

 See Also

[SolidWorks.Interop.swconst Namespace](#)

swNormalCutParameters_e (Type)

SOLIDWORKS API Enumerations

swNormalCutParameters_e Enumeration

See Also

 

[SolidWorks.Interop.swconst Namespace](#) : swNormalCutParameters_e Enumeration

Sheet metal normal cut parameters.

[Send comments on this topic.](#)

Syntax

Visual Basic (Declaration)

```
Public Enum swNormalCutParameters_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swNormalCutParameters\_e
```

C#

```
public enum swNormalCutParameters_e : System.Enum
```

C++/CLI

```
public enum class swNormalCutParameters_e : public System.Enum
```

Members

Member	Description
swNormalCutExtent	0 = Cuts the maximum amount from the intersection profiles on the top and bottom of the sheet metal body
swNormalCutOffsetPlane	1 = Adjusts the layer where the intersection curve intersects the sheet metal body; Select a reference plane or top or bottom face to define the offset plane and then either set ISMNormalCutFeatureData2-LinkToKFactor to true or set ISMNormalCutFeatureData2-LayerAdjustmentValue to a value between 0 and 1 to adjust the layer

See Also

[SolidWorks.Interop.swconst Namespace](#)

swNotifyEntityType_e (Type)

[SolidWorks.Interop.swconst Namespace](#) : swNotifyEntityType_e Enumeration

Notification entity types.

Syntax

Visual Basic (Declaration)

```
Public Enum swNotifyEntityType_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swNotifyEntityType\_e
```

C#

```
public enum swNotifyEntityType_e : System.Enum
```

C++/CLI

```
public enum class swNotifyEntityType_e : public System.Enum
```

Members

Member	Description
swNotifyBlockDef	Obsolete
swNotifyComponent	2 = Assembly component is being added, renamed, or deleted
swNotifyComponentInternal	8 = Assembly component is internal to the assembly
swNotifyConfiguration	1 = Configuration is being added, renamed, or deleted
swNotifyDerivedConfiguration	4 = Derived configuration is being added, renamed, or deleted
swNotifyDrawingSheet	5 = Drawing sheet is being added, renamed, or deleted
swNotifyDrawingView	6 = Drawing view is being added, renamed, or deleted
swNotifyFeature	3 = Feature is being added, renamed, or deleted

See Also

[SolidWorks.Interop.swconst Namespace](#)

swNumberboxUnitType_e (Type)

SOLIDWORKS API Enumerations

swNumberboxUnitType_e Enumeration

See Also

[SolidWorks.Interop.swconst Namespace](#) : swNumberboxUnitType_e Enumeration

Number box units.

Syntax

Visual Basic (Declaration)

```
Public Enum swNumberboxUnitType_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swNumberboxUnitType\_e
```

C#

```
public enum swNumberboxUnitType_e : System.Enum
```

C++/CLI

```
public enum class swNumberboxUnitType_e : public System.Enum
```

Members

Member	Description
swNumberBox_Angle	4
swNumberBox_Density	5
swNumberBox_Force	7
swNumberBox_Frequency	10
swNumberBox_Gravity	8
swNumberBox_Length	3
swNumberBox_Percent	11
swNumberBox_Stress	6
swNumberBox_Time	9
swNumberBox_UnitlessDouble	2
swNumberBox_UnitlessInteger	1

See Also

[SolidWorks.Interop.swconst Namespace](#)

swNumberedListStartType_e (Type)

SOLIDWORKS API Enumerations

swNumberedListStartType_e Enumeration

See Also

 

SolidWorks.Interop.swconst Namespace : swNumberedListStartType_e Enumeration

Numbered list start types.

[Send comments on this topic.](#)

Syntax

Visual Basic (Declaration)

```
Public Enum swNumberedListStartType_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swNumberedListStartType\_e
```

C#

```
public enum swNumberedListStartType_e : System.Enum
```

C++/CLI

```
public enum class swNumberedListStartType_e : public System.Enum
```

Members

Member	Description
swStartNumberingFromBottom	1
swStartNumberingFromTop	0
swStartNumberingInvalid	-1 = Invalid

See Also

[SolidWorks.Interop.swconst Namespace](#)

swNumberedListType_e (Type)

SOLIDWORKS API Enumerations

swNumberedListType_e Enumeration

[See Also](#)

[Send comments on this topic.](#)

 

[SolidWorks.Interop.swconst Namespace](#) : swNumberedListType_e Enumeration

Numbered list types.

Syntax

Visual Basic (Declaration)

Public Enum swNumberedListType_e
Inherits System.Enum

Visual Basic (Usage)

Dim instance As [swNumberedListType_e](#)

C#

public enum swNumberedListType_e : System.Enum

C++/CLI

public enum class swNumberedListType_e : public System.Enum

Members

Member	Description
swNumberedListType1	1 = 1, 2, 3, etc.
swNumberedListType2	2 = A, B, C, etc.
swNumberedListType3	3 = a, b, c, etc.
swNumberedListType4	4 = i, ii, iii, etc.
swNumberedListType5	5 = i, ii, iii, etc.
swNumberedListTypeInvalid	0 = Invalid

See Also

[SolidWorks.Interop.swconst Namespace](#)

swNumberingFormat_e (Type)

SOLIDWORKS API Enumerations

swNumberingFormat_e Enumeration

[See Also](#)

[Send comments on this topic.](#)

 

SolidWorks.Interop.swconst Namespace : swNumberingFormat_e Enumeration

Format of numbered list items.

Syntax

Visual Basic (Declaration)

```
Public Enum swNumberingFormat_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swNumberingFormat\_e
```

C#

```
public enum swNumberingFormat_e : System.Enum
```

C++/CLI

```
public enum class swNumberingFormat_e : public System.Enum
```

Members

Member	Description
swNumberingFormat1	0 = 1, 2, 3, etc.
swNumberingFormat2	1 = 1., 2., 3, etc.
swNumberingFormat3	2 = (1), (2), (3), etc.
swNumberingFormatInvalid	-1 = Invalid

See Also

[SolidWorks.Interop.swconst Namespace](#)

swNumberingType_e (Type)

SOLIDWORKS API Enumerations

swNumberingType_e Enumeration

[See Also](#)

[SolidWorks.Interop.swconst Namespace](#) : swNumberingType_e Enumeration

Types of numbering for indented BOM tables.

[Send comments on this topic.](#)

Syntax

Visual Basic (Declaration)

```
Public Enum swNumberingType_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swNumberingType\_e
```

C#

```
public enum swNumberingType_e : System.Enum
```

C++/CLI

```
public enum class swNumberingType_e : public System.Enum
```

Members

Member	Description
swIndentedBOMNotSet	3 = The BOM table type is not swBomType_e.swBomType_Indented .
swNumberingType_Detailed	1
swNumberingType_Flat	2
swNumberingType_None	0

See Also

[SolidWorks.Interop.swconst Namespace](#)

swObjectEquality (Type)

 

[SolidWorks.Interop.swconst Namespace](#) : swObjectEquality Enumeration

Object equality states.

 Syntax

Visual Basic (Declaration)

```
Public Enum swObjectEquality
    Inherits System.Enum
```

Visual Basic (Usage)  Copy Code

```
Dim instance As swObjectEquality
```

C#

```
public enum swObjectEquality : System.Enum
```

C++/CLI

```
public enum class swObjectEquality : public System.Enum
```

 Members

Member	Description
swObjectNotSame	0 = Specified objects are not the same object
swObjectSame	1 = Specified objects are the same object
swObjectUnsupported	2 = Unable to determine if the specified objects are the same object

 See Also

[SolidWorks.Interop.swconst Namespace](#)

swOffsetPlanarWireBodyOptions_e (Type)

SOLIDWORKS API Enumerations

swOffsetPlanarWireBodyOptions_e Enumeration

[See Also](#)

 

[SolidWorks.Interop.swconst Namespace](#) : swOffsetPlanarWireBodyOptions_e Enumeration

How to fill the gap between edges.

[Send comments on this topic.](#)

Syntax

Visual Basic (Declaration)

```
Public Enum swOffsetPlanarWireBodyOptions_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swOffsetPlanarWireBodyOptions\_e
```

C#

```
public enum swOffsetPlanarWireBodyOptions_e : System.Enum
```

C++/CLI

```
public enum class swOffsetPlanarWireBodyOptions_e : public System.Enum
```

Members

Member	Description
swOffsetPlanarWireBodyOptions_GapFillExtend	1 = Fill with curve extension
swOffsetPlanarWireBodyOptions_GapFillRound	0 = Fill with circular arc
swOffsetPlanarWireBodyOptions_GapFillTangent	2 = Fill with tangent extension

See Also

[SolidWorks.Interop.swconst Namespace](#)

swOleObjectOptions_e (Type)

SOLIDWORKS API Enumerations

swOleObjectOptions_e Enumeration

[See Also](#)

[Send comments on this topic.](#)

 

SolidWorks.Interop.swconst Namespace : swOleObjectOptions_e Enumeration

OLE object options.

 Syntax

Visual Basic (Declaration)

Public Enum swOleObjectOptions_e
Inherits System.Enum

Visual Basic (Usage)

Dim instance As [swOleObjectOptions_e](#)

C#

public enum swOleObjectOptions_e : System.Enum

C++/CLI

public enum class swOleObjectOptions_e : public System.Enum

 Members

Member	Description
swOleObjectOptions_GetAll	0
swOleObjectOptions_GetOnCurrentSheet	1

 See Also

[SolidWorks.Interop.swconst Namespace](#)

swOnSurfacePlaneProjectType_e (Type)

SOLIDWORKS API Enumerations

swOnSurfacePlaneProjectType_e Enumeration

See Also

 

[SolidWorks.Interop.swconst Namespace](#) : swOnSurfacePlaneProjectType_e Enumeration

Types of planes on surfaces.

[Send comments on this topic.](#)

Syntax

Visual Basic (Declaration)

```
Public Enum swOnSurfacePlaneProjectType_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swOnSurfacePlaneProjectType\_e
```

C#

```
public enum swOnSurfacePlaneProjectType_e : System.Enum
```

C++/CLI

```
public enum class swOnSurfacePlaneProjectType_e : public System.Enum
```

Members

Member	Description
swOnSurfacePlaneProjectAlongSketchNormal	1
swOnSurfacePlaneProjecttoNearestLocation	0

See Also

[SolidWorks.Interop.swconst Namespace](#)

swOpenDocOptions_e (Type)

SOLIDWORKS API Enumerations

swOpenDocOptions_e Enumeration

See Also

▼

SolidWorks.Interop.swconst Namespace : swOpenDocOptions_e Enumeration

How to open documents using ISldWorks::OpenDoc6, Bitmask.

[Send comments on this topic.](#)

 Syntax

Visual Basic (Declaration)

```
Public Enum swOpenDocOptions_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swOpenDocOptions_e
```

C#

```
public enum swOpenDocOptions_e : System.Enum
```

C++/CLI

```
public enum class swOpenDocOptions_e : public System.Enum
```

 Members

Member	Description
swOpenDocOptions_AdvancedConfig	8192 or 0x2000: Open assembly using an advanced configuration
swOpenDocOptions_AutoMissingConfig	32 or 0x20 = Obsolete; do not use The software automatically uses the last-used configuration of a model when it discovers missing configurations or component references as it silently opens drawings and assemblies.
swOpenDocOptions_DontLoadHiddenComponents	256 or 0x100 = By default, hidden components are loaded when you open an assembly document. Set swOpenDocOptions_DontLoadHiddenComponents to not load hidden components when opening an assembly document
swOpenDocOptions_LDR_EditAssembly	2048 or 0x800 = Open in Large Design Review (resolved) mode with edit assembly enabled; use in combination with swOpenDocOptions_ViewOnly
swOpenDocOptions_LoadExternalReferencesInMemory	512 or 0x200 = Open external references in memory only; this setting is valid only if swUserPreferenceIntegerValue_e.swLoadExternalReferences is not set to swLoadExternalReferences_e.swLoadExternalReferences_None swUserPreferenceToggle_e.swExtRefLoadRefDocsInMemory (System Options > External References > Load documents in memory only) is ignored when opening documents through the API because IDocumentSpecification::LoadExternalReferencesInMemory and ISldWorks::OpenDoc6 (swOpenDocOptions_e.swOpenDocOptions_LoadExternalReferencesInMemory) have sole control of reference loading
swOpenDocOptions_LoadLightweight	128 or 0x80 = Open assembly document as lightweight NOTE: The default for whether an assembly document is opened lightweight is based on a registry setting accessed via Tools, Options, Assemblies or with the user preference setting swAutoLoadPartsLightweight To override the default and specify a value with ISldWorks::OpenDoc6, set swOpenDocOptions_OverrideDefaultLoadLightweight. If set, then you can set swOpenDocOptions_LoadLightweight to open an assembly document as lightweight
swOpenDocOptions_LoadModel	16 or 0x10 = Load Detached model upon opening document (drawings only)
swOpenDocOptions_OpenDetailingMode	1024 or 0x400 = Open document in detailing mode
swOpenDocOptions_OverrideDefaultLoadLightweight	64 or 0x40 = Override default setting whether to open an assembly document as lightweight
swOpenDocOptions_RapidDraft	8 or 0x8 = Convert document to Detached format (drawings only)
swOpenDocOptions_ReadOnly	2 or 0x2 = Open document read only
swOpenDocOptions_Silent	1 or 0x1 = Open document silently
swOpenDocOptions_SpeedPak	4096 or 0x1000 = Open document using the SpeedPak option
swOpenDocOptions_ViewOnly	4 or 0x4 = Open document in Large Design Review mode (assemblies only)

 See Also

[SolidWorks.Interop.swconst Namespace](#)

swOrdDimEndSymbol_e (Type)

SOLIDWORKS API Enumerations

swOrdDimEndSymbol_e Enumeration

See Also

[Send comments on this topic.](#)

 

SolidWorks.Interop.swconst Namespace : swOrdDimEndSymbol_e Enumeration

Ordinate dimension end symbols.

 Syntax

Visual Basic (Declaration)

Public Enum swOrdDimEndSymbol_e
Inherits System.Enum

Visual Basic (Usage)  Copy Code

Dim instance As [swOrdDimEndSymbol_e](#)

C#

public enum swOrdDimEndSymbol_e : System.Enum

C++/CLI

public enum class swOrdDimEndSymbol_e : public System.Enum

 Members

Member	Description
swOrdDimEndSymbol_Dowel	1
swOrdDimEndSymbol_DownwardLeft	3
swOrdDimEndSymbol_None	0
swOrdDimEndSymbol_UpwardRight	2

 See Also

[SolidWorks.Interop.swconst Namespace](#)

swOutOfDateStatus_e (Type)

SOLIDWORKS API Enumerations

swOutOfDateStatus_e Enumeration

See Also

[Send comments on this topic.](#)

 

[SolidWorks.Interop.swconst Namespace](#) : swOutOfDateStatus_e Enumeration

Rebuild state of the components.

 Syntax

Visual Basic (Declaration)

Public Enum swOutOfDateStatus_e
Inherits System.Enum

Visual Basic (Usage)  Copy Code

Dim instance As [swOutOfDateStatus_e](#)

C#

public enum swOutOfDateStatus_e : System.Enum

C++/CLI

public enum class swOutOfDateStatus_e : public System.Enum

 Members

Member	Description
swModelOutOfDate	2
swModelUpToDate	1
swUnknownState	0

 See Also

[SolidWorks.Interop.swconst Namespace](#)

swPackAndGoDocumentStatus_e (Type)

SOLIDWORKS API Enumerations

swPackAndGoDocumentStatus_e Enumeration

[See Also](#)

 

[SolidWorks.Interop.swconst Namespace](#) : swPackAndGoDocumentStatus_e Enumeration

Types of documents for Pack and Go.

[Send comments on this topic.](#)

Syntax

Visual Basic (Declaration)

```
Public Enum swPackAndGoDocumentStatus_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swPackAndGoDocumentStatus\_e
```

C#

```
public enum swPackAndGoDocumentStatus_e : System.Enum
```

C++/CLI

```
public enum class swPackAndGoDocumentStatus_e : public System.Enum
```

Members

Member	Description
swPackAndGoDocumentStatus_Normal	0 = Normal
swPackAndGoDocumentStatus_Unknown	2 = Unknown
swPackAndGoDocumentStatus_Virtual	1 = Virtual

See Also

[SolidWorks.Interop.swconst Namespace](#)

swPackAndGoFolderOptions_e (Type)

SOLIDWORKS API Enumerations

swPackAndGoFolderOptions_e Enumeration

[See Also](#)

 

[SolidWorks.Interop.swconst Namespace](#) : swPackAndGoFolderOptions_e Enumeration

Types of folder structure options for Pack and Go.

[Send comments on this topic.](#)

 Syntax

Visual Basic (Declaration)

```
Public Enum swPackAndGoFolderOptions_e
    Inherits System.Enum
```

Visual Basic (Usage)  Copy Code

```
Dim instance As swPackAndGoFolderOptions\_e
```

C#

```
public enum swPackAndGoFolderOptions_e : System.Enum
```

C++/CLI

```
public enum class swPackAndGoFolderOptions_e : public System.Enum
```

 Members

Member	Description
swPackAndGoFolderOptions_FullStructure	2
swPackAndGoFolderOptions_MinimalFolders	1
swPackAndGoFolderOptions_SingleFolder	0

 See Also

[SolidWorks.Interop.swconst Namespace](#)

swPackAndGoSaveStatus_e (Type)

SOLIDWORKS API Enumerations

swPackAndGoSaveStatus_e Enumeration

See Also

[Send comments on this topic.](#)

 

[SolidWorks.Interop.swconst Namespace](#) : swPackAndGoSaveStatus_e Enumeration

Status of each document intended for Pack and Go.

 Syntax

Visual Basic (Declaration)

```
Public Enum swPackAndGoSaveStatus_e
    Inherits System.Enum
```

Visual Basic (Usage)  Copy Code

```
Dim instance As swPackAndGoSaveStatus\_e
```

C#

```
public enum swPackAndGoSaveStatus_e : System.Enum
```

C++/CLI

```
public enum class swPackAndGoSaveStatus_e : public System.Enum
```

 Members

Member	Description
swPackAndGoSaveStatus_FileAlreadyExist	2 = File already exists
swPackAndGoSaveStatus_SaveError	4 = Save error
swPackAndGoSaveStatus_SaveToEmpty	3 = Saving empty file
swPackAndGoSaveStatus_Succeed	0 = Success
swPackAndGoSaveStatus_UserInputNotCorrect	1 = User input not correct

 See Also

[SolidWorks.Interop.swconst Namespace](#)

swPageSetupDrawingColor_e (Type)

SOLIDWORKS API Enumerations

swPageSetupDrawingColor_e Enumeration

See Also

 

SolidWorks.Interop.swconst Namespace : swPageSetupDrawingColor_e Enumeration

Colors of drawings set-up values.

[Send comments on this topic.](#)

Syntax

Visual Basic (Declaration)

```
Public Enum swPageSetupDrawingColor_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swPageSetupDrawingColor\_e
```

C#

```
public enum swPageSetupDrawingColor_e : System.Enum
```

C++/CLI

```
public enum class swPageSetupDrawingColor_e : public System.Enum
```

Members

Member	Description
swPageSetup_AutomaticDrawingColor	1
swPageSetup_BlackAndWhite	3
swPageSetup_ColorGrey	2

See Also

[SolidWorks.Interop.swconst Namespace](#)

swPageSetupInUse_e (Type)

SOLIDWORKS API Enumerations

swPageSetupInUse_e Enumeration

[See Also](#)

 [SolidWorks.Interop.swconst Namespace](#) : swPageSetupInUse_e Enumeration

Page set-up values.

[Send comments on this topic.](#)

Syntax

Visual Basic (Declaration)

```
Public Enum swPageSetupInUse_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swPageSetupInUse\_e
```

C#

```
public enum swPageSetupInUse_e : System.Enum
```

C++/CLI

```
public enum class swPageSetupInUse_e : public System.Enum
```

Members

Member	Description
swPageSetupInUse_Application	1
swPageSetupInUse_Document	2
swPageSetupInUse_DrawingSheet	3

See Also

[SolidWorks.Interop.swconst Namespace](#)

swPageSetupOrientation_e (Type)

SOLIDWORKS API Enumerations

swPageSetupOrientation_e Enumeration

[Send comments on this topic.](#)

[See Also](#)

 

[SolidWorks.Interop.swconst Namespace](#) : swPageSetupOrientation_e Enumeration

Page orientation set-up values.

Syntax

Visual Basic (Declaration)

Public Enum swPageSetupOrientation_e
Inherits System.Enum

Visual Basic (Usage)

Dim instance As [swPageSetupOrientation_e](#)

C#

public enum swPageSetupOrientation_e : System.Enum

C++/CLI

public enum class swPageSetupOrientation_e : public System.Enum

Members

Member	Description
swPageSetupOrient_Landscape	2
swPageSetupOrient_Portrait	1

See Also

[SolidWorks.Interop.swconst Namespace](#)

swParabolaPts_e (Type)

SOLIDWORKS API Enumerations

swParabolaPts_e Enumeration

See Also

[Send comments on this topic.](#)

 

[SolidWorks.Interop.swconst Namespace](#) : swParabolaPts_e Enumeration

Parabola points.

 Syntax

Visual Basic (Declaration)

```
Public Enum swParabolaPts_e
    Inherits System.Enum
```

Visual Basic (Usage)  Copy Code

```
Dim instance As swParabolaPts\_e
```

C#

```
public enum swParabolaPts_e : System.Enum
```

C++/CLI

```
public enum class swParabolaPts_e : public System.Enum
```

 Members

Member	Description
swParabolaApexPt	3
swParabolaEndPt	1
swParabolaFocusPt	2
swParabolaStartPt	0

 See Also

[SolidWorks.Interop.swconst Namespace](#)

swParagraphType_e (Type)

SOLIDWORKS API Enumerations

swParagraphType_e Enumeration

See Also

 

[SolidWorks.Interop.swconst Namespace](#) : swParagraphType_e Enumeration

Paragraph list types.

[Send comments on this topic.](#)

 Syntax

Visual Basic (Declaration)

Public Enum swParagraphType_e
Inherits System.Enum

Visual Basic (Usage)

Dim instance As [swParagraphType_e](#)



C#

public enum swParagraphType_e : System.Enum

C++/CLI

public enum class swParagraphType_e : public System.Enum

 Members

Member	Description
swParagraphBullet	0
swParagraphNone	-1
swParagraphNumbered	1

 See Also

[SolidWorks.Interop.swconst Namespace](#)

swParameterizationPropertyType_e (Type)

SOLIDWORKS API Enumerations

swParameterizationPropertyType_e Enumeration

See Also

 

[SolidWorks.Interop.swconst Namespace](#) : swParameterizationPropertyType_e Enumeration

Properties of U and V parameters.

[Send comments on this topic.](#)

 Syntax

Visual Basic (Declaration)

```
Public Enum swParameterizationPropertyType_e
    Inherits System.Enum
```

Visual Basic (Usage)  Copy Code

```
Dim instance As swParameterizationPropertyType\_e
```

C#

```
public enum swParameterizationPropertyType_e : System.Enum
```

C++/CLI

```
public enum class swParameterizationPropertyType_e : public System.Enum
```

 Members

Member	Description
swParameterizationPropertyType_AllDerivativesContinuous	13737
swParameterizationPropertyType_AllDerivativesNotContinuous	13738
swParameterizationPropertyType_BoundsCoincident	13746 = Bounds at the ends of the parameter range are coincident
swParameterizationPropertyType_Circular	13740 = The parameter represents an angle around a circle; A circle indicates that the other parameter is a constant
swParameterizationPropertyType_Linear	13739 = The parameter is proportional to the distance along a straight line; A straight line indicates that the other parameter is a constant
swParameterizationPropertyType_Periodic	13701 = Periodic parameterization

 See Also

[SolidWorks.Interop.swconst Namespace](#)

swParamType_e (Type)

 

[SolidWorks.Interop.swconst Namespace](#) : swParamType_e Enumeration

Parameter data types.

 Syntax

Visual Basic (Declaration)

```
Public Enum swParamType_e
    Inherits System.Enum
```

Visual Basic (Usage)  [Copy Code](#)

```
Dim instance As swParamType\_e
```

C#

```
public enum swParamType_e : System.Enum
```

C++/CLI

```
public enum class swParamType_e : public System.Enum
```

 Members

Member	Description
swParamTypeDouble	0
swParamTypeDVector	3
swParamTypeInteger	2
swParamTypeString	1

 See Also

[SolidWorks.Interop.swconst Namespace](#)

swParasolidOutputVersion_e (Type)

SOLIDWORKS API Enumerations

swParasolidOutputVersion_e Enumeration

See Also

 SolidWorks.Interop.swconst Namespace : swParasolidOutputVersion_e Enumeration

Parasolid output versions.

[Send comments on this topic.](#)

Syntax

Visual Basic (Declaration)

```
Public Enum swParasolidOutputVersion_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swParasolidOutputVersion\_e
```

C#

```
public enum swParasolidOutputVersion_e : System.Enum
```

C++/CLI

```
public enum class swParasolidOutputVersion_e : public System.Enum
```

Members

Member	Description
swParasolidOutputVersion_100	4
swParasolidOutputVersion_110	5
swParasolidOutputVersion_111	6
swParasolidOutputVersion_120	7
swParasolidOutputVersion_121	8
swParasolidOutputVersion_130	9
swParasolidOutputVersion_140	10
swParasolidOutputVersion_150	11
swParasolidOutputVersion_151	12
swParasolidOutputVersion_160	13
swParasolidOutputVersion_161	14
swParasolidOutputVersion_171	15
swParasolidOutputVersion_181	16
swParasolidOutputVersion_191	17
swParasolidOutputVersion_200	18
swParasolidOutputVersion_210	19
swParasolidOutputVersion_220	20
swParasolidOutputVersion_230	21
swParasolidOutputVersion_240	22
swParasolidOutputVersion_250	23
swParasolidOutputVersion_260	24
swParasolidOutputVersion_270	25
swParasolidOutputVersion_280	26
swParasolidOutputVersion_290	27
swParasolidOutputVersion_300	28
swParasolidOutputVersion_310	29
swParasolidOutputVersion_320	30
swParasolidOutputVersion_330	31
swParasolidOutputVersion_341	32
swParasolidOutputVersion_351	DO NOT USE; instead, use swParasolidOutputVersion_latest = 0
swParasolidOutputVersion_80	1
swParasolidOutputVersion_90	2
swParasolidOutputVersion_91	3
swParasolidOutputVersion_latest	0

See Also

[SolidWorks.Interop.swconst Namespace](#)

swPartConfigurationGroupingOption_e (Type)

SOLIDWORKS API Enumerations

swPartConfigurationGroupingOption_e Enumeration

[Send comments on this topic.](#)

[See Also](#)

 

[SolidWorks.Interop.swconst Namespace](#) : swPartConfigurationGroupingOption_e Enumeration

Part configuration groupings for BOM table display.

 Syntax

Visual Basic (Declaration)

Public Enum swPartConfigurationGroupingOption_e
Inherits System.Enum

Visual Basic (Usage)  Copy Code

Dim instance As [swPartConfigurationGroupingOption_e](#)

C#

public enum swPartConfigurationGroupingOption_e : System.Enum

C++/CLI

public enum class swPartConfigurationGroupingOption_e : public System.Enum

 Members

Member	Description
swDisplay_AllConfigurationOfSamePart_AsOneItem	2 = display configurations of the same part as one item
swDisplay_ConfigurationOfSamePart_AsSeparateItem	1 = display configurations of the same part as separate items
swDisplay_ConfigurationWithSameName_AsOneItem	3 = display configurations with the same name as one item

 See Also

[SolidWorks.Interop.swconst Namespace](#)

swPartDimXpertToleranceMethod_e (Type)

SOLIDWORKS API Enumerations

swPartDimXpertToleranceMethod_e Enumeration

See Also

 

[SolidWorks.Interop.swconst Namespace](#) : swPartDimXpertToleranceMethod_e Enumeration

DimXpert tolerance methods.

[Send comments on this topic.](#)

Syntax

Visual Basic (Declaration)

```
Public Enum swPartDimXpertToleranceMethod_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swPartDimXpertToleranceMethod\_e
```

C#

```
public enum swPartDimXpertToleranceMethod_e : System.Enum
```

C++/CLI

```
public enum class swPartDimXpertToleranceMethod_e : public System.Enum
```

Members

Member	Description
swPartDimXpertToleranceMethod_BlockTolerance	0
swPartDimXpertToleranceMethod_GeneralBlockTolerance	2
swPartDimXpertToleranceMethod_GeneralTolerance	1

See Also

[SolidWorks.Interop.swconst Namespace](#)

swPartingLineFeatureStatus_e (Type)

SOLIDWORKS API Enumerations

swPartingLineFeatureStatus_e Enumeration

See Also

▼

SolidWorks.Interop.swconst Namespace : swPartingLineFeatureStatus_e Enumeration

Statuses of parting line features.

[Send comments on this topic.](#)

Syntax

Visual Basic (Declaration)

```
Public Enum swPartingLineFeatureStatus_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swPartingLineFeatureStatus\_e
```

C#

```
public enum swPartingLineFeatureStatus_e : System.Enum
```

C++/CLI

```
public enum class swPartingLineFeatureStatus_e : public System.Enum
```

Members

Member	Description
STATUS_MOLD_PARTINGLINE_EDGES_OPEN	2 = Select edges that form a closed loop
STATUS_MOLD_PARTINGLINE_NON_SEPARABLE	4 = The parting line is complete, but the mold cannot be separated into core and cavity; you might need to create shut-off surfaces
STATUS_MOLD_PARTINGLINE_SEPARABLE	3 = The parting line is complete; the mold can be separated into core and cavity
STATUS_MOLD_REDUNDANT_EDGES	1 = There are more than enough edges selected to form a parting line; remove any redundant edges or add edges to close gaps between disjoint edge chains

See Also

[SolidWorks.Interop.swconst Namespace](#)

swPartingSurfaceMoldParmType_e (Type)

SOLIDWORKS API Enumerations

swPartingSurfaceMoldParmType_e Enumeration

See Also

 

[SolidWorks.Interop.swconst Namespace](#) : swPartingSurfaceMoldParmType_e Enumeration

Types of mold parting surfaces.

[Send comments on this topic.](#)

Syntax

Visual Basic (Declaration)

```
Public Enum swPartingSurfaceMoldParmType_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swPartingSurfaceMoldParmType\_e
```

C#

```
public enum swPartingSurfaceMoldParmType_e : System.Enum
```

C++/CLI

```
public enum class swPartingSurfaceMoldParmType_e : public System.Enum
```

Members

Member	Description
swPartingSurfaceMoldParmNormal	1
swPartingSurfaceMoldParmPerpendicular	4
swPartingSurfaceMoldParmTangent	0

See Also

[SolidWorks.Interop.swconst Namespace](#)

swPartingSurfaceSmoothingType_e (Type)

SOLIDWORKS API Enumerations

swPartingSurfaceSmoothingType_e Enumeration

[Send comments on this topic.](#)

[See Also](#)

 

[SolidWorks.Interop.swconst Namespace](#) : swPartingSurfaceSmoothingType_e Enumeration

Smooth mold parting surfaces.

 Syntax

Visual Basic (Declaration)

Public Enum swPartingSurfaceSmoothingType_e
Inherits System.Enum

Visual Basic (Usage)

Dim instance As [swPartingSurfaceSmoothingType_e](#)

 [Copy Code](#)

C#

public enum swPartingSurfaceSmoothingType_e : System.Enum

C++/CLI

public enum class swPartingSurfaceSmoothingType_e : public System.Enum

 Members

Member	Description
swPartingSurfaceSharp	1
swPartingSurfaceSmooth	2

 See Also

[SolidWorks.Interop.swconst Namespace](#)

swPartnerEntitlementStatus_e (Type)

SOLIDWORKS API Enumerations

swPartnerEntitlementStatus_e Enumeration

See Also

Send comments on this topic.

 

SolidWorks.Interop.swconst Namespace : swPartnerEntitlementStatus_e Enumeration

Partner entitlement status.

 Syntax

Visual Basic (Declaration)

```
Public Enum swPartnerEntitlementStatus_e
    Inherits System.Enum
```

Visual Basic (Usage)  Copy Code

```
Dim instance As swPartnerEntitlementStatus\_e
```

C#

```
public enum swPartnerEntitlementStatus_e : System.Enum
```

C++/CLI

```
public enum class swPartnerEntitlementStatus_e : public System.Enum
```

 Members

Member	Description
swPEAddinGUIDMismatch	4 or 0x4
swPEAddinNameMismatch	2 or 0x2
swPEFail	1 or 0x1
swPELicenseError	64 or 0x40
swPELicenseExpired	16 or 0x10
swPESuccess	0 or 0x0
swPETierMismatch	32 or 0x20
swPEVersionMismatch	8 or 0x8

 See Also

[SolidWorks.Interop.swconst Namespace](#)

swPartNotify_e (Type)

SOLIDWORKS API Enumerations

swPartNotify_e Enumeration

See Also

Send comments on this topic.

 SolidWorks.Interop.swconst Namespace : swPartNotify_e Enumeration

Part notifications.

 Syntax

Visual Basic (Declaration)

Public Enum swPartNotify_e
Inherits System.Enum

Visual Basic (Usage)

Dim instance As [swPartNotify_e](#)

C#

public enum swPartNotify_e : System.Enum

C++/CLI

public enum class swPartNotify_e : public System.Enum

 Members

Member	Description
swPartActiveAnnotationViewChangeNotify	80 = ActiveAnnotationViewChangeNotify
swPartActiveDisplayStateChangePostNotify	61 = ActiveDisplayStateChangePostNotify
swPartActiveDisplayStateChangePreNotify	60 = ActiveDisplayStateChangePreNotify
swPartActiveViewChangeNotify	53 = ActiveViewChangeNotify
swPartAddCustomPropertyNotify	21 = AddCustomPropertyNotify
swPartAddDependencyNotify	85 = AddDependencyNotify
swPartAddDvePagePreNotify	Not used
swPartAddItemNotify	16 = AddItemNotify
swPartAutoSaveNotify	12 = AutoSaveNotify
swPartAutoSaveToStorageNotify	13 = AutoSaveToStorageNotify
swPartAutoSaveToStorageStoreNotify	66 = AutoSaveToStorageStoreNotify
swPartBodyVisibleChangeNotify	29 = BodyVisibleChangeNotify
swPartChangeCustomPropertyNotify	22 = ChangeCustomPropertyNotify
swPartClearSelectionsNotify	42 = ClearSelectionsNotify
swPartCloseDesignTableNotify	46 = CloseDesignTableNotify
swPartCommandManagerTabActivatedPreNotify	71 = CommandManagerTabActivatedPreNotify
swPartConfigChangeNotify	10 = ActiveConfigChangeNotify
swPartConfigChangePostNotify	11 = ActiveConfigChangePostNotify
swPartConfigurationChangeNotify	51 = ConfigurationChangeNotify
swPartConvertToBodiesPostNotify	78 = ConvertToBodiesPostNotify
swPartConvertToBodiesPreNotify	77 = ConvertToBodiesPreNotify
swPartDeleteCustomPropertyNotify	23 = DeleteCustomPropertyNotify
swPartDeleteDependencyNotify	86 = DeleteDependencyNotify
swPartDeleteItemNotify	18 = DeleteItemNotify
swPartDeleteItemPreNotify	41 = DeleteItemPreNotify
swPartDeleteSelectionPreNotify	27 = DeleteSelectionPreNotify
swPartDestroyNotify	Obsolete
swPartDestroyNotify2	50 = DestroyNotify2
swPartDimensionChangeNotify	37 = DimensionChangeNotify
swPartDisplayPaneCollapseNotify	82 = DisplayPaneCollapseNotify
swPartDisplayPaneExpandNotify	81 = DisplayPaneExpandNotify
swPartDragStateChangeNotify	67 = DragStateChangeNotify
swPartDynamicHighlightNotify	36 = DynamicHighlightNotify
swPartEquationEditorPostNotify	44 = EquationEditorPostNotify
swPartEquationEditorPreNotify	43 = EquationEditorPreNotify
swPartFeatureEditPreNotify	24 = FeatureEditPreNotify
swPartFeatureManagerFilterStringChangeNotify	54 = FeatureManagerFilterStringChangeNotify
swPartFeatureManagerTabActivatedNotify	75 = FeatureManagerTabActivatedNotify
swPartFeatureManagerTabActivatedPreNotify	74 = FeatureManagerTabActivatedPreNotify
swPartFeatureManagerTreeRebuildNotify	34 = FeatureManagerTreeRebuildNotify
swPartFeatureSketchEditPreNotify	25 = FeatureSketchEditPreNotify
swPartFileDropPostNotify	35 = FileDropPostNotify
swPartFileDropPreNotify	56 = FileDropPreNotify
swPartFileReloadCancelNotify	38 = FileReloadCancelNotify
swPartFileReloadNotify	20 = FileReloadNotify
swPartFileReloadPreNotify	28 = FileReloadPreNotify
swPartFileSaveAsNotify	Obsolete
swPartFileSaveAsNotify2	26 = FileSaveAsNotify2
swPartFileSaveNotify	6 = FileSaveNotify
swPartFileSavePostCancelNotify	39 = FileSavePostCancelNotify
swPartFileSavePostNotify	31 = FileSavePostNotify
swPartFlipLoopNotify	55 = FlipLoopNotify
swPartInsertTableNotify	68 = InsertTableNotify
swPartLightingDialogCreateNotify	15 = LightingDialogCreateNotify
swPartLoadFromStorageNotify	8 = LoadFromStorageNotify
swPartLoadFromStorageStoreNotify	32 = LoadFromStorageStoreNotify
swPartModifyNotify	19 = ModifyNotify

swPartModifyTableNotify	69 = ModifyTableNotify
swPartNewSelectionNotify	5 = NewSelectionNotify
swPartOpenDesignTableNotify	45 = OpenDesignTableNotify
swPartPreRenameItemNotify	72 = PreRenameItemNotify
swPartPromptBodiesToKeepNotify	47 = PromptBodiesToKeepNotify
swPartPublishTo3DPDFNotify	78 = PublishTo3DPDFNotify
swPartRedoPostNotify	62 = RedoPostNotify
swPartRedoPreNotify	63 = RedoPreNotify
swPartRegenNotify	1 = RegenNotify
swPartRegenPostNotify	Obsolete
swPartRegenPostNotify2	30 = RegenPostNotify2
swPartRenamedDocumentNotify	73 = RenamedDocumentNotify
swPartRenameDisplayTitleNotify	79 = RenameDisplayTitleNotify
swPartRenameItemNotify	17 = RenameItemNotify
swPartSaveToStorageNotify	9 = SaveToStorageNotify
swPartSaveToStorageStoreNotify	33 = SaveToStorageStoreNotify
swPartSensorAlertPreNotify	57 = SensorAlertPreNotify
swPartSketchSolveNotify	40 = SketchSolveNotify
swPartSolidBodyFolderReorderNotify	83 = SolidBodyFolderReorderNotify
swPartSuppressionStateChangeNotify	52 = SuppressionStateChangeNotify
swPartUndoPostNotify	58 = UndoPostNotify
swPartUndoPreNotify	64 = UndoPreNotify
swPartUnitsChangeNotify	49 = UnitsChangeNotify
swPartUserSelectionPostNotify	70 = UserSelectionPostNotify
swPartUserSelectionPreNotify	59 = UserSelectionPreNotify
swPartViewNewNotify	Obsolete
swPartViewNewNotify2	14 = ViewNewNotify2
swPartWeldmentCutListUpdatePostNotify	65 = WeldmentCutListUpdatePostNotify

Remarks

To receive notifications, a DLL application must register for the notifications by object type. This registration must be done for each instance of a particular object. For example:

For example, in the file in the Visual C++ 6.0 wizard-generated add-in that supports part events (e.g., PartDoc.h), include:

```
BEGIN_SINK_MAP(CSwPart)

    SINK_ENTRY_EX(ID_PARTDOC_EVENTS, DIID_DPartDocEvents, swPartDestroyNotify, DestroyNotify)

    SINK_ENTRY_EX(ID_PARTDOC_EVENTS, DIID_DPartDocEvents, swPartNewSelectionNotify,
NewSelectionNotify)

END_SINK_MAP()
```

If developing a C++ application, use these enumerators to [register for notifications](#) for [IPartDoc](#) events.

See Also

[SolidWorks.Interop.swconst Namespace](#)

swPatternElementSelection_e (Type)

SOLIDWORKS API Enumerations

swPatternElementSelection_e Enumeration

See Also

[Send comments on this topic.](#)

 

SolidWorks.Interop.swconst Namespace : swPatternElementSelection_e Enumeration

Pattern element selection options.

 Syntax

Visual Basic (Declaration)

```
Public Enum swPatternElementSelection_e
    Inherits System.Enum
```

Visual Basic (Usage)  Copy Code

```
Dim instance As swPatternElementSelection\_e
```

C#

```
public enum swPatternElementSelection_e : System.Enum
```

C++/CLI

```
public enum class swPatternElementSelection_e : public System.Enum
```

 Members

Member	Description
swBodiesToPattern	2
swErrorInPatternElementSelection	0
swFeatureFaces	1

 See Also

[SolidWorks.Interop.swconst Namespace](#)

swPatternEndCondition_e (Type)

SOLIDWORKS API Enumerations

swPatternEndCondition_e Enumeration

See Also

 

[SolidWorks.Interop.swconst Namespace](#) : swPatternEndCondition_e Enumeration

Pattern spacing options.

[Send comments on this topic.](#)

Syntax

Visual Basic (Declaration)

Public Enum swPatternEndCondition_e
Inherits System.Enum

Visual Basic (Usage)

Dim instance As [swPatternEndCondition_e](#)

C#

public enum swPatternEndCondition_e : System.Enum

C++/CLI

public enum class swPatternEndCondition_e : public System.Enum

Members

Member	Description
swPatternEndCondition_SpacingAndInstances	0 = Independently set the pattern instance number and spacing
swPatternEndCondition_UpToReference	1 = Pattern instance number and spacing is based on a selected up-to-reference geometry and an offset

See Also

[SolidWorks.Interop.swconst Namespace](#)

swPatternFeatureImportExportError_e (Type)

SOLIDWORKS API Enumerations

swPatternFeatureImportExportError_e Enumeration

See Also

▼

SolidWorks.Interop.swconst Namespace : swPatternFeatureImportExportError_e Enumeration

Variable pattern feature errors when importing or exporting Microsoft Excel data.

Syntax

Visual Basic (Declaration)

```
Public Enum swPatternFeatureImportExportError_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swPatternFeatureImportExportError\_e
```

C#

```
public enum swPatternFeatureImportExportError_e : System.Enum
```

C++/CLI

```
public enum class swPatternFeatureImportExportError_e : public System.Enum
```

Members

Member	Description
swPatternFeatureImportExportError_AccessDeniedOrInvalidPath	19 = Access denied or invalid path
swPatternFeatureImportExportError_ColumnARows1And2Error	5 = Column A, Rows 1 and 2 must be merged and named Instance
swPatternFeatureImportExportError_ColumnBRows1And2Error	7 = Column B, Rows 1 and 2 must be merged and named Instances to Skip
swPatternFeatureImportExportError_DimensionNameDoesNotExist	12 = Dimension name does not exist in the parent feature
swPatternFeatureImportExportError_DimValueFormatIncorrect	15 = Dimension is incorrectly formatted
swPatternFeatureImportExportError_DuplicateDimensions	10 = Duplicate dimensions are not allowed in the import file
swPatternFeatureImportExportError_EmptyRowsOrColumns	4 = Empty rows or columns are not allowed
swPatternFeatureImportExportError_Failed	1 = Failed
swPatternFeatureImportExportError_FailedToRetrieveExcelApp	20 = Failed to find Microsoft Excel application
swPatternFeatureImportExportError_FailedToRetrieveModelDocument	16 = Failed to retrieve model document
swPatternFeatureImportExportError_FeatureDoesNotExist	9 = Feature does not exist in the selected features or references to pattern
swPatternFeatureImportExportError_FeatureOrDimDoesNotExist	13 = Feature does not exist in the selected features or references to pattern, or the dimension name does not exist in the parent feature
swPatternFeatureImportExportError_FileExistsAndOverwritelsFalse	17 = Microsoft Excel file exists, but the file cannot be overwritten
swPatternFeatureImportExportError_ImproperValuesForColumnB	8 = Invalid value; valid values are 0 (not skipped) or 1 (skipped)
swPatternFeatureImportExportError_InstNumStartsFromNonZero	6 = Instances in the Microsoft Excel table must start at 0
swPatternFeatureImportExportError_NoValidDimensionToImport	14 = No valid dimensions to import from this Microsoft Excel file
swPatternFeatureImportExportError_OutOfRangeDimensionValue	11 = Dimension in this cell is not in the range of dimensions
swPatternFeatureImportExportError_ReadOnlyFile	18 = Microsoft Excel file is read only
swPatternFeatureImportExportError_Succeed	0 = Succeeded
swPatternFeatureImportExportError_UnequalNumOfCellsInColumn	2 = All columns containing dimensions in this imported table must have the same number of cells; these columns cannot be empty or merged
swPatternFeatureImportExportError_UnequalNumOfCellsInRow	3 = All rows containing dimensions in this imported table must have the same number of cells; these rows cannot be empty or merged

See Also

[SolidWorks.Interop.swconst Namespace](#)

swPatternLayoutSpacingType_e (Type)

SOLIDWORKS API Enumerations

swPatternLayoutSpacingType_e Enumeration

See Also

[Send comments on this topic.](#)

 

[SolidWorks.Interop.swconst Namespace](#) : swPatternLayoutSpacingType_e Enumeration

Pattern layout spacing types.

 Syntax

Visual Basic (Declaration)

```
Public Enum swPatternLayoutSpacingType_e
    Inherits System.Enum
```

Visual Basic (Usage)  Copy Code

```
Dim instance As swPatternLayoutSpacingType\_e
```

C#

```
public enum swPatternLayoutSpacingType_e : System.Enum
```

C++/CLI

```
public enum class swPatternLayoutSpacingType_e : public System.Enum
```

 Members

Member	Description
swPatternLayoutInstances	1 = Specify number of instances per loop or side of the pattern layout
swPatternLayoutTargetSpacing	0 = Specify distance between pattern instance centers

 See Also

[SolidWorks.Interop.swconst Namespace](#)

swPatternLayoutType_e (Type)

SOLIDWORKS API Enumerations

swPatternLayoutType_e Enumeration

[See Also](#)

[Send comments on this topic.](#)

 

SolidWorks.Interop.swconst Namespace : swPatternLayoutType_e Enumeration

Pattern layout types.

 Syntax

Visual Basic (Declaration)

Public Enum swPatternLayoutType_e
Inherits System.Enum

Visual Basic (Usage)

Dim instance As [swPatternLayoutType_e](#)

C#

public enum swPatternLayoutType_e : System.Enum

C++/CLI

public enum class swPatternLayoutType_e : public System.Enum

 Members

Member	Description
swPatternLayoutCircular	0
swPatternLayoutPerforation	3
swPatternLayoutPolygon	2
swPatternLayoutSquare	1

 See Also

[SolidWorks.Interop.swconst Namespace](#)

swPatternReferenceTypes_e (Type)

SOLIDWORKS API Enumerations

swPatternReferenceTypes_e Enumeration

See Also

 

SolidWorks.Interop.swconst Namespace : swPatternReferenceTypes_e Enumeration

Local linear pattern axis types.

[Send comments on this topic.](#)

Syntax

Visual Basic (Declaration)

```
Public Enum swPatternReferenceTypes_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swPatternReferenceTypes\_e
```

C#

```
public enum swPatternReferenceTypes_e : System.Enum
```

C++/CLI

```
public enum class swPatternReferenceTypes_e : public System.Enum
```

Members

Member	Description
swPatternReferenceTypeAxis	0
swPatternReferenceTypeEdge	1
swPatternReferenceTypeFace	3
swPatternReferenceTypeRefDim	2

See Also

[SolidWorks.Interop.swconst Namespace](#)

swPerformanceFeedback_e (Type)

SOLIDWORKS API Enumerations

swPerformanceFeedback_e Enumeration

[See Also](#)

[Send comments on this topic.](#)

 

[SolidWorks.Interop.swconst Namespace](#) : swPerformanceFeedback_e Enumeration

Performance feedback options.

Syntax

Visual Basic (Declaration)

```
Public Enum swPerformanceFeedback_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swPerformanceFeedback\_e
```

C#

```
public enum swPerformanceFeedback_e : System.Enum
```

C++/CLI

```
public enum class swPerformanceFeedback_e : public System.Enum
```

Members

Member	Description
swPerformanceFeedback_No	0
swPerformanceFeedback_RemindLater	2
swPerformanceFeedback_RemindNow	3
swPerformanceFeedback_Yes	1

See Also

[SolidWorks.Interop.swconst Namespace](#)

swPersistReferencedObjectStates_e (Type)

SOLIDWORKS API Enumerations

swPersistReferencedObjectStates_e Enumeration

See Also

[SolidWorks.Interop.swconst Namespace](#) : swPersistReferencedObjectStates_e Enumeration

Object codes for objects' persistent reference IDs. [Bitmask](#).

Syntax

Visual Basic (Declaration)

```
Public Enum swPersistReferencedObjectStates_e
    Inherits System.Enum
```

Visual Basic (Usage)

Copy Code

```
Dim instance As swPersistReferencedObjectStates\_e
```

C#

```
public enum swPersistReferencedObjectStates_e : System.Enum
```

C++/CLI

```
public enum class swPersistReferencedObjectStates_e : public System.Enum
```

Members

Member	Description
swPersistReferencedObject_Deleted	4 or 0x4
swPersistReferencedObject_Invalid	1 or 0x1
swPersistReferencedObject_Ok	0 or 0x0
swPersistReferencedObject_Suppressed	2 or 0x2

See Also

[SolidWorks.Interop.swconst Namespace](#)

swPipingPenetrationStatus_e (Type)

SOLIDWORKS API Enumerations

swPipingPenetrationStatus_e Enumeration

See Also

 

[SolidWorks.Interop.swconst Namespace](#) : swPipingPenetrationStatus_e Enumeration

Piping penetration status.

[Send comments on this topic.](#)

 Syntax

Visual Basic (Declaration)

Public Enum swPipingPenetrationStatus_e
Inherits System.Enum

Visual Basic (Usage)

Dim instance As [swPipingPenetrationStatus_e](#)

C#

public enum swPipingPenetrationStatus_e : System.Enum

C++/CLI

public enum class swPipingPenetrationStatus_e : public System.Enum

 Members

Member	Description
swPenetrationFailed	1 = Unspecified error
swPenetrationFailedAlreadyPenetrating	8 = Pipe is already penetrating
swPenetrationFailedBadFitting	7 = Pipe cannot be found or fitting to pierce cannot be found
swPenetrationFailedBadSelection	6 = Sketch point cannot be used for penetration
swPenetrationFailedDllNotLoaded	3 = Routing not installed
swPenetrationFailedMultiBody	9 = Pipe cannot penetrate multibody
swPenetrationFailedNoSelection	4 = No sketch point selected
swPenetrationFailedNotRouting	5 = Sketch is not a routing sketch
swPenetrationFailedPipeTooWide	2 = Pipe too wide to cut other pipe
swPenetrationSucceeded	0 = Okay

 See Also

[SolidWorks.Interop.swconst Namespace](#)

swPLYQuality_e (Type)

SOLIDWORKS API Enumerations

swPLYQuality_e Enumeration

See Also

 

[SolidWorks.Interop.swconst Namespace](#) : swPLYQuality_e Enumeration

[Send comments on this topic.](#)

Polygon file format resolutions.

 Syntax

Visual Basic (Declaration)

Public Enum swPLYQuality_e
Inherits System.Enum

Visual Basic (Usage)

Dim instance As [swPLYQuality_e](#)



C#

public enum swPLYQuality_e : System.Enum

C++/CLI

public enum class swPLYQuality_e : public System.Enum

 Members

Member	Description
swPLYQuality_Coarse	1
swPLYQuality_Custom	3
swPLYQuality_Fine	2

 See Also

[SolidWorks.Interop.swconst Namespace](#)

swPMContainer_e (Type)

SOLIDWORKS API Enumerations

swPMContainer_e Enumeration

See Also

Send comments on this topic.

 

SolidWorks.Interop.swconst Namespace : swPMContainer_e Enumeration

Docking states of PropertyManager page.

 Syntax

Visual Basic (Declaration)

Public Enum swPMContainer_e
Inherits System.Enum

Visual Basic (Usage)  Copy Code

Dim instance As [swPMContainer_e](#)

C#

public enum swPMContainer_e : System.Enum

C++/CLI

public enum class swPMContainer_e : public System.Enum

 Members

Member	Description
swPMFloating	3 = True floating state where PropertyManager page lives inside new docking pane; a single floating window owns all PropertyManager pages of all open documents
swPMinTabsWithFM	0 = Old-style PropertyManager page embedded in tabs at top
swPMPinnedAboveFM	1 = Quasi floating state where PropertyManager page automatically displays, resizes itself in the lower-left corner of model frame window, and covers the FeatureManager design tree; one window for each open document
swPMPinnedLowerRight	4 = Quasi floating state where PropertyManager page automatically displays, resizes itself in the lower-right corner of the model frame window, covers the graphic area, and has full height; one window for each open document
swPMPinnedNextToFM	2 = Quasi floating state where PropertyManager page automatically displays, resizes itself to the right of the FeatureManager design tree, covers the graphics area, and has full height; one window for each open document

 See Also

[SolidWorks.Interop.swconst Namespace](#)

swPMIDatumAnchorStyle_e (Type)

SOLIDWORKS API Enumerations

swPMIDatumAnchorStyle_e Enumeration

See Also

▼

SolidWorks.Interop.swconst Namespace : swPMIDatumAnchorStyle_e Enumeration

PMI datum anchor styles.

[Send comments on this topic.](#)

Syntax

Visual Basic (Declaration)

```
Public Enum swPMIDatumAnchorStyle_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swPMIDatumAnchorStyle\_e
```

C#

```
public enum swPMIDatumAnchorStyle_e : System.Enum
```

C++/CLI

```
public enum class swPMIDatumAnchorStyle_e : public System.Enum
```

Members

Member	Description
swPMIDatumAnchorStyle_EmptyTriangle	2
swPMIDatumAnchorStyle_EmptyTriangleWithShoulder	3
swPMIDatumAnchorStyle_FilledTriangle	0
swPMIDatumAnchorStyle_FilledTriangleWithShoulder	1

See Also

[SolidWorks.Interop.swconst Namespace](#)

swPMIDatumShape_e (Type)

SOLIDWORKS API Enumerations

swPMIDatumShape_e Enumeration

See Also

[Send comments on this topic.](#)

 

[SolidWorks.Interop.swconst Namespace](#) : swPMIDatumShape_e Enumeration

PMI datum shapes.

 Syntax

Visual Basic (Declaration)

Public Enum swPMIDatumShape_e
Inherits System.Enum

Visual Basic (Usage)  Copy Code

Dim instance As [swPMIDatumShape_e](#)

C#

public enum swPMIDatumShape_e : System.Enum

C++/CLI

public enum class swPMIDatumShape_e : public System.Enum

 Members

Member	Description
swPMIDatumShape_Round	1
swPMIDatumShape_Square	0

 See Also

[SolidWorks.Interop.swconst Namespace](#)

swPMIDatumTargetAreaStyle_e (Type)

SOLIDWORKS API Enumerations

swPMIDatumTargetAreaStyle_e Enumeration

[See Also](#)

[Send comments on this topic.](#)

 

[SolidWorks.Interop.swconst Namespace](#) : swPMIDatumTargetAreaStyle_e Enumeration

PMI datum target area styles.

 Syntax

Visual Basic (Declaration)

Public Enum swPMIDatumTargetAreaStyle_e
Inherits System.Enum

Visual Basic (Usage)

Dim instance As [swPMIDatumTargetAreaStyle_e](#)

 [Copy Code](#)

C#

public enum swPMIDatumTargetAreaStyle_e : System.Enum

C++/CLI

public enum class swPMIDatumTargetAreaStyle_e : public System.Enum

 Members

Member	Description
swPMIDatumTargetAreaStyle_Circular	3
swPMIDatumTargetAreaStyle_None	0
swPMIDatumTargetAreaStyle_Rectangular	4
swPMIDatumTargetAreaStyle_Unknown	1
swPMIDatumTargetAreaStyle_X	2

 See Also

[SolidWorks.Interop.swconst Namespace](#)

[SolidWorks.Interop.swconst Namespace](#)

swPMIDatumTargetMovableStyle_e (Type)

SOLIDWORKS API Enumerations

swPMIDatumTargetMovableStyle_e Enumeration

[See Also](#)

[Send comments on this topic.](#)

[SolidWorks.Interop.swconst Namespace](#) : swPMIDatumTargetMovableStyle_e Enumeration

PMI datum target movable styles.

Syntax

Visual Basic (Declaration)

```
Public Enum swPMIDatumTargetMovableStyle_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swPMIDatumTargetMovableStyle\_e
```

C#

```
public enum swPMIDatumTargetMovableStyle_e : System.Enum
```

C++/CLI

```
public enum class swPMIDatumTargetMovableStyle_e : public System.Enum
```

Members

Member	Description
swPMIDatumTargetMovableStyle_Horizontal	2 = Movable symbol moves along the horizontal axis
swPMIDatumTargetMovableStyle_None	0
swPMIDatumTargetMovableStyle_Rotational	3 = Movable symbol adjusts to always point at the target area
swPMIDatumTargetMovableStyle_Unknown	1

See Also

[SolidWorks.Interop.swconst Namespace](#)

swPMIDatumTargetSymbolStyle_e (Type)

SOLIDWORKS API Enumerations

swPMIDatumTargetSymbolStyle_e Enumeration

See Also

[Send comments on this topic.](#)

 

[SolidWorks.Interop.swconst Namespace](#) : swPMIDatumTargetSymbolStyle_e Enumeration

PMI datum target symbol styles.

 Syntax

Visual Basic (Declaration)

Public Enum swPMIDatumTargetSymbolStyle_e
Inherits System.Enum

Visual Basic (Usage)

Dim instance As [swPMIDatumTargetSymbolStyle_e](#)

 [Copy Code](#)

C#

public enum swPMIDatumTargetSymbolStyle_e : System.Enum

C++/CLI

public enum class swPMIDatumTargetSymbolStyle_e : public System.Enum

 Members

Member	Description
swPMIDatumTargetSymbolStyle_AreaOutside	3 = Area size appears outside of the target symbol
swPMIDatumTargetSymbolStyle_None	0
swPMIDatumTargetSymbolStyle_Symbol	2 = Area size appears in the top half of the target symbol
swPMIDatumTargetSymbolStyle_Unknown	1

 See Also

[SolidWorks.Interop.swconst Namespace](#)

swPMIDatumType_e (Type)

SOLIDWORKS API Enumerations

swPMIDatumType_e Enumeration

See Also

[Send comments on this topic.](#)

 

[SolidWorks.Interop.swconst Namespace](#) : swPMIDatumType_e Enumeration

Datum types for PMI annotations.

 Syntax

Visual Basic (Declaration)

Public Enum swPMIDatumType_e
Inherits System.Enum

Visual Basic (Usage)

Dim instance As [swPMIDatumType_e](#)



C#

public enum swPMIDatumType_e : System.Enum

C++/CLI

public enum class swPMIDatumType_e : public System.Enum

 Members

Member	Description
swPMIDatumType_DatumFeature	0
swPMIDatumType_DatumTarget	1

 See Also

[SolidWorks.Interop.swconst Namespace](#)

swPMILeaderLocation_e (Type)

SOLIDWORKS API Enumerations

swPMILeaderLocation_e Enumeration

See Also

[Send comments on this topic.](#)

 

[SolidWorks.Interop.swconst Namespace](#) : swPMILeaderLocation_e Enumeration

PMI leader locations.

 Syntax

Visual Basic (Declaration)

Public Enum swPMILeaderLocation_e
Inherits System.Enum

Visual Basic (Usage)

Dim instance As [swPMILeaderLocation_e](#)



C#

public enum swPMILeaderLocation_e : System.Enum

C++/CLI

public enum class swPMILeaderLocation_e : public System.Enum

 Members

Member	Description
swPMILeaderLocation_Left	1
swPMILeaderLocation_Nearest	3
swPMILeaderLocation_None	0
swPMILeaderLocation_Right	2

 See Also

[SolidWorks.Interop.swconst Namespace](#)

swPMILeaderModifier_e (Type)

SOLIDWORKS API Enumerations

swPMILeaderModifier_e Enumeration

See Also

[Send comments on this topic.](#)

 

[SolidWorks.Interop.swconst Namespace](#) : swPMILeaderModifier_e Enumeration

PMI leader modifiers.

 Syntax

Visual Basic (Declaration)

Public Enum swPMILeaderModifier_e
Inherits System.Enum

Visual Basic (Usage)  Copy Code

Dim instance As [swPMILeaderModifier_e](#)

C#

public enum swPMILeaderModifier_e : System.Enum

C++/CLI

public enum class swPMILeaderModifier_e : public System.Enum

 Members

Member	Description
swPMILeaderModifier_AllAround	1
swPMILeaderModifier_AllAroundThisSide	2
swPMILeaderModifier_AllOver	3
swPMILeaderModifier_AllOverThisSide	4
swPMILeaderModifier_None	0

 See Also

[SolidWorks.Interop.swconst Namespace](#)

swPMILeaderStyle_e (Type)

SOLIDWORKS API Enumerations

swPMILeaderStyle_e Enumeration

See Also

[Send comments on this topic.](#)

 

[SolidWorks.Interop.swconst Namespace](#) : swPMILeaderStyle_e Enumeration

PMI leader styles.

 Syntax

Visual Basic (Declaration)

Public Enum swPMILeaderStyle_e
Inherits System.Enum

Visual Basic (Usage)  Copy Code

Dim instance As [swPMILeaderStyle_e](#)

C#

public enum swPMILeaderStyle_e : System.Enum

C++/CLI

public enum class swPMILeaderStyle_e : public System.Enum

 Members

Member	Description
swPMILeaderStyle_Bent	2
swPMILeaderStyle_Inside	5
swPMILeaderStyle_None	0
swPMILeaderStyle_Outside	4
swPMILeaderStyle_Perpendicular	3
swPMILeaderStyle_Smart	6
swPMILeaderStyle_Straight	1

 See Also

[SolidWorks.Interop.swconst Namespace](#)

swPMILeaderType_e (Type)

SOLIDWORKS API Enumerations

swPMILeaderType_e Enumeration

See Also

[Send comments on this topic.](#)

 

[SolidWorks.Interop.swconst Namespace](#) : swPMILeaderType_e Enumeration

PMI leader types.

Syntax

Visual Basic (Declaration)

```
Public Enum swPMILeaderType_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swPMILeaderType\_e
```

C#

```
public enum swPMILeaderType_e : System.Enum
```

C++/CLI

```
public enum class swPMILeaderType_e : public System.Enum
```

Members

Member	Description
swPMILeaderType_Leader	1
swPMILeaderType_MultiJog	2
swPMILeaderType_NoLeader	0

See Also

[SolidWorks.Interop.swconst Namespace](#)

swPMITolPerUnitAreaType_e (Type)

SOLIDWORKS API Enumerations

swPMITolPerUnitAreaType_e Enumeration

[Send comments on this topic.](#)

[See Also](#)

▼

[SolidWorks.Interop.swconst Namespace](#) : swPMITolPerUnitAreaType_e Enumeration

PMI tolerance per unit area types.

Syntax

Visual Basic (Declaration)

```
Public Enum swPMITolPerUnitAreaType_e
    Inherits System.Enum
```

Visual Basic (Usage) Copy Code

```
Dim instance As swPMITolPerUnitAreaType\_e
```

C#

```
public enum swPMITolPerUnitAreaType_e : System.Enum
```

C++/CLI

```
public enum class swPMITolPerUnitAreaType_e : public System.Enum
```

Members

Member	Description
swPMITolPerUnitType_Circular	2
swPMITolPerUnitType_None	0
swPMITolPerUnitType_Rectangular	3
swPMITolPerUnitType_Square	4
swPMITolPerUnitType_Unknown	1

See Also

[SolidWorks.Interop.swconst Namespace](#)

swPMIType_e (Type)

 

[SolidWorks.Interop.swconst Namespace](#) : swPMIType_e Enumeration

Types of PMI annotations.

 Syntax

Visual Basic (Declaration)

```
Public Enum swPMIType_e
    Inherits System.Enum
```

Visual Basic (Usage)  Copy Code

```
Dim instance As swPMIType\_e
```

C#

```
public enum swPMIType_e : System.Enum
```

C++/CLI

```
public enum class swPMIType_e : public System.Enum
```

 Members

Member	Description
swPMIType_Datum	2
swPMIType_Dimension	1
swPMIType_GTol	3
swPMIType_None	0
swPMIType_Unknown	4

 See Also

[SolidWorks.Interop.swconst Namespace](#)

swPMIUnit_e (Type)

SOLIDWORKS API Enumerations

swPMIUnit_e Enumeration

See Also

[Send comments on this topic.](#)

 [SolidWorks.Interop.swconst Namespace](#) : swPMIUnit_e Enumeration

Units of measure for Product and Manufacturing Information purposes.

 Syntax

Visual Basic (Declaration)

```
Public Enum swPMIUnit_e
    Inherits System.Enum
```

Visual Basic (Usage)  Copy Code

```
Dim instance As swPMIUnit\_e
```

C#

```
public enum swPMIUnit_e : System.Enum
```

C++/CLI

```
public enum class swPMIUnit_e : public System.Enum
```

 Members

Member	Description
swPMIUnit_ANGSTROM	1
swPMIUnit_CM	2
swPMIUnit_DEGREE	12
swPMIUnit_FEET	3
swPMIUnit_FEETINCHES	4
swPMIUnit_INCHES	5
swPMIUnit_METER	6
swPMIUnit_MICRON	7
swPMIUnit_MIL	8
swPMIUnit_MM	9
swPMIUnit_NANOMETER	10
swPMIUnit_None	0
swPMIUnit_RADIAN	13
swPMIUnit_UIN	11 = Microinch

 See Also

[SolidWorks.Interop.swconst Namespace](#)