

SOLIDWORKS Enumerations (swconst) — Reference (12/17)

swRenamedDocumentFinalAction_e swSetHelixRegionParameterStatus_e

SOLIDWORKS API Documentation (converted from CHM)

swRenamedDocumentFinalAction_e (Type)

SOLIDWORKS API Enumerations

swRenamedDocumentFinalAction_e Enumeration

[See Also](#)

 [SolidWorks.Interop.swconst Namespace](#) : swRenamedDocumentFinalAction_e Enumeration

Final actions for renaming document references.

[Send comments on this topic.](#)

Syntax

Visual Basic (Declaration)

```
Public Enum swRenamedDocumentFinalAction_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swRenamedDocumentFinalAction\_e
```

C#

```
public enum swRenamedDocumentFinalAction_e : System.Enum
```

C++/CLI

```
public enum class swRenamedDocumentFinalAction_e : public System.Enum
```

Members

Member	Description
swRenamedDocumentFinalAction_Cancel	2
swRenamedDocumentFinalAction_Default	0
swRenamedDocumentFinalAction_Ok	1

See Also

[SolidWorks.Interop.swconst Namespace](#)

swRenameDocumentError_e (Type)

SOLIDWORKS API Enumerations

swRenameDocumentError_e Enumeration

See Also

[Send comments on this topic.](#)



[SolidWorks.Interop.swconst Namespace](#) : swRenameDocumentError_e Enumeration

Rename components errors.



Syntax

Visual Basic (Declaration)

```
Public Enum swRenameDocumentError_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swRenameDocumentError\_e
```

C#

```
public enum swRenameDocumentError_e : System.Enum
```

C++/CLI

```
public enum class swRenameDocumentError_e : public System.Enum
```



Members

Member	Description
swRenameDocumentError_ComponentNotResolved	5 = You must resolve the component before attempting to rename it
swRenameDocumentError_DocumentNameInUse	12 = You cannot rename the component to the specified name because a document with that name is open
swRenameDocumentError_DocumentNotSaved	15 = You cannot rename the document, and the document was not saved
swRenameDocumentError_FileAlreadyExists	8 = You cannot rename the component to the specified name because a file with that name exists on disk
swRenameDocumentError_InvalidCharactersInName	9 = You specified an invalid component name; the name is either too long or contains invalid characters
swRenameDocumentError_InvalidForDrawings	3 = You cannot rename drawing documents
swRenameDocumentError_InvalidSelection	2 = You must select a valid component; your selection is invalid for renaming
swRenameDocumentError_InvalidVirtualComponent	10 = You cannot rename virtual components
swRenameDocumentError_LightWeightComponent	6 = You cannot rename the child component whose parent component is lightweight
swRenameDocumentError_NameTooLong	11 = You cannot rename the component to the specified name because that name is too long
swRenameDocumentError_NoModelLoaded	4 = You cannot rename the component because a model is not loaded in memory
swRenameDocumentError_None	0 = Success
swRenameDocumentError_NotAllowedWithPDM	17 = You cannot rename the component because the SOLIDWORKS Professional PDM add-in is not loaded
swRenameDocumentError_PatternedComponent	19 = You cannot rename patterned components
swRenameDocumentError_PendingNameAlreadyInUse	13 = You cannot rename the component to the specified name because a document with the same name has been temporarily renamed but not yet saved
swRenameDocumentError_ReadOnlyDocument	14 = You cannot rename read-only documents or documents referenced by read-only documents
swRenameDocumentError_RoutingComponent	7 = You cannot rename routing components
swRenameDocumentError_ToolboxComponent	18 = You cannot rename Toolbox components
swRenameDocumentError_UnspecifiedInternalError	1 = You cannot rename the component due to an internal error
swRenameDocumentError_VirtualComponent	16 = You cannot rename virtual components



See Also

[SolidWorks.Interop.swconst Namespace](#)

swRenameOptions_e (Type)

SOLIDWORKS API Enumerations

swRenameOptions_e Enumeration

[Send comments on this topic.](#)

[See Also](#)

 

[SolidWorks.Interop.swconst Namespace](#) : swRenameOptions_e Enumeration

Options for renaming a pasted drawing sheet.

Syntax

Visual Basic (Declaration)

```
Public Enum swRenameOptions_e
    Inherits System.Enum
```

Visual Basic (Usage)



Copy Code

```
Dim instance As swRenameOptions\_e
```

C#

```
public enum swRenameOptions_e : System.Enum
```

C++/CLI

```
public enum class swRenameOptions_e : public System.Enum
```

Members

Member	Description
swRenameOption_No	2
swRenameOption_Yes	1

See Also

[SolidWorks.Interop.swconst Namespace](#)

swRendererType_e (Type)

SOLIDWORKS API Enumerations

swRendererType_e Enumeration

See Also

[Send comments on this topic.](#)

 

[SolidWorks.Interop.swconst Namespace](#) : swRendererType_e Enumeration

Renderer type.

 Syntax

Visual Basic (Declaration)

```
Public Enum swRendererType_e
    Inherits System.Enum
```

Visual Basic (Usage)  Copy Code

```
Dim instance As swRendererType\_e
```

C#

```
public enum swRendererType_e : System.Enum
```

C++/CLI

```
public enum class swRendererType_e : public System.Enum
```

 Members

Member	Description
swRendererType_Photoworks_Buffer	1 = Valid in documents created in SOLIDWORKS 2010 and earlier
swRendererType_Solidworks_Screen	0

 See Also

[SolidWorks.Interop.swconst Namespace](#)

swRenderMaterialBumpMap_e (Type)

SOLIDWORKS API Enumerations

swRenderMaterialBumpMap_e Enumeration

See Also

[Send comments on this topic.](#)

 SolidWorks.Interop.swconst Namespace : swRenderMaterialBumpMap_e Enumeration

Render material (appearance) surface finish.

Syntax

Visual Basic (Declaration)

```
Public Enum swRenderMaterialBumpMap_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swRenderMaterialBumpMap\_e
```

C#

```
public enum swRenderMaterialBumpMap_e : System.Enum
```

C++/CLI

```
public enum class swRenderMaterialBumpMap_e : public System.Enum
```

Members

Member	Description
swRenderMaterialBumpMapCasting	2
swRenderMaterialBumpMapChips	7
swRenderMaterialBumpMapCircular	8
swRenderMaterialBumpMapDimpled	5
swRenderMaterialBumpMapFrom_File	1
swRenderMaterialBumpMapKnurled	6
swRenderMaterialBumpMapNone	0
swRenderMaterialBumpMapRough	3
swRenderMaterialBumpMapRough_Smooth	9
swRenderMaterialBumpMapTread_Plate	4

See Also

[SolidWorks.Interop.swconst Namespace](#)

swRenderMaterialColorForms_e (Type)

SOLIDWORKS API Enumerations

swRenderMaterialColorForms_e Enumeration

[See Also](#)

 

[SolidWorks.Interop.swconst Namespace](#) : swRenderMaterialColorForms_e Enumeration

Number of render material (appearance) colors.

[Send comments on this topic.](#)

Syntax

Visual Basic (Declaration)

```
Public Enum swRenderMaterialColorForms_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swRenderMaterialColorForms\_e
```

C#

```
public enum swRenderMaterialColorForms_e : System.Enum
```

C++/CLI

```
public enum class swRenderMaterialColorForms_e : public System.Enum
```

Members

Member	Description
swRenderMaterialColorFormsColor_ Undefined	-1
swRenderMaterialColorFormsImage	0
swRenderMaterialColorFormsOne_Color	
swRenderMaterialColorFormsThree_Colors	
swRenderMaterialColorFormsTwo_Colors	

See Also

[SolidWorks.Interop.swconst Namespace](#)

swRenderMaterialIlluminationTypes_e (Type)

SOLIDWORKS API Enumerations

swRenderMaterialIlluminationTypes_e Enumeration

[Send comments on this topic.](#)

[See Also](#)

 

[SolidWorks.Interop.swconst Namespace](#) : swRenderMaterialIlluminationTypes_e Enumeration

Render material (appearance) illumination types.

Syntax

Visual Basic (Declaration)

```
Public Enum swRenderMaterialIlluminationTypes_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swRenderMaterialIlluminationTypes\_e
```

C#

```
public enum swRenderMaterialIlluminationTypes_e : System.Enum
```

C++/CLI

```
public enum class swRenderMaterialIlluminationTypes_e : public System.Enum
```

Members

Member	Description
swRenderMaterialIlluminationType_matte	
swRenderMaterialIlluminationType_use_underlying_material	0
swRenderMaterialIlluminationTypes_anisotropic	
swRenderMaterialIlluminationTypes_car_paint	
swRenderMaterialIlluminationTypes_circular_anisotropic	
swRenderMaterialIlluminationTypes_conductor	
swRenderMaterialIlluminationTypes_constant	
swRenderMaterialIlluminationTypes_cut_hole_with_decals	
swRenderMaterialIlluminationTypes_dielectric	
swRenderMaterialIlluminationTypes_dielectric_advanced	
swRenderMaterialIlluminationTypes_glass	
swRenderMaterialIlluminationTypes_illumination_undefined	-1
swRenderMaterialIlluminationTypes_metal	
swRenderMaterialIlluminationTypes_mirror	
swRenderMaterialIlluminationTypes_multilayer_paint	
swRenderMaterialIlluminationTypes_plastic	
swRenderMaterialIlluminationTypes_satin_finish	
swRenderMaterialIlluminationTypes_studio_plastic	
swRenderMaterialIlluminationTypes_translucent	
swRenderMaterialIlluminationTypes_translucent_plastic	
swRenderMaterialIlluminationTypes_woven_anisotropic	

See Also

[SolidWorks.Interop.swconst Namespace](#)

swReorderComponentsWhere_e (Type)

SOLIDWORKS API Enumerations

swReorderComponentsWhere_e Enumeration

See Also

[Send comments on this topic.](#)

[SolidWorks.Interop.swconst Namespace](#) : swReorderComponentsWhere_e Enumeration

Where to move the components.

Syntax

Visual Basic (Declaration)

```
Public Enum swReorderComponentsWhere_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swReorderComponentsWhere\_e
```

C#

```
public enum swReorderComponentsWhere_e : System.Enum
```

C++/CLI

```
public enum class swReorderComponentsWhere_e : public System.Enum
```

Members

Member	Description
swReorderComponents_After	1 = Move the source components to just after the target
swReorderComponents_Before	2 = Move the source components to just before the target
swReorderComponents_FirstInFolder	4 = Move the source components into the target folder, as the first items in the folder
swReorderComponents_LastInFolder	3 = Move the source components into the target folder, as the last items in the folder

See Also

[SolidWorks.Interop.swconst Namespace](#)

swRepaintTypes_e (Type)

SOLIDWORKS API Enumerations

swRepaintTypes_e Enumeration

[Send comments on this topic.](#)

[See Also](#)

 

SolidWorks.Interop.swconst Namespace : swRepaintTypes_e Enumeration

Repaint notification types.

Syntax

Visual Basic (Declaration)

```
Public Enum swRepaintTypes_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swRepaintTypes\_e
```

C#

```
public enum swRepaintTypes_e : System.Enum
```

C++/CLI

```
public enum class swRepaintTypes_e : public System.Enum
```

Members

Member	Description
swDamageRepairUpdate	7
swExplodedUpdate	4
swInsertSketchUpdate	5
swLightUpdate	1
swMaterialUpdate	2
swScrollViewUpdate	10
swSectionedExitUpdate	9
swSectionedUpdate	3
swSelectionUpdate	8
swStandardUpdate	0
swViewDisplayUpdate	6

See Also

[SolidWorks.Interop.swconst Namespace](#)

swRepairSketchOption_e (Type)

SOLIDWORKS API Enumerations

swRepairSketchOption_e Enumeration

[Send comments on this topic.](#)

[See Also](#)

 

[SolidWorks.Interop.swconst Namespace](#) : swRepairSketchOption_e Enumeration

Options for repairing sketches. [Bitmask](#).

Syntax

Visual Basic (Declaration)

```
Public Enum swRepairSketchOption_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swRepairSketchOption\_e
```

C#

```
public enum swRepairSketchOption_e : System.Enum
```

C++/CLI

```
public enum class swRepairSketchOption_e : public System.Enum
```

Members

Member	Description
swRepairSketchBreakIntersection	8 = Break intersection
swRepairSketchCleanup	0 = Clean up
swRepairSketchCloseGaps	4 = Close gaps
swRepairSketchMergeSegment	2 = Merge segment
swRepairSketchZeroSegment	1 = Zero segment

See Also

[SolidWorks.Interop.swconst Namespace](#)

swReplaceComponentError_e (Type)

SOLIDWORKS API Enumerations

swReplaceComponentError_e Enumeration

[See Also](#)

 [SolidWorks.Interop.swconst Namespace](#) : swReplaceComponentError_e Enumeration

Replace component errors.

[Send comments on this topic.](#)

 Syntax

Visual Basic (Declaration)

```
Public Enum swReplaceComponentError_e
    Inherits System.Enum
```

Visual Basic (Usage) 

```
Dim instance As swReplaceComponentError\_e
```

C#

```
public enum swReplaceComponentError_e : System.Enum
```

C++/CLI

```
public enum class swReplaceComponentError_e : public System.Enum
```

 Members

Member	Description
swReplaceComponent_EmptyName	2
swReplaceComponent_InvalidFileName	3
swReplaceComponent_NotTopLevelComponent	6
swReplaceComponent_SameFile	5
swReplaceComponent_SameModelDifferentPath	4
swReplaceComponent_Success	1
swReplaceComponent_Undefined	0
swReplaceComponent_UnknownError	7

 See Also

[SolidWorks.Interop.swconst Namespace](#)

swReplaceComponentsConfiguration_e (Type)

SOLIDWORKS API Enumerations

swReplaceComponentsConfiguration_e Enumeration

[Send comments on this topic.](#)

[See Also](#)

 [SolidWorks.Interop.swconst Namespace](#) : swReplaceComponentsConfiguration_e Enumeration

Replace components configuration options.

Syntax

Visual Basic (Declaration)

```
Public Enum swReplaceComponentsConfiguration_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swReplaceComponentsConfiguration\_e
```

C#

```
public enum swReplaceComponentsConfiguration_e : System.Enum
```

C++/CLI

```
public enum class swReplaceComponentsConfiguration_e : public System.Enum
```

Members

Member	Description
swReplaceComponentsConfiguration_ManuallySelect	1 = Use the specified configuration
swReplaceComponentsConfiguration_MatchName	0 = Let SOLIDWORKS attempt to match the configuration of the old components with a configuration in the replacement component

See Also

[SolidWorks.Interop.swconst Namespace](#)

swReverseEndPointTangentResult_e (Type)

SOLIDWORKS API Enumerations

swReverseEndPointTangentResult_e Enumeration

See Also

 

[SolidWorks.Interop.swconst Namespace](#) : swReverseEndPointTangentResult_e Enumeration
Result codes for [ISketchManager::ReverseEndPointTangent](#).

[Send comments on this topic.](#)

Syntax

Visual Basic (Declaration)

```
Public Enum swReverseEndPointTangentResult_e  
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swReverseEndPointTangentResult\_e
```

C#

```
public enum swReverseEndPointTangentResult_e : System.Enum
```

C++/CLI

```
public enum class swReverseEndPointTangentResult_e : public System.Enum
```

Members

Member	Description
swReverseEndPointTangent_ConstraintConflict	2 = Reversing the end point tangent direction creates a conflict with existing constraints
swReverseEndPointTangent_InvalidSelection	1 = Select a valid end point tangent direction entity
swReverseEndPointTangent_Success	0

See Also

[SolidWorks.Interop.swconst Namespace](#)

swRevisionCloudShape_e (Type)

SOLIDWORKS API Enumerations

swRevisionCloudShape_e Enumeration

[Send comments on this topic.](#)

[See Also](#)

 

[SolidWorks.Interop.swconst Namespace](#) : swRevisionCloudShape_e Enumeration

Revision cloud shapes.

 Syntax

Visual Basic (Declaration)

Public Enum swRevisionCloudShape_e
Inherits System.Enum

Visual Basic (Usage)  Copy Code

Dim instance As [swRevisionCloudShape_e](#)

C#

public enum swRevisionCloudShape_e : System.Enum

C++/CLI

public enum class swRevisionCloudShape_e : public System.Enum

 Members

Member	Description
swRevisionCloudShape_Ellipse	1
swRevisionCloudShape_Freehand	0
swRevisionCloudShape_Polygon	3
swRevisionCloudShape_Rectangle	2

 See Also

[SolidWorks.Interop.swconst Namespace](#)

swRevisionTableMultipleSheetStyle_e (Type)

SOLIDWORKS API Enumerations

swRevisionTableMultipleSheetStyle_e Enumeration

[See Also](#)

 

[SolidWorks.Interop.swconst Namespace](#) : swRevisionTableMultipleSheetStyle_e Enumeration

Revision table multiple sheet styles.

[Send comments on this topic.](#)

Syntax

Visual Basic (Declaration)

```
Public Enum swRevisionTableMultipleSheetStyle_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swRevisionTableMultipleSheetStyle\_e
```

C#

```
public enum swRevisionTableMultipleSheetStyle_e : System.Enum
```

C++/CLI

```
public enum class swRevisionTableMultipleSheetStyle_e : public System.Enum
```

Members

Member	Description
swRevisionTable_Independent	3
swRevisionTable_LinkedToSheet1	2
swRevisionTable_SeeSheet1	1

See Also

[SolidWorks.Interop.swconst Namespace](#)

swRevisionTableSymbolShape_e (Type)

SOLIDWORKS API Enumerations

swRevisionTableSymbolShape_e Enumeration

[See Also](#)

 

[SolidWorks.Interop.swconst Namespace](#) : swRevisionTableSymbolShape_e Enumeration

Revision table symbol shapes.

[Send comments on this topic.](#)

Syntax

Visual Basic (Declaration)

```
Public Enum swRevisionTableSymbolShape_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swRevisionTableSymbolShape\_e
```

C#

```
public enum swRevisionTableSymbolShape_e : System.Enum
```

C++/CLI

```
public enum class swRevisionTableSymbolShape_e : public System.Enum
```

Members

Member	Description
swRevisionTable_CircleSymbol	1
swRevisionTable_HexagonSymbol	4
swRevisionTable_SquareSymbol	2
swRevisionTable_TriangleSymbol	3

See Also

[SolidWorks.Interop.swconst Namespace](#)

swRevisionTableTagStyle_e (Type)

SOLIDWORKS API Enumerations

swRevisionTableTagStyle_e Enumeration

[See Also](#)

 

[SolidWorks.Interop.swconst Namespace](#) : swRevisionTableTagStyle_e Enumeration

Revision table symbol shapes.

[Send comments on this topic.](#)

 Syntax

Visual Basic (Declaration)

```
Public Enum swRevisionTableTagStyle_e
    Inherits System.Enum
```

Visual Basic (Usage)  Copy Code

```
Dim instance As swRevisionTableTagStyle\_e
```

C#

```
public enum swRevisionTableTagStyle_e : System.Enum
```

C++/CLI

```
public enum class swRevisionTableTagStyle_e : public System.Enum
```

 Members

Member	Description
swRevisionTable_AlphabeticTags	1
swRevisionTable_NumericTags	2

 See Also

[SolidWorks.Interop.swconst Namespace](#)

swRevolveOptions_e (Type)

SOLIDWORKS API Enumerations

swRevolveOptions_e Enumeration

[See Also](#)

 

[SolidWorks.Interop.swconst Namespace](#) : swRevolveOptions_e Enumeration

Revolve feature options. [Bitmask](#).

[Send comments on this topic.](#)

 Syntax

Visual Basic (Declaration)

```
Public Enum swRevolveOptions_e
    Inherits System.Enum
```

Visual Basic (Usage)  Copy Code

```
Dim instance As swRevolveOptions\_e
```

C#

```
public enum swRevolveOptions_e : System.Enum
```

C++/CLI

```
public enum class swRevolveOptions_e : public System.Enum
```

 Members

Member	Description
swAutoCloseSketch	1 or 0x1
swRevolveOptionsNone	0 or 0x0

 See Also

[SolidWorks.Interop.swconst Namespace](#)

swRevolveType_e (Type)

SOLIDWORKS API Enumerations

swRevolveType_e Enumeration

See Also

 SolidWorks.Interop.swconst Namespace : swRevolveType_e Enumeration

Revolve feature types.

[Send comments on this topic.](#)

Syntax

Visual Basic (Declaration)

```
Public Enum swRevolveType_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swRevolveType\_e
```

C#

```
public enum swRevolveType_e : System.Enum
```

C++/CLI

```
public enum class swRevolveType_e : public System.Enum
```

Members

Member	Description
swRevolveTypeMidPlane	1 = Mid-plane revolution
swRevolveTypeMidPlane360Degrees	4 = Create revolve: mid-plane revolution with a 360-degree angle - Or - Edit revolve: mid-plane revolution with a 360-degree angle; if you use IRevolveFeatureData2::SetRevolutionAngle , then the 360-degree angle is overwritten
swRevolveTypeOneDirection	0 = One-direction revolution
swRevolveTypeOneDirection360Degrees	3 = Create revolve: one direction revolution with a 360-degree angle - Or - Edit revolve: one direction revolution with a 360-degree angle; if you use IRevolveFeatureData2::SetRevolutionAngle , then the 360-degree angle is overwritten
swRevolveTypeTwoDirection	2 = Two direction revolution
swRevolveTypeTwoDirection360Degrees	5 = Create and edit revolves: two direction revolution

Remarks

To...	Use...
Create revolve	IFeatureManager::FeatureRevolve IFeatureManager::FeatureRevolveCut IFeatureManager::FeatureRevolveThin IFeatureManager::FeatureRevolveThinCut
Edit revolve	IRevolveFeatureData2::Type

See Also

[SolidWorks.Interop.swconst Namespace](#)

swRibExtrusionDirection_e (Type)

SOLIDWORKS API Enumerations

swRibExtrusionDirection_e Enumeration

[Send comments on this topic.](#)

[See Also](#)

 [SolidWorks.Interop.swconst Namespace](#) : swRibExtrusionDirection_e Enumeration

Rib extrusion directions.

Syntax

Visual Basic (Declaration)

```
Public Enum swRibExtrusionDirection_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swRibExtrusionDirection\_e
```

C#

```
public enum swRibExtrusionDirection_e : System.Enum
```

C++/CLI

```
public enum class swRibExtrusionDirection_e : public System.Enum
```

Members

Member	Description
swRibNormalToSketch	0
swRibParallelToSketch	1

See Also

[SolidWorks.Interop.swconst Namespace](#)

swRibType_e (Type)

SOLIDWORKS API Enumerations

swRibType_e Enumeration

See Also

[Send comments on this topic.](#)

 

[SolidWorks.Interop.swconst Namespace](#) : swRibType_e Enumeration

Rib types.

 Syntax

Visual Basic (Declaration)

```
Public Enum swRibType_e
    Inherits System.Enum
```

Visual Basic (Usage)  Copy Code

```
Dim instance As swRibType\_e
```

C#

```
public enum swRibType_e : System.Enum
```

C++/CLI

```
public enum class swRibType_e : public System.Enum
```

 Members

Member	Description
swRibLinear	0
swRibNatural	1

 See Also

[SolidWorks.Interop.swconst Namespace](#)

swRotationAxisIndex_e (Type)

SOLIDWORKS API Enumerations

swRotationAxisIndex_e Enumeration

[Send comments on this topic.](#)

[See Also](#)

 [SolidWorks.Interop.swconst Namespace](#) : swRotationAxisIndex_e Enumeration

Rotation ring manipulator options when creating or editing an explode step.

Syntax

Visual Basic (Declaration)

```
Public Enum swRotationAxisIndex_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swRotationAxisIndex\_e
```

C#

```
public enum swRotationAxisIndex_e : System.Enum
```

C++/CLI

```
public enum class swRotationAxisIndex_e : public System.Enum
```

Members

Member	Description
swRotationAxisIndex_Unknown	-1 = Use in IExplodeStep.SetRotationAxis to continue using the current enumerator value
swRotationAxisIndex_XYRing	0
swRotationAxisIndex_YZRing	1
swRotationAxisIndex_ZXRing	2

See Also

[SolidWorks.Interop.swconst Namespace](#)

swRoutingComponentGroupingOption_e (Type)

SOLIDWORKS API Enumerations

swRoutingComponentGroupingOption_e Enumeration

[Send comments on this topic.](#)

[See Also](#)

 [SolidWorks.Interop.swconst Namespace](#) : swRoutingComponentGroupingOption_e Enumeration

Routing components grouping options. [Bitmask](#).

 Syntax

Visual Basic (Declaration)

Public Enum swRoutingComponentGroupingOption_e
Inherits System.Enum

Visual Basic (Usage)

 Copy Code

Dim instance As [swRoutingComponentGroupingOption_e](#)

C#

public enum swRoutingComponentGroupingOption_e : System.Enum

C++/CLI

public enum class swRoutingComponentGroupingOption_e : public System.Enum

 Members

Member	Description
swDisplayUnitsInBOM	4 or 0x4
swGroupPipesOrTubesWithTheSameDiameterAndSchedule	2 or 0x2
swRoutingGroupSpoolComponents	8 or 0x8
swShowOnlyRoutingComponentsInBOM	1 or 0x1

 See Also

[SolidWorks.Interop.swconst Namespace](#)

swRoutingFlattenConnectorOptions_e (Type)

SOLIDWORKS API Enumerations

swRoutingFlattenConnectorOptions_e Enumeration

[Send comments on this topic.](#)

[See Also](#)

 [SolidWorks.Interop.swconst Namespace](#) : swRoutingFlattenConnectorOptions_e Enumeration

Flattened route connector display options.

Syntax

Visual Basic (Declaration)

```
Public Enum swRoutingFlattenConnectorOptions_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swRoutingFlattenConnectorOptions\_e
```

C#

```
public enum swRoutingFlattenConnectorOptions_e : System.Enum
```

C++/CLI

```
public enum class swRoutingFlattenConnectorOptions_e : public System.Enum
```

Members

Member	Description
swDisplay3DConnectors_e	1
SwUseDrawingConnectorBlocks_e	2

See Also

[SolidWorks.Interop.swconst Namespace](#)

swRoutingFlattenSegmentOrientation_e (Type)

SOLIDWORKS API Enumerations

swRoutingFlattenSegmentOrientation_e Enumeration

See Also

 

SolidWorks.Interop.swconst Namespace : swRoutingFlattenSegmentOrientation_e Enumeration

Flattened route segment orientation.

[Send comments on this topic.](#)

Syntax

Visual Basic (Declaration)

```
Public Enum swRoutingFlattenSegmentOrientation_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swRoutingFlattenSegmentOrientation\_e
```

C#

```
public enum swRoutingFlattenSegmentOrientation_e : System.Enum
```

C++/CLI

```
public enum class swRoutingFlattenSegmentOrientation_e : public System.Enum
```

Members

Member	Description
SwHorizontal_e	2
swVertical_e	1

See Also

[SolidWorks.Interop.swconst Namespace](#)

swRoutingFlattenTypes_e (Type)

SOLIDWORKS API Enumerations

swRoutingFlattenTypes_e Enumeration

See Also

[Send comments on this topic.](#)

                            

[SolidWorks.Interop.swconst Namespace](#) : swRoutingFlattenTypes_e Enumeration

Route flattening types.

Syntax

Visual Basic (Declaration)

```
Public Enum swRoutingFlattenTypes_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swRoutingFlattenTypes\_e
```

C#

```
public enum swRoutingFlattenTypes_e : System.Enum
```

C++/CLI

```
public enum class swRoutingFlattenTypes_e : public System.Enum
```

Members

Member	Description
swAnnotation_e	1
SwManufacture_e	2

See Also

[SolidWorks.Interop.swconst Namespace](#)

swRoutingSearchType_e (Type)

SOLIDWORKS API Enumerations

swRoutingSearchType_e Enumeration

[Send comments on this topic.](#)

[See Also](#)

 

[SolidWorks.Interop.swconst Namespace](#) : swRoutingSearchType_e Enumeration

Routing search types.

Syntax

Visual Basic (Declaration)

```
Public Enum swRoutingSearchType_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swRoutingSearchType\_e
```

C#

```
public enum swRoutingSearchType_e : System.Enum
```

C++/CLI

```
public enum class swRoutingSearchType_e : public System.Enum
```

Members

Member	Description
swRoutingCableSearch	3
swRoutingComponentSearch	1
swRoutingConnectorSearch	0
swRoutingFittingSearch	7
swRoutingPipeSearch	5
swRoutingPipeSegmentSearch	6
swRoutingSignalSearch	4
swRoutingWireSearch	2

See Also

[SolidWorks.Interop.swconst Namespace](#)

swRuledSurfaceType_e (Type)

SOLIDWORKS API Enumerations

swRuledSurfaceType_e Enumeration

[See Also](#)

 

[SolidWorks.Interop.swconst Namespace](#) : swRuledSurfaceType_e Enumeration

Ruled surface types.

[Send comments on this topic.](#)

Syntax

Visual Basic (Declaration)

```
Public Enum swRuledSurfaceType_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swRuledSurfaceType\_e
```

C#

```
public enum swRuledSurfaceType_e : System.Enum
```

C++/CLI

```
public enum class swRuledSurfaceType_e : public System.Enum
```

Members

Member	Description
swRuledSurfaceType_NormalToSurface	2
swRuledSurfaceType_PerpendicularToVector	4
swRuledSurfaceType_Sweep	5
swRuledSurfaceType_TangentToSurface	1
swRuledSurfaceType_TaperedToVector	3

See Also

[SolidWorks.Interop.swconst Namespace](#)

swRunMacroError_e (Type)

SOLIDWORKS API Enumerations

swRunMacroError_e Enumeration

See Also

 [SolidWorks.Interop.swconst Namespace](#) : swRunMacroError_e Enumeration

VBA macro error codes.

[Send comments on this topic.](#)

Syntax

Visual Basic (Declaration)

```
Public Enum swRunMacroError_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swRunMacroError\_e
```

C#

```
public enum swRunMacroError_e : System.Enum
```

C++/CLI

```
public enum class swRunMacroError_e : public System.Enum
```

Members

Member	Description
swRunMacroError_BadParmCount	9
swRunMacroError_BadVarType	10
swRunMacroError_Busy	17
swRunMacroError_CallFailed	20
swRunMacroError_CallRejected	19
swRunMacroError_CantSave	27
swRunMacroError_ConnectionTerminated	18
swRunMacroError_DiskError	26
swRunMacroError_Exception	12
swRunMacroError_InvalidArg	1
swRunMacroError_InvalidIndex	22
swRunMacroError_InvalidProcname	6
swRunMacroError_InvalidPropertyType	7
swRunMacroError_MacrosAreDisabled	2
swRunMacroError_NoPermission	23
swRunMacroError_NotInDesignMode	3
swRunMacroError_OnlyCodeModules	4
swRunMacroError_OpenFileFailed	28
swRunMacroError_OutOfMemory	5
swRunMacroError_Overflow	13
swRunMacroError_ParmNotOptional	15
swRunMacroError_Reverted	24
swRunMacroError_SuborfuncExpected	8
swRunMacroError_TooManyOpenFiles	25
swRunMacroError_TypeMismatch	14
swRunMacroError_UnknownLcid	16
swRunMacroError_UserInterrupt	11
swRunMacroError_Zombie	21

Remarks

VSTA error codes not yet implementd.

See Also

[SolidWorks.Interop.swconst Namespace](#)

swRunMacroOption_e (Type)

SOLIDWORKS API Enumerations

swRunMacroOption_e Enumeration

[Send comments on this topic.](#)

[See Also](#)

 

[SolidWorks.Interop.swconst Namespace](#) : swRunMacroOption_e Enumeration

VBA macro options.

 Syntax

Visual Basic (Declaration)

```
Public Enum swRunMacroOption_e
    Inherits System.Enum
```

Visual Basic (Usage)  Copy Code

```
Dim instance As swRunMacroOption\_e
```

C#

```
public enum swRunMacroOption_e : System.Enum
```

C++/CLI

```
public enum class swRunMacroOption_e : public System.Enum
```

 Members

Member	Description
swRunMacroDefault	0
swRunMacroUnloadAfterRun	1

 Remarks

VSTA macro options not yet implementd.

 See Also

[SolidWorks.Interop.swconst Namespace](#)

swSafeArrayType_e (Type)

SOLIDWORKS API Enumerations

swSafeArrayType_e Enumeration

[Send comments on this topic.](#)

[See Also](#)

 

[SolidWorks.Interop.swconst Namespace](#) : swSafeArrayType_e Enumeration

SafeArray types.

Syntax

Visual Basic (Declaration)

```
Public Enum swSafeArrayType_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swSafeArrayType\_e
```

C#

```
public enum swSafeArrayType_e : System.Enum
```

C++/CLI

```
public enum class swSafeArrayType_e : public System.Enum
```

Members

Member	Description
swBooleanArray	11
swBstrArray	8
swByteArray	16
swDispatchArray	9
swDoubleArray	5
swLongArray	3
swLongLongArray	20
swUnknownArray	13
swUnsignedByteArray	17
swUnsignedLongLongArray	21
swWordArray	2

See Also

[SolidWorks.Interop.swconst Namespace](#)

swSameAs_Status_e (Type)

SOLIDWORKS API Enumerations

swSameAs_Status_e Enumeration

[See Also](#)

 

[SolidWorks.Interop.swconst Namespace](#) : swSameAs_Status_e Enumeration

Comparison status.

[Send comments on this topic.](#)

Syntax

Visual Basic (Declaration)

```
Public Enum swSameAs_Status_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swSameAs\_Status\_e
```

C#

```
public enum swSameAs_Status_e : System.Enum
```

C++/CLI

```
public enum class swSameAs_Status_e : public System.Enum
```

Members

Member	Description
swSameAs_Different	FALSE
swSameAs_NotImplemented	-1
swSameAs_Same	TRUE

See Also

[SolidWorks.Interop.swconst Namespace](#)

swSaveAsmAsPartOptions_e (Type)

SOLIDWORKS API Enumerations

swSaveAsmAsPartOptions_e Enumeration

[See Also](#)

 

[SolidWorks.Interop.swconst Namespace](#) : swSaveAsmAsPartOptions_e Enumeration

Save assembly as parts options.

[Send comments on this topic.](#)

Syntax

Visual Basic (Declaration)

```
Public Enum swSaveAsmAsPartOptions_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swSaveAsmAsPartOptions\_e
```

C#

```
public enum swSaveAsmAsPartOptions_e : System.Enum
```

C++/CLI

```
public enum class swSaveAsmAsPartOptions_e : public System.Enum
```

Members

Member	Description
swSaveAsmAsPart_AllComponents	1
swSaveAsmAsPart_ExteriorComponents	2
swSaveAsmAsPart_ExteriorFaces	3
swSaveAsmAsPart_UserDefinedComponents	4

See Also

[SolidWorks.Interop.swconst Namespace](#)

swSaveAsOptions_e (Type)

SOLIDWORKS API Enumerations

swSaveAsOptions_e Enumeration

See Also

 

SolidWorks.Interop.swconst Namespace : swSaveAsOptions_e Enumeration

Save As options. [Bitmask](#).

[Send comments on this topic.](#)

 Syntax

Visual Basic (Declaration)

```
Public Enum swSaveAsOptions_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swSaveAsOptions\_e
```

C#

```
public enum swSaveAsOptions_e : System.Enum
```

C++/CLI

```
public enum class swSaveAsOptions_e : public System.Enum
```

 Members

Member	Description
swSaveAsOptions_AvoidRebuildOnSave	8 or 0x8
swSaveAsOptions_Copy	2 or 0x2; Save the document as a copy and continue editing
swSaveAsOptions_CopyAndOpen	512 or 0x200; Save the document as a copy and open it
swSaveAsOptions_DetachedDrawing	Obsolete.
swSaveAsOptions_ExportTo2DPdfFromInspection	2048 or 0x800; Export drawing sheets from Inspection to 2DPdf
swSaveAsOptions_IgnoreBiography	256 or 0x100; Prune a SOLIDWORKS file's revision history to just the current file name
swSaveAsOptions_IncludeVirtualSubAsmComps	1024 or 0x400; Save regular components in virtual subassemblies
swSaveAsOptions_OverrideSaveEModel	32 or 0x20; Saves eDrawings-related information into a section of the file being saved; specifying this setting overrides the Tools, Options, System Options, General, Save eDrawings data in SOLIDWORKS document setting; not a valid option for IPartDoc::SaveToFile2
swSaveAsOptions_PropagateVisualProperties	4096 or 0x1000; Export drawing sheets from Inspection to 2DPdf
swSaveAsOptions_SaveEModelData	Obsolete.
swSaveAsOptions_SaveReferenced	4 or 0x4; Supports parts, assemblies, and drawings; this setting indicates to save all components (sub-assemblies and parts) in both assemblies and drawings; if a part has an external reference, then this setting indicates to save the external reference
swSaveAsOptions_Silent	1 or 0x1
swSaveAsOptions_UpdateInactiveViews	16 or 0x10; Not a valid option for IPartDoc::SaveToFile2 ; this setting is only applicable for a drawing that has one or more sheets; this setting updates the views on inactive sheets

 Remarks

These options only apply to saving to native SOLIDWORKS file formats. For example, to export a SOLIDWORKS file to a VRML file format, use [ISldWorks::GetUserPreferenceToggle](#) and [ISldWorks::SetUserPreferenceToggle](#) with [swExportVrmlAllComponentsInSingleFile](#).

 See Also

[SolidWorks.Interop.swconst Namespace](#)

swSaveAsVersion_e (Type)

SOLIDWORKS API Enumerations

swSaveAsVersion_e Enumeration

[Send comments on this topic.](#)

[See Also](#)

 

[SolidWorks.Interop.swconst Namespace](#) : swSaveAsVersion_e Enumeration

Version of a particular format to save the document.

Syntax

Visual Basic (Declaration)

```
Public Enum swSaveAsVersion_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swSaveAsVersion\_e
```

C#

```
public enum swSaveAsVersion_e : System.Enum
```

C++/CLI

```
public enum class swSaveAsVersion_e : public System.Enum
```

Members

Member	Description
swSaveAsCurrentVersion	0 = This is the typical save behavior.
swSaveAsDetachedDrawing	4
swSaveAsFormatProE	2
swSaveAsStandardDrawing	3
swSaveAsSW98plus	Obsolete and no longer supported.

See Also

[SolidWorks.Interop.swconst Namespace](#)

swSaveItemsPathError_e (Type)

SOLIDWORKS API Enumerations

swSaveItemsPathError_e Enumeration

[Send comments on this topic.](#)

[See Also](#)



[SolidWorks.Interop.swconst Namespace](#) : swSaveItemsPathError_e Enumeration

Error return codes for [AdvancedSaveAsOptions.ModifyItemsNameAndPath](#).

Syntax

Visual Basic (Declaration)

```
Public Enum swSaveItemsPathError_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swSaveItemsPathError\_e
```

C#

```
public enum swSaveItemsPathError_e : System.Enum
```

C++/CLI

```
public enum class swSaveItemsPathError_e : public System.Enum
```

Members

Member	Description
swSaveItemsPathError_ArraySizeNotMatching	1 = Input arrays must be the same size
swSaveItemsPathError_InvalidPath	2 = Path provided does not exist or user does not have write access
swSaveItemsPathError_Succeeded	0
swSaveItemsPathError_WrongComponentName	3 = Name provided is not supported by SOLIDWORKS

See Also

[SolidWorks.Interop.swconst Namespace](#)

swSaveReminderIntervalMode_e (Type)

SOLIDWORKS API Enumerations

swSaveReminderIntervalMode_e Enumeration

See Also

[Send comments on this topic.](#)

 [SolidWorks.Interop.swconst Namespace](#) : swSaveReminderIntervalMode_e Enumeration

Intervals in which to remind user to save document.

Syntax

Visual Basic (Declaration)

```
Public Enum swSaveReminderIntervalMode_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swSaveReminderIntervalMode\_e
```

C#

```
public enum swSaveReminderIntervalMode_e : System.Enum
```

C++/CLI

```
public enum class swSaveReminderIntervalMode_e : public System.Enum
```

Members

Member	Description
swSaveReminderIntervalMode_Changes	1
swSaveReminderIntervalMode_Minutes	2

See Also

[SolidWorks.Interop.swconst Namespace](#)

swSaveRestoreSettingsResults_e (Type)

SOLIDWORKS API Enumerations

swSaveRestoreSettingsResults_e Enumeration

[See Also](#)

 

[SolidWorks.Interop.swconst Namespace](#) : swSaveRestoreSettingsResults_e Enumeration

Return values for saving and restoring SOLIDWORKS settings.

[Send comments on this topic.](#)

Syntax

Visual Basic (Declaration)

```
Public Enum swSaveRestoreSettingsResults_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swSaveRestoreSettingsResults\_e
```

C#

```
public enum swSaveRestoreSettingsResults_e : System.Enum
```

C++/CLI

```
public enum class swSaveRestoreSettingsResults_e : public System.Enum
```

Members

Member	Description
swSaveRestoreSettingsFailure_Generic	1
swSaveRestoreSettingsFailure_InvalidFilename	2
swSaveRestoreSettingsSuccess	0

See Also

[SolidWorks.Interop.swconst Namespace](#)

swSaveToVersion_e (Type)

SOLIDWORKS API Enumerations

swSaveToVersion_e Enumeration

[Send comments on this topic.](#)

[See Also](#)

 

[SolidWorks.Interop.swconst Namespace](#) : swSaveToVersion_e Enumeration

Previous version file formats available for save compatibility checks.

Syntax

Visual Basic (Declaration)

```
Public Enum swSaveToVersion_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swSaveToVersion\_e
```

C#

```
public enum swSaveToVersion_e : System.Enum
```

C++/CLI

```
public enum class swSaveToVersion_e : public System.Enum
```

Members

Member	Description
swSaveToVersion_Antepenultimate	2 = Save to the file format of the second most recent previous major release of SOLIDWORKS
swSaveToVersion_DoNotUpgrade	0 = Save without upgrading it to a more recent file format
swSaveToVersion_Penultimate	1 = Save to the file format of the most recent previous major release of SOLIDWORKS

See Also

[SolidWorks.Interop.swconst Namespace](#)

swSaveWithReferencesOptions_e (Type)

SOLIDWORKS API Enumerations

swSaveWithReferencesOptions_e Enumeration

See Also

 

SolidWorks.Interop.swconst Namespace : swSaveWithReferencesOptions_e Enumeration

Options for saving references while getting the [IAdvancedSaveAsOptions](#) object; used by the Options parameter of [IModelDocExtension::GetAdvancedSaveAsOptions](#). [Bitmask](#).

 Syntax

Visual Basic (Declaration)

```
Public Enum swSaveWithReferencesOptions_e
    Inherits System.Enum
```

Visual Basic (Usage)  Copy Code

```
Dim instance As swSaveWithReferencesOptions\_e
```

C#

```
public enum swSaveWithReferencesOptions_e : System.Enum
```

C++/CLI

```
public enum class swSaveWithReferencesOptions_e : public System.Enum
```

 Members

Member	Description
swSaveWithReferencesOptions_IncludeBrokenReferences	4 = Reference list contains both normal references and components with broken references
swSaveWithReferencesOptions_IncludeToolBoxParts	2 = Reference list contains both normal and ToolBox references
swSaveWithReferencesOptions_IncludeVirtualComponents	1 = Reference list contains both normal and virtual component references
swSaveWithReferencesOptions_None	0 = Reference list contains only normal references

 See Also

[SolidWorks.Interop.swconst Namespace](#)

swScaleType_e (Type)

SOLIDWORKS API Enumerations

swScaleType_e Enumeration

See Also

[Send comments on this topic.](#)

 SolidWorks.Interop.swconst Namespace : swScaleType_e Enumeration

Scale types.

 Syntax

Visual Basic (Declaration)

```
Public Enum swScaleType_e
    Inherits System.Enum
```

Visual Basic (Usage)  Copy Code

```
Dim instance As swScaleType\_e
```

C#

```
public enum swScaleType_e : System.Enum
```

C++/CLI

```
public enum class swScaleType_e : public System.Enum
```

 Members

Member	Description
swScaleAboutCentroid	0
swScaleAboutCoordinateSystem	2
swScaleAboutOrigin	1

 See Also

[SolidWorks.Interop.swconst Namespace](#)

swSceneBackgroundType_e (Type)

SOLIDWORKS API Enumerations

swSceneBackgroundType_e Enumeration

[Send comments on this topic.](#)

[See Also](#)

 

[SolidWorks.Interop.swconst Namespace](#) : swSceneBackgroundType_e Enumeration

Scene background options.

Syntax

Visual Basic (Declaration)

```
Public Enum swSceneBackgroundType_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swSceneBackgroundType\_e
```

C#

```
public enum swSceneBackgroundType_e : System.Enum
```

C++/CLI

```
public enum class swSceneBackgroundType_e : public System.Enum
```

Members

Member	Description
swBackgroundType_Color	5
swBackgroundType_Graduated	2
swBackgroundType_Image	3
swBackgroundType_None	0
swBackgroundType_Plain	1
swBackgroundType_UseEnvironment	4

See Also

[SolidWorks.Interop.swconst Namespace](#)

swSceneFloorAlign_e (Type)

SOLIDWORKS API Enumerations

swSceneFloorAlign_e Enumeration

[Send comments on this topic.](#)

[See Also](#)

 

[SolidWorks.Interop.swconst Namespace](#) : swSceneFloorAlign_e Enumeration

Scene floor alignment options.

Syntax

Visual Basic (Declaration)

```
Public Enum swSceneFloorAlign_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swSceneFloorAlign\_e
```

C#

```
public enum swSceneFloorAlign_e : System.Enum
```

C++/CLI

```
public enum class swSceneFloorAlign_e : public System.Enum
```

Members

Member	Description
swSceneFloorAlign_VIEW	0
swSceneFloorAlign_XY	1
swSceneFloorAlign_YZ	2
swSceneFloorAlign_ZX	3

See Also

[SolidWorks.Interop.swconst Namespace](#)

swScrewMateDistanceOptions_e (Type)

SOLIDWORKS API Enumerations

swScrewMateDistanceOptions_e Enumeration

[Send comments on this topic.](#)

[See Also](#)

 

[SolidWorks.Interop.swconst Namespace](#) : swScrewMateDistanceOptions_e Enumeration

Screw mate revolution options.

Syntax

Visual Basic (Declaration)

```
Public Enum swScrewMateDistanceOptions_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swScrewMateDistanceOptions\_e
```

C#

```
public enum swScrewMateDistanceOptions_e : System.Enum
```

C++/CLI

```
public enum class swScrewMateDistanceOptions_e : public System.Enum
```

Members

Member	Description
swDistancePerRevolution	1 = Specify the distance that one component travels for each revolution of the other component
swRevolutionsPerUnitLength	0 = Specify the number of revolutions of one component for each unit length that the other component travels

See Also

[SolidWorks.Interop.swconst Namespace](#)

swSearchFolderTypes_e (Type)

SOLIDWORKS API Enumerations

swSearchFolderTypes_e Enumeration

[Send comments on this topic.](#)

[See Also](#)

 

[SolidWorks.Interop.swconst Namespace](#) : swSearchFolderTypes_e Enumeration

Search folder types.

 Syntax

Visual Basic (Declaration)

```
Public Enum swSearchFolderTypes_e
    Inherits System.Enum
```

Visual Basic (Usage)  Copy Code

```
Dim instance As swSearchFolderTypes\_e
```

C#

```
public enum swSearchFolderTypes_e : System.Enum
```

C++/CLI

```
public enum class swSearchFolderTypes_e : public System.Enum
```

 Members

Member	Description
swDocumentType	0

 See Also

[SolidWorks.Interop.swconst Namespace](#)

swSearchIndexingPerformance_e (Type)

SOLIDWORKS API Enumerations

swSearchIndexingPerformance_e Enumeration

See Also

 

[SolidWorks.Interop.swconst Namespace](#) : swSearchIndexingPerformance_e Enumeration

Options when to perform search indexing.

[Send comments on this topic.](#)

Syntax

Visual Basic (Declaration)

```
Public Enum swSearchIndexingPerformance_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swSearchIndexingPerformance\_e
```

C#

```
public enum swSearchIndexingPerformance_e : System.Enum
```

C++/CLI

```
public enum class swSearchIndexingPerformance_e : public System.Enum
```

Members

Member	Description
swSearchIndexingPerformanceAlwaysIndex	1
swSearchIndexingPerformanceIndexOnlyWhenComputerIsIdle	0

See Also

[SolidWorks.Interop.swconst Namespace](#)

swSecondaryMemberBetweenPointsDistanceFromEndType_e (Type)

SOLIDWORKS API Enumerations

swSecondaryMemberBetweenPointsDistanceFromEndType_e Enumeration

[See Also](#)

 [SolidWorks.Interop.swconst Namespace](#) : swSecondaryMemberBetweenPointsDistanceFromEndType_e Enumeration

Distance types of structure system secondary members created between end points of primary members.

[Send comments on this topic.](#)

Syntax

Visual Basic (Declaration)

```
Public Enum swSecondaryMemberBetweenPointsDistanceFromEndType_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swSecondaryMemberBetweenPointsDistanceFromEndType\_e
```

C#

```
public enum swSecondaryMemberBetweenPointsDistanceFromEndType_e : System.Enum
```

C++/CLI

```
public enum class swSecondaryMemberBetweenPointsDistanceFromEndType_e : public System.Enum
```

Members

Member	Description
swSecondaryMemberBetweenPointsDistanceFromEndType_Distance	0
swSecondaryMemberBetweenPointsDistanceFromEndType_LengthRatio	1

See Also

[SolidWorks.Interop.swconst Namespace](#)

swSecondaryMemberUpToMembersDistanceFromEndType_e (Type)

SOLIDWORKS API Enumerations

swSecondaryMemberUpToMembersDistanceFromEndType_e Enumeration

See Also

 [SolidWorks.Interop.swconst Namespace](#) : swSecondaryMemberUpToMembersDistanceFromEndType_e Enumeration

Distance from end types for structure system secondary up-to members.

[Send comments on this topic.](#)

 Syntax

Visual Basic (Declaration)

```
Public Enum swSecondaryMemberUpToMembersDistanceFromEndType_e
    Inherits System.Enum
```

Visual Basic (Usage)

 Copy Code

```
Dim instance As swSecondaryMemberUpToMembersDistanceFromEndType\_e
```

C#

```
public enum swSecondaryMemberUpToMembersDistanceFromEndType_e : System.Enum
```

C++/CLI

```
public enum class swSecondaryMemberUpToMembersDistanceFromEndType_e : public System.Enum
```

 Members

Member	Description
swSecondaryMemberUpToMembersDistanceFromEndType_Distance	0
swSecondaryMemberUpToMembersDistanceFromEndType_LengthRatio	1

 See Also

[SolidWorks.Interop.swconst Namespace](#)

swSecondaryMemberUpToMembersMemberPointParameters_e (Type)

SOLIDWORKS API Enumerations

swSecondaryMemberUpToMembersMemberPointParameters_e Enumeration

See Also

 [SolidWorks.Interop.swconst Namespace](#) : swSecondaryMemberUpToMembersMemberPointParameters_e Enumeration

Point parameters for structure system secondary up-to members.

[Send comments on this topic.](#)

Syntax

Visual Basic (Declaration)

```
Public Enum swSecondaryMemberUpToMembersMemberPointParameters_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swSecondaryMemberUpToMembersMemberPointParameters\_e
```

C#

```
public enum swSecondaryMemberUpToMembersMemberPointParameters_e : System.Enum
```

C++/CLI

```
public enum class swSecondaryMemberUpToMembersMemberPointParameters_e : public System.Enum
```

Members

Member	Description
swSecondaryMemberUpToMembersMemberPointParameters_FromPoint	1
swSecondaryMemberUpToMembersMemberPointParameters_PointMemberPair	0

See Also

[SolidWorks.Interop.swconst Namespace](#)

swSeedAlignmentReferencePoint_e (Type)

SOLIDWORKS API Enumerations

swSeedAlignmentReferencePoint_e Enumeration

[Send comments on this topic.](#)

[See Also](#)

 

[SolidWorks.Interop.swconst Namespace](#) : swSeedAlignmentReferencePoint_e Enumeration

Types of reference points for aligning rotated pattern instances to the seed instance in linear component patterns.

Syntax

Visual Basic (Declaration)

```
Public Enum swSeedAlignmentReferencePoint_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swSeedAlignmentReferencePoint\_e
```

C#

```
public enum swSeedAlignmentReferencePoint_e : System.Enum
```

C++/CLI

```
public enum class swSeedAlignmentReferencePoint_e : public System.Enum
```

Members

Member	Description
swSeedAlignmentReferencePoint_BoundingBoxCenter	0
swSeedAlignmentReferencePoint_ComponentOrigin	1

See Also

[SolidWorks.Interop.swconst Namespace](#)

swSelectionMarkAction_e (Type)

SOLIDWORKS API Enumerations

swSelectionMarkAction_e Enumeration

[Send comments on this topic.](#)

[See Also](#)

 

[SolidWorks.Interop.swconst Namespace](#) : swSelectionMarkAction_e Enumeration

Selecton mark actions.

Syntax

Visual Basic (Declaration)

```
Public Enum swSelectionMarkAction_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swSelectionMarkAction\_e
```

C#

```
public enum swSelectionMarkAction_e : System.Enum
```

C++/CLI

```
public enum class swSelectionMarkAction_e : public System.Enum
```

Members

Member	Description
swSelectionMarkAppend	1
swSelectionMarkClear	3
swSelectionMarkRemove	2
swSelectionMarkSet	0

See Also

[SolidWorks.Interop.swconst Namespace](#)

swSelectionReferenceTypes_e (Type)

SOLIDWORKS API Enumerations

swSelectionReferenceTypes_e Enumeration

[Send comments on this topic.](#)

[See Also](#)

 

[SolidWorks.Interop.swconst Namespace](#) : swSelectionReferenceTypes_e Enumeration

Selecton reference types.

Syntax

Visual Basic (Declaration)

```
Public Enum swSelectionReferenceTypes_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swSelectionReferenceTypes\_e
```

C#

```
public enum swSelectionReferenceTypes_e : System.Enum
```

C++/CLI

```
public enum class swSelectionReferenceTypes_e : public System.Enum
```

Members

Member	Description
swReferenceTypeBody	7
swReferenceTypeEdge	2
swReferenceTypeFace	3
swReferenceTypeRefPlan	5
swReferenceTypeRefSurface	4
swReferenceTypeSketchPoint	6
swReferenceTypeVertex	1

See Also

[SolidWorks.Interop.swconst Namespace](#)

swSelectOption_e (Type)

SOLIDWORKS API Enumerations

swSelectOption_e Enumeration

[Send comments on this topic.](#)

[See Also](#)

 

[SolidWorks.Interop.swconst Namespace](#) : swSelectOption_e Enumeration

Selection options. [Bitmask](#).

Syntax

Visual Basic (Declaration)

```
Public Enum swSelectOption_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swSelectOption\_e
```

C#

```
public enum swSelectOption_e : System.Enum
```

C++/CLI

```
public enum class swSelectOption_e : public System.Enum
```

Members

Member	Description
swSelectOptionDefault	0 or 0x0
swSelectOptionExtensive	1 or 0x1

See Also

[SolidWorks.Interop.swconst Namespace](#)

swSelectType_e (Type)

SOLIDWORKS API Enumerations

swSelectType_e Enumeration

See Also

 SolidWorks.Interop.swconst Namespace : swSelectType_e Enumeration

Values for types of returned IDs.

[Send comments on this topic.](#)

Syntax

Visual Basic (Declaration)

Public Enum swSelectType_e
Inherits System.Enum

Visual Basic (Usage)

Dim instance As [swSelectType_e](#)

C#

public enum swSelectType_e : System.Enum

C++/CLI

public enum class swSelectType_e : public System.Enum

Members

Member	Description
swSelADVSTRUCTMEMBER	295; See Remarks
swSelANNOTATIONTABLES	98; See Remarks
swSelANNOTATIONVIEW	139; See Remarks
swSelARROWS	49; See Remarks
swSelATTRIBUTES	8; See Remarks
swSelBELTCHAINFEATS	149; See Remarks
swSelBLOCKDEF	99; See Remarks
swSelBLOCKINST	93; See Remarks
swSelBODYFEATURES	22; See Remarks
swSelBODYFOLDER	118; See Remarks
swSelBOMFEATURES	97; See Remarks
swSelBOMS	54; See Remarks
swSelBOMTEMPS	64; See Remarks
swSelBorder	254; See Remarks
swSelBREAKLINES	31; See Remarks
swSelBROWSERITEM	69; See Remarks
swSelCAMERAS	136; See Remarks
swSelCENTERLINES	103; See Remarks
swSelCENTERMARKS	28; See Remarks
swSelCENTERMARKSYMS	100; See Remarks
swSelCOMMENT	127; See Remarks
swSelCOMMENTSFOLDER	126; See Remarks
swSelCOMPONENTS	20; See Remarks
swSelCOMPPATTERN	37; See Remarks
swSelCOMPSDONTOVERRIDE	72; See Remarks
swSelCONFIGURATIONS	47; See Remarks
swSelCONNECTIONPOINTS	66; See Remarks
swSelCOORDSYS	61; See Remarks
swSelCOSMETICWELDS	220; See Remarks
swSelCTHEADS	39; See Remarks
swSelCUSTOMSYMBOLS	60; See Remarks
swSelDATUMAXES	5; See Remarks
swSelDATUMLINES	62; See Remarks
swSelDATUMPLANES	4; See Remarks
swSelDATUMPOINTS	6; See Remarks
swSelDATUMTAGS	36; See Remarks
swSelDCABINETS	42; See Remarks
swSelDETAILCIRCLES	17; See Remarks
swSelDIMENSIONS	14; See Remarks
swSelDISPLAYSTATE	148; See Remarks
swSelDOCSFOLDER	125; See Remarks
swSelDOWELSYMS	86; See Remarks
swSelDRAWINGVIEWS	12; See Remarks
swSelDTMTARGS	40; See Remarks
swSelEDGES	1; See Remarks
swSelEMBEDLINKDOC	123; See Remarks
swSelEMPTYSPACE	72; See Remarks
swSelEQNFOLDER	55; See Remarks
swSelEVERYTHING	-3; See Remarks
swSelEXCLUDEMANIPULATORS	111; See Remarks
swSelEXPLLINES	45; See Remarks
swSelEXPLSTEPS	44; See Remarks
swSelEXPLVIEWS	43; See Remarks
swSelEXTSKETCHPOINTS	25; See Remarks
swSelEXTSKETCHSEGS	24; See Remarks
swSelEXTSKETCHTEXT	88; See Remarks

swSelFABRICATEDROUTE	70; See Remarks
swSelFACES	2; See Remarks
swSelFACETS	268; See Remarks
swSelFAMILYTABLE	317; see Remarks
swSelFAMILYTABLEFEAT	316; see Remarks
swSelFRAMEPOINT	77; See Remarks
swSelFTRFOLDER	94; See Remarks
swSelGENERALTABLEFEAT	142; See Remarks
swSelGRAPHICSBODY	262; See Remarks
swSelGTOLS	13; See Remarks
swSelHELIX	26; See Remarks
swSelHOLESERIES	83; See Remarks
swSelHOLETABLEAXES	105; See Remarks
swSelHOLETABLEFEATS	104; See Remarks
swSelIMPORTFOLDER	57; See Remarks
swSelINCONTEXTFEAT	29; See Remarks
swSelINCONTEXTFEATS	32; See Remarks
swSelJOURNAL	124; See Remarks
swSelLEADERS	84; See Remarks
swSelLIGHTS	73; See Remarks
swSelLOCATIONS	-2; See Remarks
swSelMAGNETICLINES	225; See Remarks
swSelMANIPULATORS	79; See Remarks
swSelMATEGROUP	30; See Remarks
swSelMATEGROUPS	33; See Remarks
swSelMATES	21; See Remarks
swSelMATESUPPLEMENT	138; See Remarks
swSelMESHFACETEDGES	269; See Remarks
swSelMESHFACETVERTICES	270; See Remarks
swSelMESHSLIDBODIES	274; See Remarks
swSelMIDPOINTS	59; See Remarks
swSelNOTES	15; See Remarks
swSelNOTHING	0; See Remarks
swSelOBJGROUP	207; See Remarks
swSelOBJHANDLES	48; See Remarks
swSelOLEITEMS	7; See Remarks
swSelPICTUREBODIES	80; See Remarks
swSelPLANESECTIONS	219; see Remarks
swSelPOINTREFS	41; See Remarks
swSelPOSGROUP	68; See Remarks
swSelPUNCHTABLEFEATS	234; See Remarks
swSelREFCURVES	23; See Remarks
swSelREFEDGES	51; See Remarks
swSelREFERENCECURVES	26; See Remarks
swSelREFFACES	52; See Remarks
swSelREFSILHOUETTE	53; See Remarks
swSelREFSURFACES	27; See Remarks
swSelREVISIONCLOUDS	240; See Remarks
swSelREVISIONTABLE	113; See Remarks
swSelREVISIONTABLEFEAT	119; See Remarks
swSelROUTECURVES	63; See Remarks
swSelROUTEPOINTS	65; See Remarks
swSelROUTESWEEPS	67; See Remarks
swSelSECTIONLINES	16; See Remarks
swSelSECTIONTEXT	18; See Remarks
swSelSELECTIONSETFOLDER	258; See Remarks
swSelSELECTIONSETNODE	259; See Remarks
swSelSFSYMBOLS	35; See Remarks
swSelSHEETS	19; See Remarks
swSelSILHOUETTES	46; See Remarks
swSelSIMELEMENT	102; See Remarks
swSelSIMULATION	101; See Remarks
swSelSKETCHBITMAP	85; See Remarks
swSelSKETCHCONTOUR	96; See Remarks
swSelSKETCHES	9; See Remarks
swSelSKETCHHATCH	56; See Remarks
swSelSKETCHPOINTFEAT	71; See Remarks
swSelSKETCHPOINTS	11; See Remarks
swSelSKETCHREGION	95; See Remarks
swSelSKETCHSEGS	10; See Remarks
swSelSKETCHTEXT	34; See Remarks
swSelSOLIDBODIES	76; See Remarks
swSelSOLIDBODIESFIRST	81; See Remarks
swSelSUBATOMFOLDER	121; See Remarks
swSelSUBSKETCHDEF	154; See Remarks
swSelSUBSKETCHINST	114; See Remarks
swSelSUBWELDFOLDER	107; See Remarks
swSelSURFACEBODIES	75; See Remarks
swSelSURFBODIESFIRST	78; See Remarks
swSelSWIFTANNOTATIONS	130; See Remarks
swSelSWIFTFEATURES	132; See Remarks
swSelSWIFTSHEMA	159; See Remarks
swSelTITLEBLOCK	192; See Remarks
swSelTITLEBLOCKTABLEFEAT	206; See Remarks
swSelUNSUPPORTED	-1; See Remarks
swSelVERTICES	3; See Remarks
swSelVIEWERHYPERLINK	58; See Remarks
swSelWELDBEADS	122; See Remarks
swSelWELDMENT	106; See Remarks
swSelWELDMENTTABLEFEATS	116; See Remarks
swSelWELDS	38; See Remarks
swSelWIREBODIES	74; See Remarks
swSelZONES	50; See Remarks

Remarks				
		IModelDocExtension::SelectById2 string	ISelectionMgr::GetSelectedObject6 return value	IFeature::GetSpecificFeature2 return value
swSelectType_e				
swSelNOTHING				
swSelEDGES	"EDGE"	IEdge		

swSelectType_e	IModelDocExtension::SelectByID2 string	ISelectionMgr::GetSelectedObject6 return value	IFeature::GetSpecificFeature2 return value
swSelFACES	"FACE"	IFace2	
swSelVERTICES	"VERTEX"	IVertex	
swSelDATUMPLANES	"PLANE"	Feature2	IRefPlane
swSelDATUMAXES	"AXIS"	Feature2	IRefAxis
swSelDATUMPOINTS	"DATUMPOINT"	Feature1	No specific interface
swSelOLEITEMS	"OLEITEM"	Not Supported	
swSelATTRIBUTES	"ATTRIBUTE"	Feature1	IAttribute
swSelSKETCHES	"SKETCH"	Feature2	ISketch
swSelSKETCHSEGS	"SKETCHSEGMENT"	ISketchSegment	
swSelSKETCHPOINTS	"SKETCHPOINT"	ISketchPoint	
swSelDRAWINGVIEWS	"DRAWINGVIEW"	IView	
swSelGTOLS	"GTOL"	IGtol	
swSelDIMENSIONS	"DIMENSION"	IDisplayDimension	
swSelINOTES	"NOTE"	INote	
swSelSECTIONLINES	"SECTIONLINE"	Feature1	IDrSection
swSelDETAILCIRCLES	"DETAILCIRCLE"	Feature1	IDetailCircle
swSelSECTIONTEXT	"SECTIONTEXT"		
swSelSHEETS	"SHEET"	ISheet	
swSelCOMPONENTS	"COMPONENT"	IComponent2	
swSelMATES	"MATE"	Feature2	IMate
swSelBODYFEATURES	"BODYFEATURE" ³	Feature1	No specific interface
swSelREFCURVES	"REFCURVE"	Feature1	IReferenceCurve
swSelEXTSKETCHSEGS	"EXTSKETCHSEGMENT"	ISketchSegment	
swSelEXTSKETCHPOINTS	"EXTSKETCHPOINT"	ISketchPoint or origin point	
swSelHELIX	"HELIX"		
swSelREFERENCECURVES	"REFERENCECURVES"	Feature1	IReferenceCurve
swSelREFSURFACES	"REFSURFACE"		
swSelCENTERMARKS	"CENTERMARKS"	Not supported	
swSelINCONTEXTFEAT	"INCONTEXTFEAT"		
swSelMATEGROUP	"MATEGROUP"		
swSelBREAKLINES	"BREAKLINE"	IBreakLine	
swSelINCONTEXTFEATS	"INCONTEXTFEATS"		
swSelMATEGROUPS	"MATEGROUPS"		
swSelSKETCHTEXT	"SKETCHTEXT"		
swSelSFSYMBOLS	"SFSYMBOL"	ISFSymbol	
swSelDATUMTAGS	"DATUMTAG"	IDatumTag	
swSelCOMPPATTERN	"COMPPATTERN"		
swSelWELDS	"WELD"	IWeldSymbol	
swSelCTHREADS	"CTHREAD"	Feature or ICThread4	ICosmeticThreadFeatureData
swSelDTMTARGS	"DTMTARG"	IDatumTargetSym	
swSelPOINTREFS	"POINTREF"		
swSelDCABINETS	"DCABINET"		

	IModelDocExtension::SelectByID2 string	ISelectionMgr::GetSelectedObject6 return value	IFeature::GetSpecificFeature2 return value
swSelectType_e			
swSelEXPLVIEWS	"EXPLODEDVIEWS"		
swSelEXPLSTEPS	"EXPLODESTEPS"		
swSelEXPLLINES	"EXPLODELINES"		
swSelSILHOUETTES	"SILHOUETTE"	ISilhouetteEdge	
swSelCONFIGURATIONS	"CONFIGURATIONS"	Feature ¹	IConfiguration
swSelOBJHANDLES			
swSelARROWS	"VIEWARROW"	IProjectionArrow	
swSelZONES	"ZONES"		
swSelREFEDGES	"REFERENCE-EDGE"	IEdge	
swSelEFFACES			
swSelREFSILHOUETTE		Feature ¹	
swSelBOMS	"BOM"		
swSelEQNFOLDER	"EQNFOLDER"		
swSelSKETCHHATCH	"SKETCHHATCH"		
swSelIMPORTFOLDER	"IMPORTFOLDER"		
swSelVIEWERHYPERLINK	"HYPERLINK"		
swSelMIDPOINTS			
swSelCUSTOMSYMBOLS - Obsolete	"CUSTOMSYMBOL"	ICustomSymbol	
swSelCOORDSYS	"COORDSYS"		
swSelDATUMLINES	"REFLINE"		
swSelROUTECURVES			
swSelBOMTEMPS	"BOMTEMP"		
swSelROUTEPOINTS	"ROUTEPOINT"		
swSelCONNECTIONPOINTS	"CONNECTIONPOINT"		
swSelROUTESWEEPS			
swSelPOSGROUP	"POSGROUP"		
swSelBROWSERITEM	"BROWSERITEM"		
swSelFABRICATEDROUTE	"ROUTEFABRICATED"		
swSelSKETCHPOINTFEAT	"SKETCHPOINTFEAT"		
swSelCOMPSDONT OVERRIDE			
swSelLIGHTS	"LIGHTS"		
swSelWIREBODIES			
swSelSURFACEBODIES	"SURFACEBODY"		
swSelSOLIDBODIES	"SOLIDBODY"		
swSelFRAMEPOINT	"FRAMEPOINT"		
swSelSURFBODIESFIRST			
swSelMANIPULATORS	"MANIPULATOR"		
swSelPICTUREBODIES	"PICTURE BODY"		
swSelSOLIDBODIESFIRST			
swSelLEADERS	"LEADER"		
swSelSKETCHBITMAP	"SKETCHBITMAP"		
swSelDOWELSYMS	"DOWELSYM"	IDowelSymbol	
swSelEXTSKETCHTEXT	"EXTSKETCHTEXT"		
swSelBLOCKINST - Obsolete	"BLOCKINST"	IBlockInstance	
swSelFTRFOLDER	"FTRFOLDER"		
swSelSKETCHREGION	"SKETCHREGION"		
swSelSKETCHCONTOUR	"SKETCHCONTOUR"		
swSelBOMFEATURES	"BOMFEATURE"		

swSelType_e	IModelDocExtension::SelectByID2 string	ISelectionMgr::GetSelectedObject6 return value	IFeature::GetSpecificFeature2 return value
swSelANNOTATIONTABLES	"ANNOTATIONTABLES"	: ITableAnnotation : ITableBlockTableAnnotation	
swSelBLOCKDEF - Obsolete	"BLOCKDEF"		
swSelCENTERMARKSYMS	"CENTERMARKSYMS"		
swSelSIMULATION	"SIMULATION"		
swSelSIMELEMENT	"SIMULATION_ELEMENT"		
swSelCENTERLINES	"CENTERLINE"		
swSelHOLETABLEFEATS	"HOLETABLE"		IHoleTable
swSelHOLETABLEAXES	"HOLETABLEAXIS"		
swSelWELDMENT	"WELDMENT"		
swSelSUBWELDFOLDER	"SUBWELDMENT"		
swSelEXCLUDEMANIPULATORS			
swSelREVISIONTABLE	"REVISIONTABLE"		
swSelSUBSKETCHINST	"SUBSKETCHINST"	ISketchBlockInstance	
swSelWELDMENTTABLEFEATS	"WELDMENTTABLE"	IWeldmentCutListFeature	
swSelBODYFOLDER	"BODYFOLDER"		IBodyFolder
swSelREVISIONTABLEFEAT	"REVISIONTABLEFEAT"		
swSelSUBATOMFOLDER			
swSelWELDBEADS ³	"WELDBEADS"		
swSelEMBEDLINKDOC	"EMBEDLINKDOC"		
swSelJOURNAL	"JOURNAL"		
swSelDOCSFOLDER	"DOCSFOLDER"		
swSelCOMMENTSFOLDER	"COMMENTSFOLDER"		ICommentFolder
swSelCOMMENT	"COMMENT"	IComment	
swSelCAMERAS	"CAMERAS"	Feature ⁴	ICamera
swSelMATESUPPLEMENT	"MATESUPPLEMENT"	IMateLoadReference	
swSelANNOTATIONVIEW	"ANNVIEW"		
swSelGENERALTABLEFEAT	"GENERALTABLEFEAT"		
swSelSUBSKETCHDEF	"SUBSKETCHDEF"		ISketchBlockDefinition
swSelDISPLAYSTATE	"VISUALSTATES"		
swSelTITLEBLOCK	"TITLEBLOCK"	ITitleBlock	
swSelEVERYTHING	"EVERYTHING"		
swSelLOCATIONS	"LOCATIONS"		
swSelUNSUPPORTED	"UNSUPPORTED"		
swSelSWIFTANNOTATIONS	"SWIFTANN"	Feature ¹	IDimXpertAnnotation
swSelSWIFTFEATURES	"SWIFTFEATURE"	Feature ⁴	IDimXpertFeature
swSelSWIFTSHEMA	"SWIFTSHEMA"	IDimXpertManager	
swSelTITLEBLOCKTABLEFEAT	"TITLEBLOCKTABLEFEAT"	ITitleBlockTableFeature	
swSelOBJGROUP	"OBJGROUP"		
swSelCOSMETICWELDS	"COSMETICWELDS"		
swSelMAGNETICLINES	"MAGNETICLINE"		
swSelSELECTIONSETFOLDER	"SELECTIONSETFOLDER"		ISelectionSetFolder
swSelSELECTIONSETNODE	"SUBSELECTIONSETNODE"		
swSelPUNCHTABLEFEATS	"PUNCHTABLE"		IPunchTable
swSelHOLESERIES	"HOLESERIES"		
swSelGRAPHICSBODY	"MESH BODY FEATURE"		
swSelFACETS	"MESHFACETREF"		
swSelMESHFACETEDGES	"MESHFINREF"		
swSelMESHFACETVERTICES	"MESHVERTEXREF"		
swSelMESHOLIDBODIES	"MSOLIDBODY"		
swSelBELTCHAINFEATS	"SKETCHBELT"		
swSelADVSTRUCTMEMBER	"ADVSTRUCTMEMBER"		
swSelFAMILYTABLEFEAT	"FamilyTableFeat"		
swSelFAMILYTABLE	"FamilyTable"		

¹ Use Feature::GetSpecificFeature2 to get the interface shown in the fourth column.

² Use QueryInterface to get the interface shown in the fourth column.

³ Use swSelWELDBEADS to select caterpillar or end-treatment weld beads in drawings. To select fillet bead features, use "BODYFEATURE" with [IModelDocExtension::SelectByID2](#).

⁴ Feature or CThread depending on whether you select the cosmetic thread feature in a part or assembly or you select the cosmetic thread annotation in a drawing.

IDs returned for members in this enumeration:

swSelNOTHING = 0,

swSelEDGES = 1, // "EDGE"

swSelFACES = 2, // "FACE"

swSelVERTICES = 3, // "VERTEX"

```

swSelDATUMPLANES = 4, // "PLANE"
swSelDATUMAXES = 5, // "AXIS"

swSelDATUMPOINTS = 6, // "DATUMPOINT"
swSelOLEITEMS = 7, // "OLEITEM"
swSelATTRIBUTES = 8, // "ATTRIBUTE"
swSelSKETCHES = 9, // "SKETCH"
swSelSKETCHSEGS = 10, // "SKETCHSEGMENT"

swSelSKETCHPOINTS = 11, // "SKETCHPOINT"
swSelDRAWINGVIEWS = 12, // "DRAWINGVIEW"
swSelGTOLS = 13, // "GTOL"
swSelDIMENSIONS = 14, // "DIMENSION"
swSelNOTES = 15, // "NOTE"

swSelSECTIONLINES = 16, // "SECTIONLINE"
swSelDETAILCIRCLES = 17, // "DETAILCIRCLE"
swSelSECTIONTEXT = 18, // "SECTIONTEXT"
swSelSHEETS = 19, // "SHEET"
swSelCOMPONENTS = 20, // "COMPONENT"

swSelMATES = 21, // "MATE"
swSelBODYFEATURES = 22, // "BODYFEATURE"
swSelREFCURVES = 23, // "REFCURVE"
swSelEXTSKETCHSEGS = 24, // "EXTSKETCHSEGMENT"
swSelEXTSKETCHPOINTS = 25, // "EXTSKETCHPOINT"

swSelHELIX = 26, // "HELIX"
swSelREFERENCECURVES = 26, // "REFERENCECURVES"
swSelREFSURFACES = 27, // "REFSURFACE"
swSelCENTERMARKS = 28, // "CENTERMARKS"
swSelINCONTEXTFEAT = 29, // "INCONTEXTFEAT"
swSelMATEGROUP = 30, // "MATEGROUP"

swSelBREAKLINES = 31, // "BREAKLINE"
swSelINCONTEXTFEATS = 32, // "INCONTEXTFEATS"
swSelMATEGROUPS = 33, // "MATEGROUPS"
swSelSKETCHTEXT = 34, // "SKETCHTEXT"
swSelSFSYMBOLS = 35, // "SFSYMBOL"

swSelDATUMTAGS = 36, // "DATUMTAG"
swSelCOMPPATTERN = 37, // "COMPPATTERN"
swSelWELDS = 38, // "WELD"
swSelCTHREADS = 39, // "CTHREAD"
swSelDTMTARGS = 40, // "DTMTARG"

swSelPOINTREFS = 41, // "POINTREF"
swSelDCABINETS = 42, // "DCABINET"
swSelEXPLVIEWS = 43, // "EXPLODEDVIEWS"
swSelEXPLSTEPS = 44, // "EXPLODESTEPS"
swSelEXPLLINES = 45, // "EXPLODELINES"

swSelSILHOUETTES = 46, // "SILHOUETTE"
swSelCONFIGURATIONS = 47, // "CONFIGURATIONS"
swSelOBJHANDLES = 48,
swSelARROWS = 49, // "VIEWARROW"
swSelZONES = 50, // "ZONES"

swSelREFEDGES = 51, // "REFERENCE-EDGE"
swSelREFFACES = 52,
swSelREFSILHOUETTE = 53,
swSelBOMS = 54, // "BOM"
swSelEQNFOLDER = 55, // "EQNFOLDER"

swSelSKETCHHATCH = 56, // "SKETCHHATCH"
swSelIMPORTFOLDER = 57, // "IMPORTFOLDER"
swSelVIEWERHYPERLINK = 58, // "HYPERLINK"
swSelMIDPOINTS = 59,
swSelCUSTOMSYMBOLS = 60, // "CUSTOMSYMBOL"

swSelCOORDSYS = 61, // "COORDSYS"
swSelDATUMLINES = 62, // "REFLINE"
swSelROUTECURVES = 63,
swSelBOMTEMPS = 64, // "BOMTEMP"
swSelROUTEPOINTS = 65, // "ROUTEPOINT"

swSelCONNECTIONPOINTS = 66, // "CONNECTIONPOINT"
swSelROUTESWEEPS = 67,
swSelPOSGROUP = 68, // "POSGROUP"
swSelBROWSERITEM = 69, // "BROWSERITEM"
swSelFABRICATEDROUTE = 70, // "ROUTEFABRICATED"

swSelSKETCHPOINTFEAT = 71, // "SKETCHPOINTFEAT"
swSelEMPTYSPACE = 72, // (is this wrong?)
swSelCOMPSDONTOVERRIDE = 72,
swSelLIGHTS = 73, // "LIGHTS"

```

```

swSelWIREBODIES = 74,
swSelSURFACEBODIES = 75, // "SURFACEBODY"

swSelSOLIDBODIES = 76, // "SOLIDBODY"
swSelFRAMEPOINT = 77, // "FRAMEPOINT"
swSelSURFBODIESFIRST = 78,
swSelMANIPULATORS = 79, // "MANIPULATOR"
swSelPICTUREBODIES = 80, // "PICTURE BODY"

swSelSOLIDBODIESFIRST = 81,
swSelHOLESERIES = 83, // "HOLESERIES"
swSelLEADERS = 84, // "LEADER"
swSelSKETCHBITMAP = 85, // "SKETCHBITMAP"

swSelDOWELSYMS = 86, // "DOWELSYM"
swSelEXTSKETCHTEXT = 88, // "EXTSKETCHTEXT"

swSelBLOCKINST = 93, // "BLOCKINST"
swSelFTRFOLDER = 94, // "FTRFOLDER"
swSelSKETCHREGION = 95, // "SKETCHREGION"

swSelSKETCHCONTOUR = 96, // "SKETCHCONTOUR"
swSelBOMFEATURES = 97, // "BOMFEATURE"
swSelANNOTATIONTABLES = 98, // "ANNOTATIONTABLES"
swSelBLOCKDEF = 99, // "BLOCKDEF"
swSelCENTERMARKSYMS = 100, // "CENTERMARKSYMS"

swSelSIMULATION = 101, // "SIMULATION"
swSelSIMELEMENT = 102, // "SIMULATION_ELEMENT"
swSelCENTERLINES = 103, // "CENTERLINE"
swSelHOLETABLEFEATS = 104, // "HOLETABLE"
swSelHOLETABLEAXES = 105, // "HOLETABLEAXIS"

swSelWELDMENT = 106, // "WELDMENT"
swSelSUBWELDFOLDER = 107, // "SUBWELDMENT"

swSelEXCLUDEMANIPULATORS = 111,
swSelREVISIONTABLE = 113, // "REVISIONTABLE"
swSelSUBSKETCHINST = 114, // "SUBSKETCHINST"

swSelWELDMENTTABLEFEATS = 116, // "WELDMENTTABLE"
swSelBODYFOLDER = 118, // "BDYFOLDER"
swSelREVISIONTABLEFEAT = 119, // "REVISIONTABLEFEAT"

swSelSUBATOMFOLDER = 121,
swSelWELDBEADS = 122, // "WELDBEADS"
swSelEMBEDLINKDOC = 123, // "EMBEDLINKDOC"
swSelJOURNAL = 124, // "JOURNAL"
swSelDOCSFOLDER = 125, // "DOCSFOLDER"

swSelCOMMENTSFOLDER = 126, // "COMMENTSFOLDER"
swSelCOMMENT = 127, // "COMMENT"
swSelSWIFTANNOTATIONS = 130, // "SWIFTANN"

swSelSWIFTFEATURES = 132, // "SWIFTFEATURE"

swSelCAMERAS = 136, // "CAMERAS"
swSelMATESUPPLEMENT = 138, // "MATESUPPLEMENT"
swSelANNOTATIONVIEW = 139, // "ANNVIEW"

swSelGENERALTABLEFEAT = 142, // "GENERALTABLEFEAT"

swSelDISPLAYSTATE = 148, // "VISUALSTATE"
swSelBELTCHAINFEATS = 149, // "SKETCHBELT"

swSelSUBSKETCHDEF = 154, // "SUBSKETCHDEF"

swSelSWIFTSHEMA = 159, // "SWIFTSHEMA"

swSelTITLEBLOCK = 192, // "TITLEBLOCK"

swSelTITLEBLOCKTABLEFEAT = 206, // "TITLEBLOCKTABLEFEAT"

swSelOBJGROUP = 207, // "OBJGROUPS"

swSelPLANESECTIONS = 219, // "PLANESECTIONS"

swSelCOSMETICWELDS = 220, // "PLANESECTIONS"

SwSelMAGNETICLINES = 225, // "MagneticLine"
swSelPUNCHTABLEFEATS = 234, // "PUNCH TABLES"
swSelREVISIONCLOUDS = 240, // "REVISIONCLOUD"
swSelBorder = 254,

swSelSELECTIONSETFOLDER = 258,
swSelSELECTIONSETNODE = 259,

swSelGRAPHICSBODY = 262, // "MESH BODY FEATURE"
swSelFACETS = 268, // "MESHFACETREF"

```

```
swSelMESHFACETEDGES = 269, //"MESHFINREF"  
swSelMESHFACETVERTICES = 270, //"MESHVERTEXREF"  
  
swSelMESHSOLIDBODIES = 274, //"MSOLIDBODY"  
  
swSelADVSTRUCTMEMBER = 295, // "ADVSTRUCTMEMBER"  
  
swSelFAMILYTABLEFEAT = 316, //FamilyTableFeat  
swSelFAMILYTABLE = 317, //FamilyTable  
  
swSelEVERYTHING    = 4294967293,  
swSelLOCATIONS     = 4294967294,  
swSelUNSUPPORTED   = 4294967295
```

 See Also

[SolidWorks.Interop.swconst Namespace](#)

swSensorAlertType_e (Type)

SOLIDWORKS API Enumerations

swSensorAlertType_e Enumeration

[Send comments on this topic.](#)

[See Also](#)

 [SolidWorks.Interop.swconst Namespace](#) : swSensorAlertType_e Enumeration

Types of sensor alert.

Syntax

Visual Basic (Declaration)

```
Public Enum swSensorAlertType_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swSensorAlertType\_e
```

C#

```
public enum swSensorAlertType_e : System.Enum
```

C++/CLI

```
public enum class swSensorAlertType_e : public System.Enum
```

Members

Member	Description
swSensorAlert_Between	6
swSensorAlert_Exactly	2
swSensorAlert_False	9
swSensorAlert_GreaterThan	0
swSensorAlert_LessThan	1
swSensorAlert_NotBetween	7
swSensorAlert_NotExactly	5
swSensorAlert_NotGreaterThan	3
swSensorAlert_NotLessThan	4
swSensorAlert_True	8

See Also

[SolidWorks.Interop.swconst Namespace](#)

swSensorType_e (Type)

[SolidWorks.Interop.swconst Namespace](#) : swSensorType_e Enumeration

Types of sensor.

Syntax

Visual Basic (Declaration)

```
Public Enum swSensorType_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swSensorType\_e
```

C#

```
public enum swSensorType_e : System.Enum
```

C++/CLI

```
public enum class swSensorType_e : public System.Enum
```

Members

Member	Description
swSensorDimension	2 = Measurement (dimension) sensor
swSensorInterfaceDetection	3 = Interference detection sensor; Obsolete
swSensorMassProperty	1 = Obsolete
swSensorProximity	5 = Obsolete
swSensorSimulation	0 = Obsolete

Remarks

As of SOLIDWORKS 2009 SP02, only sensors of type swSensorDimension are supported. Non-dimension measurement sensors (=4) and all of the other sensor types are no longer supported.

See Also

[SolidWorks.Interop.swconst Namespace](#)

swSetComponentIdentifierResult_e (Type)

SOLIDWORKS API Enumerations

swSetComponentIdentifierResult_e Enumeration

[Send comments on this topic.](#)

[See Also](#)

 [SolidWorks.Interop.swconst Namespace](#) : swSetComponentIdentifierResult_e Enumeration

Set component identifier status. [Bitmask](#).

Syntax

Visual Basic (Declaration)

```
Public Enum swSetComponentIdentifierResult_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swSetComponentIdentifierResult\_e
```

C#

```
public enum swSetComponentIdentifierResult_e : System.Enum
```

C++/CLI

```
public enum class swSetComponentIdentifierResult_e : public System.Enum
```

Members

Member	Description
swSetComponentIdentifierResult_BlockedBySystemOption	8
swSetComponentIdentifierResult_InvalidPrimary	1
swSetComponentIdentifierResult_InvalidSecondary	2
swSetComponentIdentifierResult_InvalidTertiary	4
swSetComponentIdentifierResult_Success	0

See Also

[SolidWorks.Interop.swconst Namespace](#)

swSetComponentsAndTransformsStatus_e (Type)

SOLIDWORKS API Enumerations

swSetComponentsAndTransformsStatus_e Enumeration

[Send comments on this topic.](#)

[See Also](#)

 [SolidWorks.Interop.swconst Namespace](#) : swSetComponentsAndTransformsStatus_e Enumeration

Results for setting interfering components and their transforms.

Syntax

Visual Basic (Declaration)

```
Public Enum swSetComponentsAndTransformsStatus_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swSetComponentsAndTransformsStatus\_e
```

C#

```
public enum swSetComponentsAndTransformsStatus_e : System.Enum
```

C++/CLI

```
public enum class swSetComponentsAndTransformsStatus_e : public System.Enum
```

Members

Member	Description
swSetComponentsAndTransforms_Failed	0
swSetComponentsAndTransforms_InvalidInput	2
swSetComponentsAndTransforms_Succeeded	1

See Also

[SolidWorks.Interop.swconst Namespace](#)

swSetHelixRegionParameterStatus_e (Type)

SOLIDWORKS API Enumerations

swSetHelixRegionParameterStatus_e Enumeration

[Send comments on this topic.](#)

[See Also](#)

 

[SolidWorks.Interop.swconst Namespace](#) : swSetHelixRegionParameterStatus_e Enumeration

Statuses for setting helix regions.

 Syntax

Visual Basic (Declaration)

```
Public Enum swSetHelixRegionParameterStatus_e
    Inherits System.Enum
```

Visual Basic (Usage)  Copy Code

```
Dim instance As swSetHelixRegionParameterStatus\_e
```

C#

```
public enum swSetHelixRegionParameterStatus_e : System.Enum
```

C++/CLI

```
public enum class swSetHelixRegionParameterStatus_e : public System.Enum
```

 Members

Member	Description
swSetHelixRegionParam_Failed	1
swSetHelixRegionParam_InvalidInput	2
swSetHelixRegionParam_Succeeded	0

 See Also

[SolidWorks.Interop.swconst Namespace](#)