

SOLIDWORKS Enumerations (swconst) — Reference (14/17): swSpeedpakUpdate_e- swTangentMagnitudeDirection_e

SOLIDWORKS API Documentation (converted from CHM)

swSpeedpakUpdate_e (Type)

SOLIDWORKS API Enumerations

swSpeedpakUpdate_e Enumeration

See Also

[Send comments on this topic.](#)

 

[SolidWorks.Interop.swconst Namespace](#) : swSpeedpakUpdate_e Enumeration

Options for updating out-of-date Speedpak configurations when saving files.

 Syntax

Visual Basic (Declaration)

Public Enum swSpeedpakUpdate_e
Inherits System.Enum

Visual Basic (Usage)

Dim instance As [swSpeedpakUpdate_e](#)

C#

public enum swSpeedpakUpdate_e : System.Enum

C++/CLI

public enum class swSpeedpakUpdate_e : public System.Enum

 Members

Member	Description
swSpeedpakUpdate_All	0
swSpeedpakUpdate_None	1
swSpeedpakUpdate_WithRebuildOnSaveMark	2

 See Also

[SolidWorks.Interop.swconst Namespace](#)

swSplitBodyType_e (Type)

SOLIDWORKS API Enumerations

swSplitBodyType_e Enumeration

[See Also](#)

[Send comments on this topic.](#)

 

[SolidWorks.Interop.swconst Namespace](#) : swSplitBodyType_e Enumeration

Split body types.

Syntax

Visual Basic (Declaration)

Public Enum swSplitBodyType_e
Inherits System.Enum

Visual Basic (Usage)

Dim instance As [swSplitBodyType_e](#)

C#

public enum swSplitBodyType_e : System.Enum

C++/CLI

public enum class swSplitBodyType_e : public System.Enum

Members

Member	Description
swSplitBodyType_e_Consume	2
swSplitBodyType_e_Hide	1
swSplitBodyType_e_Show	0

See Also

[SolidWorks.Interop.swconst Namespace](#)

swSplitFaceOnParam_e (Type)

SOLIDWORKS API Enumerations

swSplitFaceOnParam_e Enumeration

[Send comments on this topic.](#)

[See Also](#)

 

[SolidWorks.Interop.swconst Namespace](#) : swSplitFaceOnParam_e Enumeration

Split face on parameters.

 Syntax

Visual Basic (Declaration)

```
Public Enum swSplitFaceOnParam_e
    Inherits System.Enum
```

Visual Basic (Usage)  [Copy Code](#)

```
Dim instance As swSplitFaceOnParam\_e
```

C#

```
public enum swSplitFaceOnParam_e : System.Enum
```

C++/CLI

```
public enum class swSplitFaceOnParam_e : public System.Enum
```

 Members

Member	Description
swSplitFaceOnParamU	1
swSplitFaceOnParamV	2

 See Also

[SolidWorks.Interop.swconst Namespace](#)

swSplitFacesOption_e (Type)

SOLIDWORKS API Enumerations

swSplitFacesOption_e Enumeration

See Also

[Send comments on this topic.](#)

 

[SolidWorks.Interop.swconst Namespace](#) : swSplitFacesOption_e Enumeration

Split faces options.

 Syntax

Visual Basic (Declaration)

Public Enum swSplitFacesOption_e
Inherits System.Enum

Visual Basic (Usage)  Copy Code

Dim instance As [swSplitFacesOption_e](#)

C#

public enum swSplitFacesOption_e : System.Enum

C++/CLI

public enum class swSplitFacesOption_e : public System.Enum

 Members

Member	Description
swSplitFacesAtPlusMinusDraftTransition	0
swSplitFacesAtSpecifiedAngle	1

 See Also

[SolidWorks.Interop.swconst Namespace](#)

swSplitLineFeatureType_e (Type)

SOLIDWORKS API Enumerations

swSplitLineFeatureType_e Enumeration

[See Also](#)

 

[SolidWorks.Interop.swconst Namespace](#) : swSplitLineFeatureType_e Enumeration

Split line feature types.

[Send comments on this topic.](#)

 Syntax

Visual Basic (Declaration)

Public Enum swSplitLineFeatureType_e
Inherits System.Enum

Visual Basic (Usage)

Dim instance As [swSplitLineFeatureType_e](#)

 [Copy Code](#)

C#

public enum swSplitLineFeatureType_e : System.Enum

C++/CLI

public enum class swSplitLineFeatureType_e : public System.Enum

 Members

Member	Description
swSplitLineFeatureType_Draft	0
swSplitLineFeatureType_Intersection	2
swSplitLineFeatureType_Projection	1

 See Also

[SolidWorks.Interop.swconst Namespace](#)

swSplitLineSplitSurfaceType_e (Type)

SOLIDWORKS API Enumerations

swSplitLineSplitSurfaceType_e Enumeration

See Also

 

[SolidWorks.Interop.swconst Namespace](#) : swSplitLineSplitSurfaceType_e Enumeration

Split line surface types.

[Send comments on this topic.](#)

Syntax

Visual Basic (Declaration)

```
Public Enum swSplitLineSplitSurfaceType_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swSplitLineSplitSurfaceType\_e
```

C#

```
public enum swSplitLineSplitSurfaceType_e : System.Enum
```

C++/CLI

```
public enum class swSplitLineSplitSurfaceType_e : public System.Enum
```

Members

Member	Description
swSplitLineSplitSurfaceType_Linear	1
swSplitLineSplitSurfaceType_Natural	0

See Also

[SolidWorks.Interop.swconst Namespace](#)

swSplitMemberDimensionType_e (Type)

SOLIDWORKS API Enumerations

swSplitMemberDimensionType_e Enumeration

See Also

 

[SolidWorks.Interop.swconst Namespace](#) : swSplitMemberDimensionType_e Enumeration

Structure system split member dimension types.

[Send comments on this topic.](#)

Syntax

Visual Basic (Declaration)

```
Public Enum swSplitMemberDimensionType_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swSplitMemberDimensionType\_e
```

C#

```
public enum swSplitMemberDimensionType_e : System.Enum
```

C++/CLI

```
public enum class swSplitMemberDimensionType_e : public System.Enum
```

Members

Member	Description
swSplitMemberDimensionType_Instance	1
swSplitMemberDimensionType_SplitLength	0

See Also

[SolidWorks.Interop.swconst Namespace](#)

swSpringDefineType_e (Type)

SOLIDWORKS API Enumerations

swSpringDefineType_e Enumeration

[See Also](#)

 

[SolidWorks.Interop.swconst Namespace](#) : swSpringDefineType_e Enumeration

Spring definition types.

[Send comments on this topic.](#)

Syntax

Visual Basic (Declaration)

Public Enum swSpringDefineType_e
Inherits System.Enum

Visual Basic (Usage)

Dim instance As [swSpringDefineType_e](#)

C#

public enum swSpringDefineType_e : System.Enum

C++/CLI

public enum class swSpringDefineType_e : public System.Enum

Members

Member	Description
swSpringDefineType_HeightAndPitch	2
swSpringDefineType_HeightAndRevolution	1
swSpringDefineType_PitchAndRevolution	0

See Also

[SolidWorks.Interop.swconst Namespace](#)

swSpringExtensionEndType_e (Type)

SOLIDWORKS API Enumerations

swSpringExtensionEndType_e Enumeration

See Also

 

[SolidWorks.Interop.swconst Namespace](#) : swSpringExtensionEndType_e Enumeration

Spring extension types.

[Send comments on this topic.](#)

Syntax

Visual Basic (Declaration)

```
Public Enum swSpringExtensionEndType_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swSpringExtensionEndType\_e
```

C#

```
public enum swSpringExtensionEndType_e : System.Enum
```

C++/CLI

```
public enum class swSpringExtensionEndType_e : public System.Enum
```

Members

Member	Description
swSpringExtensionEndType_FullLoop	0
swSpringExtensionEndType_HalfLoop	1
swSpringExtensionEndType_UserDefined	2

See Also

[SolidWorks.Interop.swconst Namespace](#)

swSpringProfileType_e (Type)

SOLIDWORKS API Enumerations

swSpringProfileType_e Enumeration

[See Also](#)

[Send comments on this topic.](#)

 

SolidWorks.Interop.swconst Namespace : swSpringProfileType_e Enumeration

Spring profile types.

Syntax

Visual Basic (Declaration)

```
Public Enum swSpringProfileType_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swSpringProfileType\_e
```

C#

```
public enum swSpringProfileType_e : System.Enum
```

C++/CLI

```
public enum class swSpringProfileType_e : public System.Enum
```

Members

Member	Description
swSpringProfileType_Circle	0
swSpringProfileType_Rectangle	1
swSpringProfileType_Trapezoid	2

See Also

[SolidWorks.Interop.swconst Namespace](#)

swSpringTorsionEndType_e (Type)

SOLIDWORKS API Enumerations

swSpringTorsionEndType_e Enumeration

See Also

 

[SolidWorks.Interop.swconst Namespace](#) : swSpringTorsionEndType_e Enumeration

Spring torsion end types.

[Send comments on this topic.](#)

Syntax

Visual Basic (Declaration)

```
Public Enum swSpringTorsionEndType_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swSpringTorsionEndType\_e
```

C#

```
public enum swSpringTorsionEndType_e : System.Enum
```

C++/CLI

```
public enum class swSpringTorsionEndType_e : public System.Enum
```

Members

Member	Description
swSpringTorsionEndType_Hinge	2
swSpringTorsionEndType_Hook	0
swSpringTorsionEndType_Straight	1
swSpringTorsionEndType_StraightOffset	3

See Also

[SolidWorks.Interop.swconst Namespace](#)

swSpringType_e (Type)

 

[SolidWorks.Interop.swconst Namespace](#) : swSpringType_e Enumeration

Spring types.

 Syntax

Visual Basic (Declaration)

Public Enum swSpringType_e
Inherits System.Enum

Visual Basic (Usage)  [Copy Code](#)

Dim instance As [swSpringType_e](#)

C#

public enum swSpringType_e : System.Enum

C++/CLI

public enum class swSpringType_e : public System.Enum

 Members

Member	Description
swSpringType_Compression	0
swSpringType_Extension	1
swSpringType_Spiral	3
swSpringType_Torsion	2

 See Also

[SolidWorks.Interop.swconst Namespace](#)

swStackedBalloonDirection_e (Type)

SOLIDWORKS API Enumerations

swStackedBalloonDirection_e Enumeration

[See Also](#)



[SolidWorks.Interop.swconst Namespace](#) : swStackedBalloonDirection_e Enumeration

Balloon stacking directions.

[Send comments on this topic.](#)

Syntax

Visual Basic (Declaration)

```
Public Enum swStackedBalloonDirection_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swStackedBalloonDirection\_e
```

C#

```
public enum swStackedBalloonDirection_e : System.Enum
```

C++/CLI

```
public enum class swStackedBalloonDirection_e : public System.Enum
```

Members

Member	Description
swStackedBalloonDir_Down	2 = Balloons stack downwards from the master balloon in the stack
swStackedBalloonDir_Left	3 = Balloons stack to the left from the master balloon in the stack
swStackedBalloonDir_None	0 = Stacking direction does not apply
swStackedBalloonDir_Right	4 = Balloons stack to the right from the master balloon in the stack
swStackedBalloonDir_Up	1 = Balloons stack upwards from the master balloon in the stack

See Also

[SolidWorks.Interop.swconst Namespace](#)

swStandardHeaderFooterPageSetupTexts_e (Type)

SOLIDWORKS API Enumerations

swStandardHeaderFooterPageSetupTexts_e Enumeration

[Send comments on this topic.](#)

[See Also](#)

 

[SolidWorks.Interop.swconst Namespace](#) : swStandardHeaderFooterPageSetupTexts_e Enumeration

Standard header and footer page setup options.

 Syntax

Visual Basic (Declaration)

Public Enum swStandardHeaderFooterPageSetupTexts_e
Inherits System.Enum

Visual Basic (Usage)

Dim instance As [swStandardHeaderFooterPageSetupTexts_e](#)

 [Copy Code](#)

C#

public enum swStandardHeaderFooterPageSetupTexts_e : System.Enum

C++/CLI

public enum class swStandardHeaderFooterPageSetupTexts_e : public System.Enum

 Members

Member	Description
swHeaderFooterText_Date	3
swHeaderFooterText_Filename	5
swHeaderFooterText_PageCount	2
swHeaderFooterText_PageNumber	1
swHeaderFooterText_Time	4

 See Also

[SolidWorks.Interop.swconst Namespace](#)

swStandardViews_e (Type)

SOLIDWORKS API Enumerations

swStandardViews_e Enumeration

[See Also](#)

[Send comments on this topic.](#)

 

SolidWorks.Interop.swconst Namespace : swStandardViews_e Enumeration

Standard view types.

Syntax

Visual Basic (Declaration)

```
Public Enum swStandardViews_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swStandardViews\_e
```

C#

```
public enum swStandardViews_e : System.Enum
```

C++/CLI

```
public enum class swStandardViews_e : public System.Enum
```

Members

Member	Description
swBackView	2
swBottomView	6
swDimetricView	9
swFrontView	1
swIsometricView	7
swLeftView	3
swRightView	4
swTopView	5
swTrimetricView	8

See Also

[SolidWorks.Interop.swconst Namespace](#)

swStartConditions_e (Type)

SOLIDWORKS API Enumerations

swStartConditions_e Enumeration

See Also

[Send comments on this topic.](#)

 

[SolidWorks.Interop.swconst Namespace](#) : swStartConditions_e Enumeration

Start conditions.

 Syntax

Visual Basic (Declaration)

```
Public Enum swStartConditions_e
    Inherits System.Enum
```

Visual Basic (Usage)  Copy Code

```
Dim instance As swStartConditions\_e
```

C#

```
public enum swStartConditions_e : System.Enum
```

C++/CLI

```
public enum class swStartConditions_e : public System.Enum
```

 Members

Member	Description
swStartOffset	3
swStartSketchPlane	0
swStartSurface	1
swStartVertex	2

 See Also

[SolidWorks.Interop.swconst Namespace](#)

swStep242Error_e (Type)

SOLIDWORKS API Enumerations

swStep242Error_e Enumeration

[Send comments on this topic.](#)

[See Also](#)

 

[SolidWorks.Interop.swconst Namespace](#) : swStep242Error_e Enumeration

Status codes for exporting SOLIDWORKS MBD 3D PDF files to STEP 242.

Syntax

Visual Basic (Declaration)

```
Public Enum swStep242Error_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swStep242Error\_e
```

C#

```
public enum swStep242Error_e : System.Enum
```

C++/CLI

```
public enum class swStep242Error_e : public System.Enum
```

Members

Member	Description
swPublishStep242_CustomPropertyError	6
swPublishStep242_EditionError	5
swPublishStep242_InvalidPath	1
swPublishStep242_MBDLicenseNotAvailable	4
swPublishStep242_Success	0
swPublishStep242_UnknownError	3

See Also

[SolidWorks.Interop.swconst Namespace](#)

swSTLQuality_e (Type)

SOLIDWORKS API Enumerations

swSTLQuality_e Enumeration

[See Also](#)

[Send comments on this topic.](#)

 

[SolidWorks.Interop.swconst Namespace](#) : swSTLQuality_e Enumeration

STL quality types.

 Syntax

Visual Basic (Declaration)

Public Enum swSTLQuality_e
Inherits System.Enum

Visual Basic (Usage)

Dim instance As [swSTLQuality_e](#)



C#

public enum swSTLQuality_e : System.Enum

C++/CLI

public enum class swSTLQuality_e : public System.Enum

 Members

Member	Description
swSTLQuality_Coarse	1
swSTLQuality_Custom	3
swSTLQuality_Fine	2

 See Also

[SolidWorks.Interop.swconst Namespace](#)

swStopContinuePrompt_e (Type)

SOLIDWORKS API Enumerations

swStopContinuePrompt_e Enumeration

See Also

[Send comments on this topic.](#)

 

[SolidWorks.Interop.swconst Namespace](#) : swStopContinuePrompt_e Enumeration

Continue repsonses.

 Syntax

Visual Basic (Declaration)

```
Public Enum swStopContinuePrompt_e
    Inherits System.Enum
```

Visual Basic (Usage)  Copy Code

```
Dim instance As swStopContinuePrompt\_e
```

C#

```
public enum swStopContinuePrompt_e : System.Enum
```

C++/CLI

```
public enum class swStopContinuePrompt_e : public System.Enum
```

 Members

Member	Description
swContinueResponse_Continue	2
swContinueResponse_Prompt	3
swContinueResponse_Stop	1

 See Also

[SolidWorks.Interop.swconst Namespace](#)

swStraightHoleClassificationType_e (Type)

SOLIDWORKS API Enumerations

swStraightHoleClassificationType_e Enumeration

See Also

Send comments on this topic.

SolidWorks.Interop.swconst Namespace : swStraightHoleClassificationType_e Enumeration

Classification types for straight hole elements of the Advanced Hole.

Syntax

Visual Basic (Declaration)

```
Public Enum swStraightHoleClassificationType_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swStraightHoleClassificationType_e
```

C#

```
public enum swStraightHoleClassificationType_e : System.Enum
```

C++/CLI

```
public enum class swStraightHoleClassificationType_e : public System.Enum
```

Members

Member	Description
swStraightHoleClassificationType_Clearance	1
swStraightHoleClassificationType_Nominal	0
swStraightHoleClassificationType_Press	3
swStraightHoleClassificationType_Transitional	2

See Also

SolidWorks.Interop.swconst Namespace

swStraightHoleFilter_e (Type)

SOLIDWORKS API Enumerations

swStraightHoleFilter_e Enumeration

See Also

[Send comments on this topic.](#)

 [SolidWorks.Interop.swconst Namespace](#) : swStraightHoleFilter_e Enumeration

Filters for straight hole elements that use the PEM standard in Advanced Holes.

 Syntax

Visual Basic (Declaration)

Public Enum swStraightHoleFilter_e
Inherits System.Enum

Visual Basic (Usage)

Dim instance As [swStraightHoleFilter_e](#)

 Copy Code

C#

public enum swStraightHoleFilter_e : System.Enum

C++/CLI

public enum class swStraightHoleFilter_e : public System.Enum

 Members

Member	Description
swStraightHoleFilter_All	0
swStraightHoleFilter_Fasteners	2
swStraightHoleFilter_Nuts	1
swStraightHoleFilter_Pins	5
swStraightHoleFilter_Standoffs	3
swStraightHoleFilter_Studs	4

 See Also

[SolidWorks.Interop.swconst Namespace](#)

swStraightHoleFitType_e (Type)

SOLIDWORKS API Enumerations

swStraightHoleFitType_e Enumeration

See Also

[Send comments on this topic.](#)

 [SolidWorks.Interop.swconst Namespace](#) : swStraightHoleFitType_e Enumeration

Fit types for straight hole elements of the Advanced Hole.

 Syntax

Visual Basic (Declaration)

Public Enum swStraightHoleFitType_e
Inherits System.Enum

Visual Basic (Usage)

Dim instance As [swStraightHoleFitType_e](#)



C#

public enum swStraightHoleFitType_e : System.Enum

C++/CLI

public enum class swStraightHoleFitType_e : public System.Enum

 Members

Member	Description
swStraightHoleFitType_Close	0
swStraightHoleFitType_Loose	2
swStraightHoleFitType_Normal	1

 See Also

[SolidWorks.Interop.swconst Namespace](#)

swStraightTapHoleCustomSizing_e (Type)

SOLIDWORKS API Enumerations

swStraightTapHoleCustomSizing_e Enumeration

See Also

[Send comments on this topic.](#)

 [SolidWorks.Interop.swconst Namespace](#) : swStraightTapHoleCustomSizing_e Enumeration

Custom sizing options for straight tap elements of the Advanced Hole.

 Syntax

Visual Basic (Declaration)

Public Enum swStraightTapHoleCustomSizing_e
Inherits System.Enum

Visual Basic (Usage)

Dim instance As [swStraightTapHoleCustomSizing_e](#)



C#

public enum swStraightTapHoleCustomSizing_e : System.Enum

C++/CLI

public enum class swStraightTapHoleCustomSizing_e : public System.Enum

 Members

Member	Description
swStraightTapHoleCustomSizing_MajorDiameter	2
swStraightTapHoleCustomSizing_TapDrillDiameter	0
swStraightTapHoleCustomSizing_TapDrillDiameterWithCosmeticThread	1

 See Also

[SolidWorks.Interop.swconst Namespace](#)

swStraightTapHoleEquation_e (Type)

SOLIDWORKS API Enumerations

swStraightTapHoleEquation_e Enumeration

See Also

[Send comments on this topic.](#)

 [SolidWorks.Interop.swconst Namespace](#) : swStraightTapHoleEquation_e Enumeration

Straight tap hole equation options for blind depth and offset distance.

Syntax

Visual Basic (Declaration)

Public Enum swStraightTapHoleEquation_e
Inherits System.Enum

Visual Basic (Usage)

Dim instance As [swStraightTapHoleEquation_e](#)

C#

public enum swStraightTapHoleEquation_e : System.Enum

C++/CLI

public enum class swStraightTapHoleEquation_e : public System.Enum

Members

Member	Description
swStraightTapHoleEquation_Diameter	0
swStraightTapHoleEquation_DiameterAndHalf	1
swStraightTapHoleEquation_TwiceTheDiameter	2
swStraightTapHoleEquation_UserDefinedValue	3

See Also

[SolidWorks.Interop.swconst Namespace](#)

swStraightTapHoleThreadClass_e (Type)

SOLIDWORKS API Enumerations

swStraightTapHoleThreadClass_e Enumeration

See Also

[Send comments on this topic.](#)

 

[SolidWorks.Interop.swconst Namespace](#) : swStraightTapHoleThreadClass_e Enumeration

Thread classes for straight tap hole elements of the Advanced Hole.

 Syntax

Visual Basic (Declaration)

Public Enum swStraightTapHoleThreadClass_e
Inherits System.Enum

Visual Basic (Usage)

Dim instance As [swStraightTapHoleThreadClass_e](#)



C#

public enum swStraightTapHoleThreadClass_e : System.Enum

C++/CLI

public enum class swStraightTapHoleThreadClass_e : public System.Enum

 Members

Member	Description
swStraightTapHoleThreadClass_1B	1
swStraightTapHoleThreadClass_2B	2
swStraightTapHoleThreadClass_3B	3

 See Also

[SolidWorks.Interop.swconst Namespace](#)

swStructureProfileAlignmentType_e (Type)

SOLIDWORKS API Enumerations

swStructureProfileAlignmentType_e Enumeration

See Also

 

[SolidWorks.Interop.swconst Namespace](#) : swStructureProfileAlignmentType_e Enumeration

Structure system profile alignment types.

[Send comments on this topic.](#)

Syntax

Visual Basic (Declaration)

```
Public Enum swStructureProfileAlignmentType_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swStructureProfileAlignmentType\_e
```

C#

```
public enum swStructureProfileAlignmentType_e : System.Enum
```

C++/CLI

```
public enum class swStructureProfileAlignmentType_e : public System.Enum
```

Members

Member	Description
swStructureProfileAlignmentType_HorizontalAxis	0
swStructureProfileAlignmentType_VerticalAxis	1

See Also

[SolidWorks.Interop.swconst Namespace](#)

swStructureProfileMirrorType_e (Type)

SOLIDWORKS API Enumerations

swStructureProfileMirrorType_e Enumeration

See Also

[Send comments on this topic.](#)

SolidWorks.Interop.swconst Namespace : swStructureProfileMirrorType_e Enumeration

Structure system profile mirror types.

Syntax

Visual Basic (Declaration)

Public Enum swStructureProfileMirrorType_e
Inherits System.Enum

Visual Basic (Usage)

Dim instance As [swStructureProfileMirrorType_e](#)

C#

public enum swStructureProfileMirrorType_e : System.Enum

C++/CLI

public enum class swStructureProfileMirrorType_e : public System.Enum

Members

Member	Description
swStructureProfileMirrorType_HorizontalAxis	0
swStructureProfileMirrorType_VerticalAxis	1

See Also

[SolidWorks.Interop.swconst Namespace](#)

swStructureProfilePiercePointType_e (Type)

SOLIDWORKS API Enumerations

swStructureProfilePiercePointType_e Enumeration

[Send comments on this topic.](#)

[See Also](#)

 

[SolidWorks.Interop.swconst Namespace](#) : swStructureProfilePiercePointType_e Enumeration

Structure profile pierce points.

Syntax

Visual Basic (Declaration)

```
Public Enum swStructureProfilePiercePointType_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swStructureProfilePiercePointType\_e
```

C#

```
public enum swStructureProfilePiercePointType_e : System.Enum
```

C++/CLI

```
public enum class swStructureProfilePiercePointType_e : public System.Enum
```

Members

Member	Description
swStructureProfilePiercePoint_BottomCenter	2
swStructureProfilePiercePoint_BottomLeft	7
swStructureProfilePiercePoint_BottomRight	8
swStructureProfilePiercePoint_Center	0
swStructureProfilePiercePoint_CenterLeft	5
swStructureProfilePiercePoint_CenterRight	6
swStructureProfilePiercePoint_Selection	9
swStructureProfilePiercePoint_TopCenter	1
swStructureProfilePiercePoint_TopLeft	3
swStructureProfilePiercePoint_TopRight	4

See Also

[SolidWorks.Interop.swconst Namespace](#)

swStructureSplitMemberType_e (Type)

SOLIDWORKS API Enumerations

swStructureSplitMemberType_e Enumeration

See Also

▼

[SolidWorks.Interop.swconst Namespace](#) : swStructureSplitMemberType_e Enumeration

Structure system split member types.

[Send comments on this topic.](#)

Syntax

Visual Basic (Declaration)

```
Public Enum swStructureSplitMemberType_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swStructureSplitMemberType\_e
```

C#

```
public enum swStructureSplitMemberType_e : System.Enum
```

C++/CLI

```
public enum class swStructureSplitMemberType_e : public System.Enum
```

Members

Member	Description
swStructureSplitMember_Dimension	1
swStructureSplitMember_Reference	0

See Also

[SolidWorks.Interop.swconst Namespace](#)

swStructureSystemMemberCreationType_e (Type)

SOLIDWORKS API Enumerations

swStructureSystemMemberCreationType_e Enumeration

See Also

▼

[SolidWorks.Interop.swconst Namespace](#) : swStructureSystemMemberCreationType_e Enumeration

Structure system member creation types.

[Send comments on this topic.](#)

Syntax

Visual Basic (Declaration)

```
Public Enum swStructureSystemMemberCreationType_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swStructureSystemMemberCreationType\_e
```

C#

```
public enum swStructureSystemMemberCreationType_e : System.Enum
```

C++/CLI

```
public enum class swStructureSystemMemberCreationType_e : public System.Enum
```

Members

Member	Description
swStructureSystemMemberCreationType_Primary_FacePlaneIntersection	3
swStructureSystemMemberCreationType_Primary_PathSegment	0
swStructureSystemMemberCreationType_Primary_PointLength	2
swStructureSystemMemberCreationType_Primary_RefPlane	1
swStructureSystemMemberCreationType_Secondary_BetweenPoints	5
swStructureSystemMemberCreationType_Secondary_SupportPlane	4
swStructureSystemMemberCreationType_Secondary_UpToMembers	6

See Also

[SolidWorks.Interop.swconst Namespace](#)

swStructureSystemMemberType_e (Type)

SOLIDWORKS API Enumerations

swStructureSystemMemberType_e Enumeration

See Also

[SolidWorks.Interop.swconst Namespace](#) : swStructureSystemMemberType_e Enumeration

Structure system member types.

[Send comments on this topic.](#)

Syntax

Visual Basic (Declaration)

```
Public Enum swStructureSystemMemberType_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swStructureSystemMemberType\_e
```

C#

```
public enum swStructureSystemMemberType_e : System.Enum
```

C++/CLI

```
public enum class swStructureSystemMemberType_e : public System.Enum
```

Members

Member	Description
swStructureSystemMemberType_Primary	0
swStructureSystemMemberType_Secondary	1

See Also

[SolidWorks.Interop.swconst Namespace](#)

swStyleSplineCurveType_e (Type)

SOLIDWORKS API Enumerations

swStyleSplineCurveType_e Enumeration

See Also

[Send comments on this topic.](#)

 SolidWorks.Interop.swconst Namespace : swStyleSplineCurveType_e Enumeration

Curve types and degrees for style splines.

 Syntax

Visual Basic (Declaration)

Public Enum swStyleSplineCurveType_e
Inherits System.Enum

Visual Basic (Usage)

Dim instance As [swStyleSplineCurveType_e](#)



C#

public enum swStyleSplineCurveType_e : System.Enum

C++/CLI

public enum class swStyleSplineCurveType_e : public System.Enum

 Members

Member	Description
BezierCurve	0
BSpline_Degree3	1
BSpline_Degree5	2
BSpline_Degree7	3

 See Also

[SolidWorks.Interop.swconst Namespace](#)

swSummInfoField_e (Type)

SOLIDWORKS API Enumerations

swSummInfoField_e Enumeration

See Also

[Send comments on this topic.](#)

 [SolidWorks.Interop.swconst Namespace](#) : swSummInfoField_e Enumeration

Summary information fields. Read-only.

 Syntax

Visual Basic (Declaration)

```
Public Enum swSummInfoField_e
    Inherits System.Enum
```

Visual Basic (Usage)  Copy Code

```
Dim instance As swSummInfoField\_e
```

C#

```
public enum swSummInfoField_e : System.Enum
```

C++/CLI

```
public enum class swSummInfoField_e : public System.Enum
```

 Members

Member	Description
swSumInfoAuthor	2
swSumInfoComment	4
swSumInfoCreateDate	6
swSumInfoCreateDate2	8
swSumInfoKeywords	3
swSumInfoSaveDate	7
swSumInfoSaveDate2	9
swSumInfoSavedBy	5
swSumInfoSubject	1
swSumInfoTitle	0

 See Also

[SolidWorks.Interop.swconst Namespace](#)

swSunlightInfoType_e (Type)

SOLIDWORKS API Enumerations

swSunlightInfoType_e Enumeration

[See Also](#)

[Send comments on this topic.](#)

 

SolidWorks.Interop.swconst Namespace : swSunlightInfoType_e Enumeration

Sunlight information.

 Syntax

Visual Basic (Declaration)

```
Public Enum swSunlightInfoType_e
    Inherits System.Enum
```

Visual Basic (Usage)  Copy Code

```
Dim instance As swSunlightInfoType\_e
```

C#

```
public enum swSunlightInfoType_e : System.Enum
```

C++/CLI

```
public enum class swSunlightInfoType_e : public System.Enum
```

 Members

Member	Description
swSunlight_LengthOfDay	3; Minutes of sunlight in a day
swSunlight_Sunrise	1; Hours from midnight to sunrise
swSunlight_Sunset	2; Hours from midnight to sunset

 See Also

[SolidWorks.Interop.swconst Namespace](#)

swSuppressDialog_e (Type)

SOLIDWORKS API Enumerations

swSuppressDialog_e Enumeration

See Also

 

[SolidWorks.Interop.swconst Namespace](#) : swSuppressDialog_e Enumeration

Task dialog suppression options. For internal use only.

[Send comments on this topic.](#)

 Syntax

Visual Basic (Declaration)

```
Public Enum swSuppressDialog_e
    Inherits System.Enum
```

Visual Basic (Usage)

 Copy Code

```
Dim instance As swSuppressDialog\_e
```

C#

```
public enum swSuppressDialog_e : System.Enum
```

C++/CLI

```
public enum class swSuppressDialog_e : public System.Enum
```

 Members

Member	Description
swSuppressDialog_All	2
swSuppressDialog_LocateReference	4
swSuppressDialog_None	1

 See Also

[SolidWorks.Interop.swconst Namespace](#)

swSuppressionError_e (Type)

SOLIDWORKS API Enumerations

swSuppressionError_e Enumeration

See Also

▼

SolidWorks.Interop.swconst Namespace : swSuppressionError_e Enumeration

Suppression errors.

[Send comments on this topic.](#)

Syntax

Visual Basic (Declaration)

```
Public Enum swSuppressionError_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swSuppressionError\_e
```

C#

```
public enum swSuppressionError_e : System.Enum
```

C++/CLI

```
public enum class swSuppressionError_e : public System.Enum
```

Members

Member	Description
swSuppressionBadComponent	0 = Component object is no longer valid; for example, if a configuration changed
swSuppressionBadState	1 = Invalid state was specified
swSuppressionChangeFailed	3 = Change failed, even though the arguments were okay
swSuppressionChangeOk	2 = State was changed

See Also

[SolidWorks.Interop.swconst Namespace](#)

swSurfaceCutFeatureError_e (Type)

SOLIDWORKS API Enumerations

swSurfaceCutFeatureError_e Enumeration

See Also

[SolidWorks.Interop.swconst Namespace](#) : swSurfaceCutFeatureError_e Enumeration

Types of surface-cut errors.

Syntax

Visual Basic (Declaration)

```
Public Enum swSurfaceCutFeatureError_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swSurfaceCutFeatureError\_e
```

C#

```
public enum swSurfaceCutFeatureError_e : System.Enum
```

C++/CLI

```
public enum class swSurfaceCutFeatureError_e : public System.Enum
```

Members

Member	Description
swSurfaceCutFeatureError_BodiesNotSpecified	1 = No bodies specified to cut
swSurfaceCutFeatureError_InvalidVariant	2 = Array passed to IFeatureManager::InsertCutSurface must contain only body objects
swSurfaceCutFeatureError_NoError	0 = No error

See Also

[SolidWorks.Interop.swconst Namespace](#)

swSurfaceExtendEndCond_e (Type)

SOLIDWORKS API Enumerations

swSurfaceExtendEndCond_e Enumeration

See Also

[Send comments on this topic.](#)

 

[SolidWorks.Interop.swconst Namespace](#) : swSurfaceExtendEndCond_e Enumeration

Surface extend end conditions.

 Syntax

Visual Basic (Declaration)

Public Enum swSurfaceExtendEndCond_e
Inherits System.Enum

Visual Basic (Usage)  Copy Code

Dim instance As [swSurfaceExtendEndCond_e](#)

C#

public enum swSurfaceExtendEndCond_e : System.Enum

C++/CLI

public enum class swSurfaceExtendEndCond_e : public System.Enum

 Members

Member	Description
swSurfaceExtendEndCondDistance	0
swSurfaceExtendEndCondUpToPoint	1
swSurfaceExtendEndCondUpToSurface	2

 See Also

[SolidWorks.Interop.swconst Namespace](#)

swSurfaceFinishSymbolOrientation_e (Type)

SOLIDWORKS API Enumerations

swSurfaceFinishSymbolOrientation_e Enumeration

See Also

[SolidWorks.Interop.swconst Namespace](#) : swSurfaceFinishSymbolOrientation_e Enumeration

Surface finish symbol orientations.

[Send comments on this topic.](#)

Syntax

Visual Basic (Declaration)

Public Enum swSurfaceFinishSymbolOrientation_e
Inherits System.Enum

Visual Basic (Usage)

Dim instance As [swSurfaceFinishSymbolOrientation_e](#)

C#

public enum swSurfaceFinishSymbolOrientation_e : System.Enum

C++/CLI

public enum class swSurfaceFinishSymbolOrientation_e : public System.Enum

Members

Member	Description
swSFOrientation_Perpendicular	3 = Symbol is displayed at the same angle as the attached entity
swSFOrientation_PerpendicularFlipped	4 = Symbol is displayed at the same angle as the attached entity, but the symbol is flipped to the other side of the entity
swSFOrientation_Rotated90	2 = Symbol is displayed vertical (rotated 90 clockwise)
swSFOrientation_Upright	1 = Symbol is displayed horizontal
swSFOrientation_UserDefined	5 = Symbol is displayed at a user-specified angle

See Also

[SolidWorks.Interop.swconst Namespace](#)

swSurfaceFinishSymbolText_e (Type)

SOLIDWORKS API Enumerations

swSurfaceFinishSymbolText_e Enumeration

[Send comments on this topic.](#)

[See Also](#)

[SolidWorks.Interop.swconst Namespace](#) : swSurfaceFinishSymbolText_e Enumeration

Types of surface finish symbol texts.

Syntax

Visual Basic (Declaration)

```
Public Enum swSurfaceFinishSymbolText_e
    Inherits System.Enum
```

Visual Basic (Usage)  [Copy Code](#)

```
Dim instance As swSurfaceFinishSymbolText\_e
```

C#

```
public enum swSurfaceFinishSymbolText_e : System.Enum
```

C++/CLI

```
public enum class swSurfaceFinishSymbolText_e : public System.Enum
```

Members

Member	Description
swSFSymbolMaterialRemovalAllowance	1
swSFSymbolMaximumRoughness	5
swSFSymbolMinimumRoughness	6
swSFSymbolOtherRoughnessValue	4
swSFSymbolProductionMethod	2
swSFSymbolRoughnessSpacing	7
swSFSymbolRoughnessValue1	8
swSFSymbolRoughnessValue2	9
swSFSymbolRoughnessValue3	10
swSFSymbolSamplingLength	3

See Also

[SolidWorks.Interop.swconst Namespace](#)

swSurfaceTrimType_e (Type)

SOLIDWORKS API Enumerations

swSurfaceTrimType_e Enumeration

[See Also](#)

 

[SolidWorks.Interop.swconst Namespace](#) : swSurfaceTrimType_e Enumeration

Surface trim types.

[Send comments on this topic.](#)

 Syntax

Visual Basic (Declaration)

Public Enum swSurfaceTrimType_e
Inherits System.Enum

Visual Basic (Usage)

Dim instance As [swSurfaceTrimType_e](#)



C#

public enum swSurfaceTrimType_e : System.Enum

C++/CLI

public enum class swSurfaceTrimType_e : public System.Enum

 Members

Member	Description
swTypeMutualTrim	1
swTypeTrimTool	0

 See Also

[SolidWorks.Interop.swconst Namespace](#)

swSurfaceTypes_e (Type)

SOLIDWORKS API Enumerations

swSurfaceTypes_e Enumeration

See Also

[Send comments on this topic.](#)

 SolidWorks.Interop.swconst Namespace : swSurfaceTypes_e Enumeration

Surface types.

 Syntax

Visual Basic (Declaration)

```
Public Enum swSurfaceTypes_e
    Inherits System.Enum
```

Visual Basic (Usage)

 Copy Code

```
Dim instance As swSurfaceTypes\_e
```

C#

```
public enum swSurfaceTypes_e : System.Enum
```

C++/CLI

```
public enum class swSurfaceTypes_e : public System.Enum
```

 Members

Member	Description
BLEND_TYPE	4007
BSURF_TYPE	4006
CONE_TYPE	4003
CYLINDER_TYPE	4002
EXTRU_TYPE	4009
OFFSET_TYPE	4008
PLANE_TYPE	4001
SPHERE_TYPE	4004
SREV_TYPE	4010
TORUS_TYPE	4005

 See Also

[SolidWorks.Interop.swconst Namespace](#)

swSweepDirection_e (Type)

SOLIDWORKS API Enumerations

swSweepDirection_e Enumeration

See Also

[Send comments on this topic.](#)

 

[SolidWorks.Interop.swconst Namespace](#) : swSweepDirection_e Enumeration

Sweep directions.

 Syntax

Visual Basic (Declaration)

```
Public Enum swSweepDirection_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swSweepDirection\_e
```

C#

```
public enum swSweepDirection_e : System.Enum
```

C++/CLI

```
public enum class swSweepDirection_e : public System.Enum
```

 Members

Member	Description
swSweepBidirectional	1
swSweepDirection1	0
swSweepDirection2	2

 See Also

[SolidWorks.Interop.swconst Namespace](#)

swSweptFlangeError_e (Type)

SOLIDWORKS API Enumerations

swSweptFlangeError_e Enumeration

See Also

 

SolidWorks.Interop.swconst Namespace : swSweptFlangeError_e Enumeration

Swept flange creation errors. [Bitmask](#).

[Send comments on this topic.](#)

 Syntax

Visual Basic (Declaration)

Public Enum swSweptFlangeError_e
Inherits System.Enum

Visual Basic (Usage)

Dim instance As [swSweptFlangeError_e](#)

C#

public enum swSweptFlangeError_e : System.Enum

C++/CLI

public enum class swSweptFlangeError_e : public System.Enum

 Members

Member	Description
swSweptFlangeError_InvalidPath	2
swSweptFlangeError_InvalidProfile	1
swSweptFlangeError_InvalidSheetMetalParameters	8 = ISweptFlangeFeatureData::UseMaterialSheetMetalParameters and ISweptFlangeFeatureData::UseGaugeTable cannot both be set to true
swSweptFlangeError_None	0
swSweptFlangeError_SelfIntersectingGeometry	4

 See Also

[SolidWorks.Interop.swconst Namespace](#)

swSweptFlangePositionTypes_e (Type)

SOLIDWORKS API Enumerations

swSweptFlangePositionTypes_e Enumeration

See Also

[Send comments on this topic.](#)

 

[SolidWorks.Interop.swconst Namespace](#) : swSweptFlangePositionTypes_e Enumeration

Types of swept flange position.

Syntax

Visual Basic (Declaration)

```
Public Enum swSweptFlangePositionTypes_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swSweptFlangePositionTypes\_e
```

C#

```
public enum swSweptFlangePositionTypes_e : System.Enum
```

C++/CLI

```
public enum class swSweptFlangePositionTypes_e : public System.Enum
```

Members

Member	Description
swSweptFlangePositionType_BendOutside	3
swSweptFlangePositionType_MaterialInside	1
swSweptFlangePositionType_MaterialOutside	2

See Also

[SolidWorks.Interop.swconst Namespace](#)

swSystemColorsCurrentColorScheme_e (Type)

SOLIDWORKS API Enumerations

swSystemColorsCurrentColorScheme_e Enumeration

[Send comments on this topic.](#)

[See Also](#)

 

[SolidWorks.Interop.swconst Namespace](#) : swSystemColorsCurrentColorScheme_e Enumeration

Current color schemes.

Syntax

Visual Basic (Declaration)

```
Public Enum swSystemColorsCurrentColorScheme_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swSystemColorsCurrentColorScheme\_e
```

C#

```
public enum swSystemColorsCurrentColorScheme_e : System.Enum
```

C++/CLI

```
public enum class swSystemColorsCurrentColorScheme_e : public System.Enum
```

Members

Member	Description
swSystemColorsCurrentColorSchemeBlueHighlight	0
swSystemColorsCurrentColorSchemeGreenHighlight	1
swSystemColorsCurrentColorSchemeOrangeHighlight	2

See Also

[SolidWorks.Interop.swconst Namespace](#)

swSystemColorsEnvelopes_e (Type)

SOLIDWORKS API Enumerations

swSystemColorsEnvelopes_e Enumeration

[See Also](#)

 [SolidWorks.Interop.swconst Namespace](#) : swSystemColorsEnvelopes_e Enumeration

System envelope colors.

[Send comments on this topic.](#)

 Syntax

Visual Basic (Declaration)

Public Enum swSystemColorsEnvelopes_e
Inherits System.Enum

Visual Basic (Usage)

Dim instance As [swSystemColorsEnvelopes_e](#)

C#

public enum swSystemColorsEnvelopes_e : System.Enum

C++/CLI

public enum class swSystemColorsEnvelopes_e : public System.Enum

 Members

Member	Description
swSystemColorsEnvelopes_DoNotChange	2
swSystemColorsEnvelopes_Opaque	1
swSystemColorsEnvelopes_SemiTransparent	0

 See Also

[SolidWorks.Interop.swconst Namespace](#)

swSystemColorsIconColor_e (Type)

SOLIDWORKS API Enumerations

swSystemColorsIconColor_e Enumeration

[See Also](#)

 

[SolidWorks.Interop.swconst Namespace](#) : swSystemColorsIconColor_e Enumeration

System icon colors.

[Send comments on this topic.](#)

Syntax

Visual Basic (Declaration)

```
Public Enum swSystemColorsIconColor_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swSystemColorsIconColor\_e
```

C#

```
public enum swSystemColorsIconColor_e : System.Enum
```

C++/CLI

```
public enum class swSystemColorsIconColor_e : public System.Enum
```

Members

Member	Description
swSystemColorsIconColorClassic	1
swSystemColorsIconColorDefault	0

See Also

[SolidWorks.Interop.swconst Namespace](#)

swSystemOptionDisplayAntiAliasing_e (Type)

SOLIDWORKS API Enumerations

swSystemOptionDisplayAntiAliasing_e Enumeration

[Send comments on this topic.](#)

[See Also](#)

 

[SolidWorks.Interop.swconst Namespace](#) : swSystemOptionDisplayAntiAliasing_e Enumeration

System anti-aliasing display options.

Syntax

Visual Basic (Declaration)

```
Public Enum swSystemOptionDisplayAntiAliasing_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swSystemOptionDisplayAntiAliasing\_e
```

C#

```
public enum swSystemOptionDisplayAntiAliasing_e : System.Enum
```

C++/CLI

```
public enum class swSystemOptionDisplayAntiAliasing_e : public System.Enum
```

Members

Member	Description
swSystemOptionDisplayAntiAliasing_Edges	2
swSystemOptionDisplayAntiAliasing_FullScene	3
swSystemOptionDisplayAntiAliasing_None	1

See Also

[SolidWorks.Interop.swconst Namespace](#)

swTabEdgesType_e (Type)

SOLIDWORKS API Enumerations

swTabEdgesType_e Enumeration

[See Also](#)

[Send comments on this topic.](#)

 

[SolidWorks.Interop.swconst Namespace](#) : swTabEdgesType_e Enumeration

Types of tab edge treatments for Tab and Slot groups.

Syntax

Visual Basic (Declaration)

Public Enum swTabEdgesType_e
Inherits System.Enum

Visual Basic (Usage)

Dim instance As [swTabEdgesType_e](#)

C#

public enum swTabEdgesType_e : System.Enum

C++/CLI

public enum class swTabEdgesType_e : public System.Enum

Members

Member	Description
ChamferEdge	2 = Specify a chamfer distance
FilletEdge	1 = Specify a fillet radius
SharpEdge	0

See Also

[SolidWorks.Interop.swconst Namespace](#)

swTableAnnotationType_e (Type)

SOLIDWORKS API Enumerations

swTableAnnotationType_e Enumeration

See Also

[Send comments on this topic.](#)

 

[SolidWorks.Interop.swconst Namespace](#) : swTableAnnotationType_e Enumeration

Table annotation types.

 Syntax

Visual Basic (Declaration)

Public Enum swTableAnnotationType_e
Inherits System.Enum

Visual Basic (Usage)

Dim instance As [swTableAnnotationType_e](#)



C#

public enum swTableAnnotationType_e : System.Enum

C++/CLI

public enum class swTableAnnotationType_e : public System.Enum

 Members

Member	Description
swTableAnnotation_BendTable	7
swTableAnnotation_BillOfMaterials	2
swTableAnnotation_FamilyTable	10
swTableAnnotation_General	0
swTableAnnotation_GeneralTolerance	9
swTableAnnotation_HoleChart	1
swTableAnnotation_PunchTable	8
swTableAnnotation_RevisionBlock	3
swTableAnnotation_TitleBlock	5
swTableAnnotation_WeldmentCutList	4
swTableAnnotation_WeldTable	6

 See Also

[SolidWorks.Interop.swconst Namespace](#)

swTableCellOrientation_e (Type)

SOLIDWORKS API Enumerations

swTableCellOrientation_e Enumeration

See Also

[Send comments on this topic.](#)

 [SolidWorks.Interop.swconst Namespace](#) : swTableCellOrientation_e Enumeration

Orientations of text in table cells.

 Syntax

Visual Basic (Declaration)

Public Enum swTableCellOrientation_e
Inherits System.Enum

Visual Basic (Usage)

Dim instance As [swTableCellOrientation_e](#)

C#

public enum swTableCellOrientation_e : System.Enum

C++/CLI

public enum class swTableCellOrientation_e : public System.Enum

 Members

Member	Description
swTableCellOrientation_Down	3
swTableCellOrientation_Left	1
swTableCellOrientation_Right	0
swTableCellOrientation_Rotate90CCW	6 = Rotate text 90 degrees counter clockwise from the current orientation
swTableCellOrientation_Rotate90CW	5 = Rotate text 90 degrees clockwise from the current orientation
swTableCellOrientation_Up	2
swTableCellOrientation_Varies	4 = Orientation varies in several table cells; not valid when calling ITableAnnotation::SetCellTextOrientation

 See Also

[SolidWorks.Interop.swconst Namespace](#)

swTableCellRangeIdentifier_e (Type)

SOLIDWORKS API Enumerations

swTableCellRangeIdentifier_e Enumeration

[Send comments on this topic.](#)

[See Also](#)

 [SolidWorks.Interop.swconst Namespace](#) : swTableCellRangeIdentifier_e Enumeration

Table cell-range identifiers.

 Syntax

Visual Basic (Declaration)

```
Public Enum swTableCellRangeIdentifier_e
    Inherits System.Enum
```

Visual Basic (Usage)  Copy Code

```
Dim instance As swTableCellRangeIdentifier\_e
```

C#

```
public enum swTableCellRangeIdentifier_e : System.Enum
```

C++/CLI

```
public enum class swTableCellRangeIdentifier_e : public System.Enum
```

 Members

Member	Description
swTableCellRange_All	-2
swTableCellRange_Current	-1

 See Also

[SolidWorks.Interop.swconst Namespace](#)

swTableColumnTypes_e (Type)

SOLIDWORKS API Enumerations

swTableColumnTypes_e Enumeration

See Also

SolidWorks.Interop.swconst Namespace : swTableColumnTypes_e Enumeration

Table column types.

Syntax

Visual Basic (Declaration)

```
Public Enum swTableColumnTypes_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swTableColumnTypes\_e
```

C#

```
public enum swTableColumnTypes_e : System.Enum
```

C++/CLI

```
public enum class swTableColumnTypes_e : public System.Enum
```

Members

Member	Description
swBendTableColumnType_Angle	503
swBendTableColumnType_BendAllowance	507
swBendTableColumnType_BendOrder	506
swBendTableColumnType_ComplementaryAngle	505
swBendTableColumnType_Direction	502
swBendTableColumnType_InnerRadius	504
swBendTableColumnType_Tag	501
swBomTableColumnType_ComponentReference	207
swBomTableColumnType_CustomProperty	204
swBomTableColumnType_CutListItemName	210
swBomTableColumnType_CutListProperties	209
swBomTableColumnType_Equation	206
swBomTableColumnType_ItemNumber	202
swBomTableColumnType_PartNumber	201
swBomTableColumnType_PLMPProperty	211
swBomTableColumnType_Quantity	203
swBomTableColumnType_ToolboxProperty	208
swBomTableColumnType_UnitOfMeasure	205
swHoleTableColumnType_Quantity	104
swHoleTableColumnType_Size	105
swHoleTableColumnType_Tag	103
swHoleTableColumnType_XLocation	101
swHoleTableColumnType_YLocation	102
swPunchTableColumnType_Angle	605
swPunchTableColumnType_PunchID	603
swPunchTableColumnType_Quantity	604
swPunchTableColumnType_Tag	606
swPunchTableColumnType_XLocation	601
swPunchTableColumnType_YLocation	602
swRevisionTableColumnType_Approved	305
swRevisionTableColumnType_CustomProperties	306
swRevisionTableColumnType_Date	304
swRevisionTableColumnType_Description	303
swRevisionTableColumnType_Revision	302
swRevisionTableColumnType_Zone	301
swTableColumnType_UserDefined	0
swWeldTableColumnType_CustomProperty	404
swWeldTableColumnType_CutListName	403
swWeldTableColumnType_ItemNumber	401
swWeldTableColumnType_Quantity	402

See Also

[SolidWorks.Interop.swconst Namespace](#)

swTableHeaderPosition_e (Type)

SOLIDWORKS API Enumerations

swTableHeaderPosition_e Enumeration

[See Also](#)

 

[SolidWorks.Interop.swconst Namespace](#) : swTableHeaderPosition_e Enumeration

Table header positions.

[Send comments on this topic.](#)

Syntax

Visual Basic (Declaration)

```
Public Enum swTableHeaderPosition_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swTableHeaderPosition\_e
```

C#

```
public enum swTableHeaderPosition_e : System.Enum
```

C++/CLI

```
public enum class swTableHeaderPosition_e : public System.Enum
```

Members

Member	Description
swTableHeader_Bottom	2
swTableHeader_None	0
swTableHeader_Top	1

See Also

[SolidWorks.Interop.swconst Namespace](#)

swTableItemInsertPosition_e (Type)

SOLIDWORKS API Enumerations

swTableItemInsertPosition_e Enumeration

[See Also](#)

[Send comments on this topic.](#)

 

SolidWorks.Interop.swconst Namespace : swTableItemInsertPosition_e Enumeration

Table item insert positions.

Syntax

Visual Basic (Declaration)

```
Public Enum swTableItemInsertPosition_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swTableItemInsertPosition\_e
```

C#

```
public enum swTableItemInsertPosition_e : System.Enum
```

C++/CLI

```
public enum class swTableItemInsertPosition_e : public System.Enum
```

Members

Member	Description
swTableItemInsertPosition_After	3
swTableItemInsertPosition_Before	2
swTableItemInsertPosition_First	1
swTableItemInsertPosition_Last	4
swTableItemMovePosition_Relative	5

See Also

[SolidWorks.Interop.swconst Namespace](#)

swTableMergeLocations_e (Type)

SOLIDWORKS API Enumerations

swTableMergeLocations_e Enumeration

[Send comments on this topic.](#)

[See Also](#)

 

[SolidWorks.Interop.swconst Namespace](#) : swTableMergeLocations_e Enumeration

Table merge locations.

 Syntax

Visual Basic (Declaration)

Public Enum swTableMergeLocations_e
Inherits System.Enum

Visual Basic (Usage)

Dim instance As [swTableMergeLocations_e](#)

 Copy Code

C#

public enum swTableMergeLocations_e : System.Enum

C++/CLI

public enum class swTableMergeLocations_e : public System.Enum

 Members

Member	Description
swTableMerge_All	3
swTableMerge_WithNext	2
swTableMerge_WithPrevious	1

 See Also

[SolidWorks.Interop.swconst Namespace](#)

swTableRowColSizeChangeBehavior_e (Type)

SOLIDWORKS API Enumerations

swTableRowColSizeChangeBehavior_e Enumeration

See Also

[Send comments on this topic.](#)

SolidWorks.Interop.swconst Namespace : swTableRowColSizeChangeBehavior_e Enumeration

Values indicate how the size of the rest of the table should behave when a height of a row or width of a column changes.

Syntax

Visual Basic (Declaration)

Public Enum swTableRowColSizeChangeBehavior_e
Inherits System.Enum

Visual Basic (Usage) Copy Code

Dim instance As [swTableRowColSizeChangeBehavior_e](#)

C#

public enum swTableRowColSizeChangeBehavior_e : System.Enum

C++/CLI

public enum class swTableRowColSizeChangeBehavior_e : public System.Enum

Members

Member	Description
swTableRowColChange_AbsorbedByNext	1 = The next row or column must absorb the change in size so that the entire table size remains the same
swTableRowColChange_AbsorbedByPrevious	2 = The next row or column must absorb the change in size so that the entire table size remains the same
swTableRowColChange_TableSizeCanChange	0 = The remaining rows or columns can shift, so that the entire table width or height changes

See Also

[SolidWorks.Interop.swconst Namespace](#)

swTableSplitDirection_e (Type)

SOLIDWORKS API Enumerations

swTableSplitDirection_e Enumeration

[See Also](#)

 

[SolidWorks.Interop.swconst Namespace](#) : swTableSplitDirection_e Enumeration

Table split directions.

[Send comments on this topic.](#)

Syntax

Visual Basic (Declaration)

Public Enum swTableSplitDirection_e
Inherits System.Enum

Visual Basic (Usage)

Dim instance As [swTableSplitDirection_e](#)

C#

public enum swTableSplitDirection_e : System.Enum

C++/CLI

public enum class swTableSplitDirection_e : public System.Enum

Members

Member	Description
swTableSplit_Horizontal	1
swTableSplit_None	0
swTableSplit_Vertical	2

See Also

[SolidWorks.Interop.swconst Namespace](#)

swTableSplitLocations_e (Type)

SOLIDWORKS API Enumerations

swTableSplitLocations_e Enumeration

[See Also](#)

 

[SolidWorks.Interop.swconst Namespace](#) : swTableSplitLocations_e Enumeration

Table split locations.

[Send comments on this topic.](#)

Syntax

Visual Basic (Declaration)

```
Public Enum swTableSplitLocations_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swTableSplitLocations\_e
```

C#

```
public enum swTableSplitLocations_e : System.Enum
```

C++/CLI

```
public enum class swTableSplitLocations_e : public System.Enum
```

Members

Member	Description
swTableSplit_AfterColumn	4
swTableSplit_AfterRow	2
swTableSplit_BeforeColumn	3
swTableSplit_BeforeRow	1

See Also

[SolidWorks.Interop.swconst Namespace](#)

swTableTagStyle_e (Type)

SOLIDWORKS API Enumerations

swTableTagStyle_e Enumeration

See Also

[Send comments on this topic.](#)

 

[SolidWorks.Interop.swconst Namespace](#) : swTableTagStyle_e Enumeration

Table tag styles

 Syntax

Visual Basic (Declaration)

```
Public Enum swTableTagStyle_e
    Inherits System.Enum
```

Visual Basic (Usage)  Copy Code

```
Dim instance As swTableTagStyle\_e
```

C#

```
public enum swTableTagStyle_e : System.Enum
```

C++/CLI

```
public enum class swTableTagStyle_e : public System.Enum
```

 Members

Member	Description
swTable_AlphaNumericTags	1
swTable_ManualTags	3
swTable_NumericTags	2

 See Also

[SolidWorks.Interop.swconst Namespace](#)

swTabSlotFeatureHeightType_e (Type)

SOLIDWORKS API Enumerations

swTabSlotFeatureHeightType_e Enumeration

See Also

 

[SolidWorks.Interop.swconst Namespace](#) : swTabSlotFeatureHeightType_e Enumeration

Types of tab height calculations in Tab and Slot groups.

[Send comments on this topic.](#)

Syntax

Visual Basic (Declaration)

Public Enum swTabSlotFeatureHeightType_e
Inherits System.Enum

Visual Basic (Usage)

Dim instance As [swTabSlotFeatureHeightType_e](#)

C#

public enum swTabSlotFeatureHeightType_e : System.Enum

C++/CLI

public enum class swTabSlotFeatureHeightType_e : public System.Enum

Members

Member	Description
Blind	0 = Specify a tab height
OffsetFromSurface	2 = Specify an offset and the slot face from which to offset the tab
UpToSurface	1 = The height is calculated internally in reference to the slot face

See Also

[SolidWorks.Interop.swconst Namespace](#)

swTabSlotFeatureSpacingType_e (Type)

SOLIDWORKS API Enumerations

swTabSlotFeatureSpacingType_e Enumeration

See Also

[Send comments on this topic.](#)

 

[SolidWorks.Interop.swconst Namespace](#) : swTabSlotFeatureSpacingType_e Enumeration

Types of spacing between tabs/slots in Tab and Slot groups.

 Syntax

Visual Basic (Declaration)

Public Enum swTabSlotFeatureSpacingType_e
Inherits System.Enum

Visual Basic (Usage)  Copy Code

Dim instance As [swTabSlotFeatureSpacingType_e](#)

C#

public enum swTabSlotFeatureSpacingType_e : System.Enum

C++/CLI

public enum class swTabSlotFeatureSpacingType_e : public System.Enum

 Members

Member	Description
EqualSpacing	0 = Specify the number of instances of tab/slot pairs
SpacingLength	1 = Specify a distance between tabs/slots; the number of instances of tab/slot pairs is calculated internally

 See Also

[SolidWorks.Interop.swconst Namespace](#)

swTangencyType_e (Type)

SOLIDWORKS API Enumerations

swTangencyType_e Enumeration

[Send comments on this topic.](#)

[See Also](#)

 

[SolidWorks.Interop.swconst Namespace](#) : swTangencyType_e Enumeration

Tangency options for lofts and profile twist options for sweeps.

Syntax

Visual Basic (Declaration)

```
Public Enum swTangencyType_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swTangencyType\_e
```

C#

```
public enum swTangencyType_e : System.Enum
```

C++/CLI

```
public enum class swTangencyType_e : public System.Enum
```

Members

Member	Description
swMinimumTwist	10 = Prevents the profile from becoming self-intersecting as it follows the sweep or loft path; valid only for 3D paths; corresponds to Profile Twist > Minimum Twist in the Sweep PropertyManager
swTangencyAllFaces	3 = Makes the adjacent faces tangent at the profile; valid only if swTwistControlType_e is set to swTwistControlFollowPath and only when attaching a sweep or loft to existing geometry; corresponds to Profile Twist > Tangent to Adjacent Faces in the Sweep PropertyManager
swTangencyDirectionVector	2 = Sets a direction plane, planar face, line, edge, cylinder, axis, or a pair of vertices; valid only if swTwistControlType_e is set to swTwistControlFollowPath; corresponds to Profile Twist > Specify Direction Vector in the Sweep PropertyManager
swTangencyNone	0
swTangencyNormalToProfile	1 = Aligns the profile normal to the sweep or loft path; valid only for 2D paths; corresponds to Profile Twist > None in the Sweep PropertyManager

See Also

[SolidWorks.Interop.swconst Namespace](#)

swTangentArcTypes_e (Type)

SOLIDWORKS API Enumerations

swTangentArcTypes_e Enumeration

See Also

[Send comments on this topic.](#)

 

[SolidWorks.Interop.swconst Namespace](#) : swTangentArcTypes_e Enumeration

Tangent arc types.

 Syntax

Visual Basic (Declaration)

Public Enum swTangentArcTypes_e
Inherits System.Enum

Visual Basic (Usage)  Copy Code

Dim instance As [swTangentArcTypes_e](#)

C#

public enum swTangentArcTypes_e : System.Enum

C++/CLI

public enum class swTangentArcTypes_e : public System.Enum

 Members

Member	Description
swBack	3
swForward	1
swLeft	2
swRight	4

 See Also

[SolidWorks.Interop.swconst Namespace](#)

swTangentMagnitudeDirection_e (Type)

SOLIDWORKS API Enumerations

swTangentMagnitudeDirection_e Enumeration

See Also

[Send comments on this topic.](#)

 

[SolidWorks.Interop.swconst Namespace](#) : swTangentMagnitudeDirection_e Enumeration

Tangent magnitude directions.

 Syntax

Visual Basic (Declaration)

Public Enum swTangentMagnitudeDirection_e
Inherits System.Enum

Visual Basic (Usage)  Copy Code

Dim instance As [swTangentMagnitudeDirection_e](#)

C#

public enum swTangentMagnitudeDirection_e : System.Enum

C++/CLI

public enum class swTangentMagnitudeDirection_e : public System.Enum

 Members

Member	Description
swTangentMagnitudeDirection1	1
swTangentMagnitudeDirection2	2

 See Also

[SolidWorks.Interop.swconst Namespace](#)