

SOLIDWORKS Enumerations (swconst) —
Reference (15/17): swTaperedTapCustomSizing_e-
swUserPreferenceDoubleValue_e

SOLIDWORKS API Documentation (converted from CHM)

swTaperedTapCustomSizing_e (Type)

SOLIDWORKS API Enumerations

swTaperedTapCustomSizing_e Enumeration

[See Also](#)

 

[SolidWorks.Interop.swconst Namespace](#) : swTaperedTapCustomSizing_e Enumeration

Custom sizing options for tapered tap elements of the Advanced Hole.

[Send comments on this topic.](#)

Syntax

Visual Basic (Declaration)

```
Public Enum swTaperedTapCustomSizing_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swTaperedTapCustomSizing\_e
```

C#

```
public enum swTaperedTapCustomSizing_e : System.Enum
```

C++/CLI

```
public enum class swTaperedTapCustomSizing_e : public System.Enum
```

Members

Member	Description
swTaperedTapCustomSizing_MajorDiameter	2
swTaperedTapCustomSizing_MinorDiameterWithCosmeticThread	1

See Also

[SolidWorks.Interop.swconst Namespace](#)

swTaperedTapThreadClass_e (Type)

SOLIDWORKS API Enumerations

swTaperedTapThreadClass_e Enumeration

See Also

[Send comments on this topic.](#)

 

[SolidWorks.Interop.swconst Namespace](#) : swTaperedTapThreadClass_e Enumeration

Thread classes for tapered tap hole elements of the Advanced Hole.

 Syntax

Visual Basic (Declaration)

```
Public Enum swTaperedTapThreadClass_e
    Inherits System.Enum
```

Visual Basic (Usage)  Copy Code

```
Dim instance As swTaperedTapThreadClass\_e
```

C#

```
public enum swTaperedTapThreadClass_e : System.Enum
```

C++/CLI

```
public enum class swTaperedTapThreadClass_e : public System.Enum
```

 Members

Member	Description
swTaperedTapThreadClass_1	1
swTaperedTapThreadClass_2	2

 See Also

[SolidWorks.Interop.swconst Namespace](#)

swTaskPaneBitmapsOptions_e (Type)

SOLIDWORKS API Enumerations

swTaskPaneBitmapsOptions_e Enumeration

[Send comments on this topic.](#)

[See Also](#)

 [SolidWorks.Interop.swconst Namespace](#) : swTaskPaneBitmapsOptions_e Enumeration

SOLIDWORKS standard Task Pane toolbar bitmap buttons .

Syntax

Visual Basic (Declaration)

```
Public Enum swTaskPaneBitmapsOptions_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swTaskPaneBitmapsOptions\_e
```

C#

```
public enum swTaskPaneBitmapsOptions_e : System.Enum
```

C++/CLI

```
public enum class swTaskPaneBitmapsOptions_e : public System.Enum
```

Members

Member	Description
swTaskPaneBitmapsOptions_Back	5
swTaskPaneBitmapsOptions_Close	1
swTaskPaneBitmapsOptions_Help	2
swTaskPaneBitmapsOptions_Next	4
swTaskPaneBitmapsOptions_Ok	3
swTaskPaneBitmapsOptions_Options	6

See Also

[SolidWorks.Interop.swconst Namespace](#)

swTaskPaneNotify_e (Type)

SOLIDWORKS API Enumerations

swTaskPaneNotify_e Enumeration

See Also

[SolidWorks.Interop.swconst Namespace](#) : swTaskPaneNotify_e Enumeration

Task Pane notifications.

[Send comments on this topic.](#)

Syntax

Visual Basic (Declaration)

```
Public Enum swTaskPaneNotify_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swTaskPaneNotify\_e
```

C#

```
public enum swTaskPaneNotify_e : System.Enum
```

C++/CLI

```
public enum class swTaskPaneNotify_e : public System.Enum
```

Members

Member	Description
swAppTaskPaneActivateNotify	1 = ActivateNotify
swAppTaskPaneDeactivateNotify	2 = DeactivateNotify
swAppTaskPaneDestroyNotify	3 = DestroyNotify
swAppTaskPaneToolBarButtonClicked	4 = ToolBarButtonClicked

Remarks

To receive notifications, a DLL application must register for the notifications by object type. This registration must be done for each instance of a particular object.

For example, in the file in the Visual C++ 6.0 wizard-generated add-in that supports Task Pane events (e.g., Taskpane.h, include:

```
DECLARE_REGISTRY_RESOURCEID(IDR_TaskPane)

BEGIN_SINK_MAP(CTaskPane)

    SINK_ENTRY_EX(ID_TASKPANE_EVENTS, DIID_DTaskpaneViewEvents,
        swAppTaskPaneDestroyNotify, DestroyNotify)

    SINK_ENTRY_EX(ID_TASKPANE_EVENTS, DIID_DTaskpaneViewEvents,
        swAppTaskPaneActivateNotify, ActivateNotify)

    SINK_ENTRY_EX(ID_TASKPANE_EVENTS, DIID_DTaskpaneViewEvents,
        swAppTaskPaneDeactivateNotify, DeActivateNotify)

END_SINK_MAP()
```

If developing a C++ application, use these enumerators to [register for notifications](#) for the [ITaskpaneView](#) events.

See Also

[SolidWorks.Interop.swconst Namespace](#)

swTaskPaneTab_e (Type)

SOLIDWORKS API Enumerations

swTaskPaneTab_e Enumeration

See Also

[Send comments on this topic.](#)

 [SolidWorks.Interop.swconst Namespace](#) : swTaskPaneTab_e Enumeration

Task Pane tabs.

 Syntax

Visual Basic (Declaration)

Public Enum swTaskPaneTab_e
Inherits System.Enum

Visual Basic (Usage)

Dim instance As [swTaskPaneTab_e](#)

C#

public enum swTaskPaneTab_e : System.Enum

C++/CLI

public enum class swTaskPaneTab_e : public System.Enum

 Members

Member	Description
swClipBoard	4 = Clipboard tab
swCustomProps	5 = Custom Properties tab
swDesignLibrary	1 = Design Library tab
swFileExplorer	2 = File Explorer tab
swPnID	6 = P&ID tab
swResources	3 = SOLIDWORKS Resources tab

 See Also

[SolidWorks.Interop.swconst Namespace](#)

swTaskpaneViewStatus_e (Type)

SOLIDWORKS API Enumerations

swTaskpaneViewStatus_e Enumeration

[See Also](#)

 

[SolidWorks.Interop.swconst Namespace](#) : swTaskpaneViewStatus_e Enumeration

Task Pane view statuses.

[Send comments on this topic.](#)

Syntax

Visual Basic (Declaration)

```
Public Enum swTaskpaneViewStatus_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swTaskpaneViewStatus\_e
```

C#

```
public enum swTaskpaneViewStatus_e : System.Enum
```

C++/CLI

```
public enum class swTaskpaneViewStatus_e : public System.Enum
```

Members

Member	Description
swTaskpaneView_CreationFailure	-1
swTaskpaneView_Okay	0
swTaskpaneView_UnsupportedHandler	1

See Also

[SolidWorks.Interop.swconst Namespace](#)

swTempBodySelectOptions_e (Type)

SOLIDWORKS API Enumerations

swTempBodySelectOptions_e Enumeration

See Also

 

SolidWorks.Interop.swconst Namespace : swTempBodySelectOptions_e Enumeration

Temporary body selection options.

[Send comments on this topic.](#)

Syntax

Visual Basic (Declaration)

```
Public Enum swTempBodySelectOptions_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swTempBodySelectOptions\_e
```

C#

```
public enum swTempBodySelectOptions_e : System.Enum
```

C++/CLI

```
public enum class swTempBodySelectOptions_e : public System.Enum
```

Members

Member	Description
swTempBodySelectable	1
swTempBodySelectOptionNone	0

See Also

[SolidWorks.Interop.swconst Namespace](#)

swTessellationMatchType_e (Type)

SOLIDWORKS API Enumerations

swTessellationMatchType_e Enumeration

See Also

▼

SolidWorks.Interop.swconst Namespace : swTessellationMatchType_e Enumeration

Tessellation match types.

[Send comments on this topic.](#)

Syntax

Visual Basic (Declaration)

```
Public Enum swTessellationMatchType_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swTessellationMatchType\_e
```

C#

```
public enum swTessellationMatchType_e : System.Enum
```

C++/CLI

```
public enum class swTessellationMatchType_e : public System.Enum
```

Members

Member	Description
swTessellationMatchEdgeCurve	2 = Clipping facet boundaries to model edge curves
swTessellationMatchFacetGeometry	1 = Clipping facet boundaries to a common edge
swTessellationMatchFacetTopology	0 = Matching facet vertices across a common edge

See Also

[SolidWorks.Interop.swconst Namespace](#)

swTextAlignmentVertical_e (Type)

SOLIDWORKS API Enumerations

swTextAlignmentVertical_e Enumeration

See Also

[Send comments on this topic.](#)

 

[SolidWorks.Interop.swconst Namespace](#) : swTextAlignmentVertical_e Enumeration

Vertical text alignment options.

 Syntax

Visual Basic (Declaration)

```
Public Enum swTextAlignmentVertical_e
    Inherits System.Enum
```

Visual Basic (Usage)  Copy Code

```
Dim instance As swTextAlignmentVertical\_e
```

C#

```
public enum swTextAlignmentVertical_e : System.Enum
```

C++/CLI

```
public enum class swTextAlignmentVertical_e : public System.Enum
```

 Members

Member	Description
swTextAlignmentBottom	2
swTextAlignmentMiddle	1
swTextAlignmentTop	0

 See Also

[SolidWorks.Interop.swconst Namespace](#)

swTextInBoxStyle_e (Type)

SOLIDWORKS API Enumerations

swTextInBoxStyle_e Enumeration

See Also

 

[SolidWorks.Interop.swconst Namespace](#) : swTextInBoxStyle_e Enumeration

Text in box styles.

[Send comments on this topic.](#)

Syntax

Visual Basic (Declaration)

```
Public Enum swTextInBoxStyle_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swTextInBoxStyle\_e
```

C#

```
public enum swTextInBoxStyle_e : System.Enum
```

C++/CLI

```
public enum class swTextInBoxStyle_e : public System.Enum
```

Members

Member	Description
swTextInBoxStyleFit	2
swTextInBoxStyleNone	0
swTextInBoxStyleWrap	1

See Also

[SolidWorks.Interop.swconst Namespace](#)

swTextJustification_e (Type)

SOLIDWORKS API Enumerations

swTextJustification_e Enumeration

See Also

▼

SolidWorks.Interop.swconst Namespace : swTextJustification_e Enumeration

Text justifications options.

[Send comments on this topic.](#)

 Syntax

Visual Basic (Declaration)

Public Enum swTextJustification_e
Inherits System.Enum

Visual Basic (Usage)

Dim instance As [swTextJustification_e](#)

C#

public enum swTextJustification_e : System.Enum

C++/CLI

public enum class swTextJustification_e : public System.Enum



 Members

Member	Description
swTextJustificationCenter	2 = Text is center-justified
swTextJustificationLeft	1 = Text is left-justified
swTextJustificationNone	0 = No text justification
swTextJustificationRight	3 = Text is right-justified

 See Also

[SolidWorks.Interop.swconst Namespace](#)

swTextPosition_e (Type)

SOLIDWORKS API Enumerations

swTextPosition_e Enumeration

See Also

[Send comments on this topic.](#)

 [SolidWorks.Interop.swconst Namespace](#) : swTextPosition_e Enumeration

Values for text reference point position types.

 Syntax

Visual Basic (Declaration)

Public Enum swTextPosition_e
Inherits System.Enum

Visual Basic (Usage)

Dim instance As [swTextPosition_e](#)



C#

public enum swTextPosition_e : System.Enum

C++/CLI

public enum class swTextPosition_e : public System.Enum

 Members

Member	Description
swCENTER	2
swLOWER_LEFT	1
swLOWER_RIGHT	4
swUPPER_CENTER	5
swUPPER_LEFT	0
swUPPER_RIGHT	3

 See Also

[SolidWorks.Interop.swconst Namespace](#)

swTextSize_e (Type)

SOLIDWORKS API Enumerations

swTextSize_e Enumeration

See Also

[Send comments on this topic.](#)

 

SolidWorks.Interop.swconst Namespace : swTextSize_e Enumeration

Toolbar text sizes.

 Syntax

Visual Basic (Declaration)

Public Enum swTextSize_e
Inherits System.Enum

Visual Basic (Usage)  Copy Code

Dim instance As [swTextSize_e](#)

C#

public enum swTextSize_e : System.Enum

C++/CLI

public enum class swTextSize_e : public System.Enum

 Members

Member	Description
swTextSize_Large	2
swTextSize_Medium	1
swTextSize_Small	0

 See Also

[SolidWorks.Interop.swconst Namespace](#)

swTextureRenderModes_e (Type)

SOLIDWORKS API Enumerations

swTextureRenderModes_e Enumeration

[See Also](#)

 

[SolidWorks.Interop.swconst Namespace](#) : swTextureRenderModes_e Enumeration

Texture render modes.

[Send comments on this topic.](#)

Syntax

Visual Basic (Declaration)

```
Public Enum swTextureRenderModes_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swTextureRenderModes\_e
```

C#

```
public enum swTextureRenderModes_e : System.Enum
```

C++/CLI

```
public enum class swTextureRenderModes_e : public System.Enum
```

Members

Member	Description
swTextureRenderModeBlend	1
swTextureRenderModeImage	0
swTextureRenderModeLuminance	2

See Also

[SolidWorks.Interop.swconst Namespace](#)

swThickenDirection_e (Type)

SOLIDWORKS API Enumerations

swThickenDirection_e Enumeration

[See Also](#)

[Send comments on this topic.](#)

 

[SolidWorks.Interop.swconst Namespace](#) : swThickenDirection_e Enumeration

Direction in which to thicken sheet bodies.

 Syntax

Visual Basic (Declaration)

```
Public Enum swThickenDirection_e
    Inherits System.Enum
```

Visual Basic (Usage)  [Copy Code](#)

```
Dim instance As swThickenDirection\_e
```

C#

```
public enum swThickenDirection_e : System.Enum
```

C++/CLI

```
public enum class swThickenDirection_e : public System.Enum
```

 Members

Member	Description
swThickenDirection_Both	2
swThickenDirection_Side1	0
swThickenDirection_Side2	1

 See Also

[SolidWorks.Interop.swconst Namespace](#)

swThickenThicknessType_e (Type)

SOLIDWORKS API Enumerations

swThickenThicknessType_e Enumeration

See Also

 

[SolidWorks.Interop.swconst Namespace](#) : swThickenThicknessType_e Enumeration

Thicken thickness directions.

[Send comments on this topic.](#)

Syntax

Visual Basic (Declaration)

Public Enum swThickenThicknessType_e
Inherits System.Enum

Visual Basic (Usage)

Dim instance As [swThickenThicknessType_e](#)

C#

public enum swThickenThicknessType_e : System.Enum

C++/CLI

public enum class swThickenThicknessType_e : public System.Enum

Members

Member	Description
swThickenSideBoth	2
swThickenSideOne	0
swThickenSideTwo	1

See Also

[SolidWorks.Interop.swconst Namespace](#)

swThinWallType_e (Type)

SOLIDWORKS API Enumerations

swThinWallType_e Enumeration

See Also

[Send comments on this topic.](#)

 

[SolidWorks.Interop.swconst Namespace](#) : swThinWallType_e Enumeration

Thin wall types.

 Syntax

Visual Basic (Declaration)

Public Enum swThinWallType_e
Inherits System.Enum

Visual Basic (Usage)  Copy Code

Dim instance As [swThinWallType_e](#)

C#

public enum swThinWallType_e : System.Enum

C++/CLI

public enum class swThinWallType_e : public System.Enum

 Members

Member	Description
swThinWallMidPlane	2
swThinWallOneDirection	0
swThinWallOppDirection	1
swThinWallTwoDirection	3

 See Also

[SolidWorks.Interop.swconst Namespace](#)

swThreadEndCondition_e (Type)

SOLIDWORKS API Enumerations

swThreadEndCondition_e Enumeration

See Also

[Send comments on this topic.](#)

 

[SolidWorks.Interop.swconst Namespace](#) : swThreadEndCondition_e Enumeration

Thread end conditions.

 Syntax

Visual Basic (Declaration)

Public Enum swThreadEndCondition_e
Inherits System.Enum

Visual Basic (Usage)  Copy Code

Dim instance As [swThreadEndCondition_e](#)

C#

public enum swThreadEndCondition_e : System.Enum

C++/CLI

public enum class swThreadEndCondition_e : public System.Enum

 Members

Member	Description
swThreadEndCondition_Blind	0
swThreadEndCondition_Revolutions	1
swThreadEndCondition_UpToSelection	2

 See Also

[SolidWorks.Interop.swconst Namespace](#)

swThreadMethod_e (Type)

SOLIDWORKS API Enumerations

swThreadMethod_e Enumeration

[See Also](#)

 

[SolidWorks.Interop.swconst Namespace](#) : swThreadMethod_e Enumeration

Thread feature types.

[Send comments on this topic.](#)

Syntax

Visual Basic (Declaration)

```
Public Enum swThreadMethod_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swThreadMethod\_e
```

C#

```
public enum swThreadMethod_e : System.Enum
```

C++/CLI

```
public enum class swThreadMethod_e : public System.Enum
```

Members

Member	Description
swThreadMethod_Cut	0
swThreadMethod_Extrude	1

See Also

[SolidWorks.Interop.swconst Namespace](#)

swThreadMirrorType_e (Type)

SOLIDWORKS API Enumerations

swThreadMirrorType_e Enumeration

See Also

[Send comments on this topic.](#)

 

[SolidWorks.Interop.swconst Namespace](#) : swThreadMirrorType_e Enumeration

Thread mirror profiles.

 Syntax

Visual Basic (Declaration)

Public Enum swThreadMirrorType_e
Inherits System.Enum

Visual Basic (Usage)  Copy Code

Dim instance As [swThreadMirrorType_e](#)

C#

public enum swThreadMirrorType_e : System.Enum

C++/CLI

public enum class swThreadMirrorType_e : public System.Enum

 Members

Member	Description
swThreadMirrorType_Horizontally	0
swThreadMirrorType_Vertically	1

 See Also

[SolidWorks.Interop.swconst Namespace](#)

swTiffCompressionScheme_e (Type)

SOLIDWORKS API Enumerations

swTiffCompressionScheme_e Enumeration

See Also

 

[SolidWorks.Interop.swconst Namespace](#) : swTiffCompressionScheme_e Enumeration

TIFF compression schemes.

[Send comments on this topic.](#)

Syntax

Visual Basic (Declaration)

```
Public Enum swTiffCompressionScheme_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swTiffCompressionScheme\_e
```

C#

```
public enum swTiffCompressionScheme_e : System.Enum
```

C++/CLI

```
public enum class swTiffCompressionScheme_e : public System.Enum
```

Members

Member	Description
swTiffGroup4FaxCompression	2
swTiffPackbitsCompression	1
swTiffUncompressed	0

See Also

[SolidWorks.Interop.swconst Namespace](#)

swTiffImageType_e (Type)

[SolidWorks.Interop.swconst Namespace](#) : swTiffImageType_e Enumeration

TIFF image types.

Syntax

Visual Basic (Declaration)

```
Public Enum swTiffImageType_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swTiffImageType\_e
```

C#

```
public enum swTiffImageType_e : System.Enum
```

C++/CLI

```
public enum class swTiffImageType_e : public System.Enum
```

Members

Member	Description
swTiffImageBlackAndWhite	0
swTiffImageGrayScale	2
swTiffImageRGB	1
swTiffImageRGBA	3

See Also

[SolidWorks.Interop.swconst Namespace](#)

swTolerances_e (Type)

SOLIDWORKS API Enumerations

swTolerances_e Enumeration

See Also

[Send comments on this topic.](#)

 

[SolidWorks.Interop.swconst Namespace](#) : swTolerances_e Enumeration

Tolerance types.

 Syntax

Visual Basic (Declaration)

Public Enum swTolerances_e
Inherits System.Enum

Visual Basic (Usage)  Copy Code

Dim instance As [swTolerances_e](#)

C#

public enum swTolerances_e : System.Enum

C++/CLI

public enum class swTolerances_e : public System.Enum

 Members

Member	Description
swBSCurveNonRationalOutputTol	1 = 3D nonrational b-spline curve output tolerance (meters)
swBSCurveOutputTol	0 = 3D b-spline curve output tolerance (meters)
swCurveChordTessellationTol	5 = Chord tolerance or deviation for tessellation for curves
swSurfAngularTessellationTol	4 = Angular tolerance or deviation for tessellation for surfaces
swSurfChordTessellationTol	3 = Chord tolerance or deviation for tessellation for surfaces
swUVCurveOutputTol	2 = 2D trim curve output tolerance (fraction of characteristic minimum face dimension)

 See Also

[SolidWorks.Interop.swconst Namespace](#)

swToleranceZoneModifier_e (Type)

SOLIDWORKS API Enumerations

swToleranceZoneModifier_e Enumeration

[See Also](#)

 

[SolidWorks.Interop.swconst Namespace](#) : swToleranceZoneModifier_e Enumeration

Tolerance zone modifiers.

[Send comments on this topic.](#)

Syntax

Visual Basic (Declaration)

Public Enum swToleranceZoneModifier_e
Inherits System.Enum

Visual Basic (Usage)

Dim instance As [swToleranceZoneModifier_e](#)

C#

public enum swToleranceZoneModifier_e : System.Enum

C++/CLI

public enum class swToleranceZoneModifier_e : public System.Enum

Members

Member	Description
swToleranceZoneModifier_Diameter	2 = Cylindrical or circular tolerance zone
swToleranceZoneModifier_None	0
swToleranceZoneModifier_SphericalDiameter	3 = Spherical tolerance zone
swToleranceZoneModifier_Unknown	1

See Also

[SolidWorks.Interop.swconst Namespace](#)

swTolType_e (Type)

SOLIDWORKS API Enumerations

swTolType_e Enumeration

See Also

[Send comments on this topic.](#)

 [SolidWorks.Interop.swconst Namespace](#) : swTolType_e Enumeration

Dimension tolerance types.

Syntax

Visual Basic (Declaration)

```
Public Enum swTolType_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swTolType\_e
```

C#

```
public enum swTolType_e : System.Enum
```

C++/CLI

```
public enum class swTolType_e : public System.Enum
```

Members

Member	Description
swTolBASIC	1
swTolBILAT	2
swTolBLOCK	10
swTolFIT	7
swTolFITTOLONLY	9
swTolFITWITHTOL	8
swTolGeneral	11
swTolLIMIT	3
swTolMAX	6
swTolMETRIC	7
swTolMIN	5
swTolNONE	0
swTolSYMMETRIC	4

See Also

[SolidWorks.Interop.swconst Namespace](#)

swToolbar_e (Type)

SOLIDWORKS API Enumerations

swToolbar_e Enumeration

See Also

Send comments on this topic.

SolidWorks.Interop.swconst Namespace : swToolbar_e Enumeration

Toolbar identifiers.

Syntax

Visual Basic (Declaration)

```
Public Enum swToolbar_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swToolbar_e
```

C#

```
public enum swToolbar_e : System.Enum
```

C++/CLI

```
public enum class swToolbar_e : public System.Enum
```

Members

Member	Description
sw2Dto3DToolbar	24
swAlignToolbar	22
swAnimationPaneToolbar	36
swAnnotationToolbar	9
swAssemblyToolbar	7
swBlocksToolbar	29
swConfigurationToolbar	41
swContextToolbar	28
swCurvesToolbar	18
swDimXpertToolbar	33
swDisplayStatesToolbar	42
swDrawingToolbar	8
swFeatureToolbar	11
swFontToolbar	12
swLayerToolbar	23
swLayoutToolbar	38
swLineToolbar	13
swMacroToolbar	5
swMainToolbar	1
swMoldToolsToolbar	19
swOfficeToolbar	32
swQuickSnapToolbar	31
swReferenceGeometryToolbar	15
swRenderToolbar	39
swRoutingToolbar	25
swScreenCaptureToolbar	37
swSelectionFilterToolbar	14
swSheetFormatToolbar	40
swSheetMetalToolbar	20
swSimulationToolbar	26
swSketchRelationsToolbar	4
swSketchToolbar	6
swSketchToolsToolbar	0
swSOLIDWORKSMBDToolbars	43
swSplineToolbar	27
swStandardToolbar	2
swStandardViewsToolbar	16
swSurfacesToolbar	21
swTableToolbar	34
swTaskPaneToolbar	30; call ISldWorks::SetToolbarVisibility to show or hide the SOLIDWORKS Task Pane
swToiXpertToolbar	33
swToolsToolbar	17
swViewToolbar	3
swWebToolbar	10
swWeldmentToolbar	35

See Also

[SolidWorks.Interop.swconst Namespace](#)

swToolBarDockStatePosition_e (Type)

SOLIDWORKS API Enumerations

swToolBarDockStatePosition_e Enumeration

See Also

[Send comments on this topic.](#)

 

[SolidWorks.Interop.swconst Namespace](#) : swToolBarDockStatePosition_e Enumeration

Toolbar docking positions.

 Syntax

Visual Basic (Declaration)

Public Enum swToolBarDockStatePosition_e
Inherits System.Enum

Visual Basic (Usage)  [Copy Code](#)

Dim instance As [swToolBarDockStatePosition_e](#)

C#

public enum swToolBarDockStatePosition_e : System.Enum

C++/CLI

public enum class swToolBarDockStatePosition_e : public System.Enum

 Members

Member	Description
swDockBottom	2
swDockLeft	4
swDockNoToolbar	-1
swDockRight	3
swDockTop	1
swNoDock	0

 See Also

[SolidWorks.Interop.swconst Namespace](#)

swToolBarLayoutOption_e (Type)

SOLIDWORKS API Enumerations

swToolBarLayoutOption_e Enumeration

[See Also](#)

 

[SolidWorks.Interop.swconst Namespace](#) : swToolBarLayoutOption_e Enumeration

Toolbar layout options for saving SOLIDWORKS settings.

[Send comments on this topic.](#)

Syntax

Visual Basic (Declaration)

```
Public Enum swToolBarLayoutOption_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swToolBarLayoutOption\_e
```

C#

```
public enum swToolBarLayoutOption_e : System.Enum
```

C++/CLI

```
public enum class swToolBarLayoutOption_e : public System.Enum
```

Members

Member	Description
swToolBarLayoutOption_AllToolbars	1
swToolBarLayoutOption_MacroToolbarOnly	2
swToolBarLayoutOption_None	0

See Also

[SolidWorks.Interop.swconst Namespace](#)

swToolbarStates_e (Type)

SOLIDWORKS API Enumerations

swToolbarStates_e Enumeration

See Also

[Send comments on this topic.](#)

 

[SolidWorks.Interop.swconst Namespace](#) : swToolbarStates_e Enumeration

Toolbar states.

 Syntax

Visual Basic (Declaration)

Public Enum swToolbarStates_e
Inherits System.Enum

Visual Basic (Usage)  [Copy Code](#)

Dim instance As [swToolbarStates_e](#)

C#

public enum swToolbarStates_e : System.Enum

C++/CLI

public enum class swToolbarStates_e : public System.Enum

 Members

Member	Description
swToolbarHidden	0

 See Also

[SolidWorks.Interop.swconst Namespace](#)

swToolBoxPartType_e (Type)

SOLIDWORKS API Enumerations

swToolBoxPartType_e Enumeration

See Also

 

[SolidWorks.Interop.swconst Namespace](#) : swToolBoxPartType_e Enumeration

Toolbox part types. [Bitmask](#).

[Send comments on this topic.](#)

Syntax

Visual Basic (Declaration)

Public Enum swToolBoxPartType_e
Inherits System.Enum

Visual Basic (Usage)

Dim instance As [swToolBoxPartType_e](#)

C#

public enum swToolBoxPartType_e : System.Enum

C++/CLI

public enum class swToolBoxPartType_e : public System.Enum

Members

Member	Description
swNotAToolboxPart	0x0 = Not a Toolbox part
swToolboxCopiedPart	0x2 = Copied part
swToolboxStandardPart	0x1 = Standard part

See Also

[SolidWorks.Interop.swconst Namespace](#)

swToolBoxPropertyName_e (Type)

SOLIDWORKS API Enumerations

swToolBoxPropertyName_e Enumeration

See Also

 

[SolidWorks.Interop.swconst Namespace](#) : swToolBoxPropertyName_e Enumeration

Toolbox properties.

[Send comments on this topic.](#)

 Syntax

Visual Basic (Declaration)

Public Enum swToolBoxPropertyName_e
Inherits System.Enum

Visual Basic (Usage)

Dim instance As [swToolBoxPropertyName_e](#)

C#

public enum swToolBoxPropertyName_e : System.Enum

C++/CLI

public enum class swToolBoxPropertyName_e : public System.Enum

 Members

Member	Description
swToolBoxPropertyName_PartName	0
swToolBoxPropertyName_Specification	1
swToolBoxPropertyName_Standard	2

 See Also

[SolidWorks.Interop.swconst Namespace](#)

swTopoEntity_e (Type)

SOLIDWORKS API Enumerations

swTopoEntity_e Enumeration

See Also

[Send comments on this topic.](#)

 

[SolidWorks.Interop.swconst Namespace](#) : swTopoEntity_e Enumeration

Types of topological entities.

 Syntax

Visual Basic (Declaration)

```
Public Enum swTopoEntity_e
    Inherits System.Enum
```

Visual Basic (Usage)  Copy Code

```
Dim instance As swTopoEntity\_e
```

C#

```
public enum swTopoEntity_e : System.Enum
```

C++/CLI

```
public enum class swTopoEntity_e : public System.Enum
```

 Members

Member	Description
swTopoBody	6
swTopoEdge	2
swTopoFace	4
swTopoLoop	3
swTopoRegion	7
swTopoShell	5
swTopoVertex	1

 See Also

[SolidWorks.Interop.swconst Namespace](#)

swTopology_e (Type)

SOLIDWORKS API Enumerations

swTopology_e Enumeration

See Also

[Send comments on this topic.](#)

 

[SolidWorks.Interop.swconst Namespace](#) : swTopology_e Enumeration

Types of bodies.

 Syntax

Visual Basic (Declaration)

```
Public Enum swTopology_e
    Inherits System.Enum
```

Visual Basic (Usage)  Copy Code

```
Dim instance As swTopology\_e
```

C#

```
public enum swTopology_e : System.Enum
```

C++/CLI

```
public enum class swTopology_e : public System.Enum
```

 Members

Member	Description
swTopoMinimumBody	4
swTopoSheetBody	2
swTopoSolidBody	1
swTopoWireBody	3

 See Also

[SolidWorks.Interop.swconst Namespace](#)

swTopologyTypes_e (Type)

SOLIDWORKS API Enumerations

swTopologyTypes_e Enumeration

See Also

 

[SolidWorks.Interop.swconst Namespace](#) : swTopologyTypes_e Enumeration

Types of topology.

[Send comments on this topic.](#)

 Syntax

Visual Basic (Declaration)

```
Public Enum swTopologyTypes_e
    Inherits System.Enum
```

Visual Basic (Usage)   Copy Code

```
Dim instance As swTopologyTypes\_e
```

C#

```
public enum swTopologyTypes_e : System.Enum
```

C++/CLI

```
public enum class swTopologyTypes_e : public System.Enum
```

 Members

Member	Description
swTopologyCoEdge	1
swTopologyNull	0
swTopologyVertex	2

 See Also

[SolidWorks.Interop.swconst Namespace](#)

swTrackingIDError_e (Type)

SOLIDWORKS API Enumerations

swTrackingIDError_e Enumeration

See Also

[Send comments on this topic.](#)

 

[SolidWorks.Interop.swconst Namespace](#) : swTrackingIDError_e Enumeration

Tracking ID errors.

 Syntax

Visual Basic (Declaration)

```
Public Enum swTrackingIDError_e
    Inherits System.Enum
```

Visual Basic (Usage)  Copy Code

```
Dim instance As swTrackingIDError\_e
```

C#

```
public enum swTrackingIDError_e : System.Enum
```

C++/CLI

```
public enum class swTrackingIDError_e : public System.Enum
```

 Members

Member	Description
swTrackingIDError_InvalidTrackingCookie	2
swTrackingIDError_InvalidTrackingID	3
swTrackingIDError_NoError	0
swTrackingIDError_UnknownError	1
swTrackingIDError_UntrackableObject	4
swTrackingIDError_UntrackedObject	5

 See Also

[SolidWorks.Interop.swconst Namespace](#)

swTranslationNotifyOptions_e (Type)

SOLIDWORKS API Enumerations

swTranslationNotifyOptions_e Enumeration

See Also

[Send comments on this topic.](#)

 

[SolidWorks.Interop.swconst Namespace](#) : swTranslationNotifyOptions_e Enumeration

Translation notification options. [Bitmask](#).

 Syntax

Visual Basic (Declaration)

```
Public Enum swTranslationNotifyOptions_e
    Inherits System.Enum
```

Visual Basic (Usage)  [Copy Code](#)

```
Dim instance As swTranslationNotifyOptions\_e
```

C#

```
public enum swTranslationNotifyOptions_e : System.Enum
```

C++/CLI

```
public enum class swTranslationNotifyOptions_e : public System.Enum
```

 Members

Member	Description
swTranslationNotifySilentMode	1 or 0x1

 See Also

[SolidWorks.Interop.swconst Namespace](#)

swTransparencyState_e (Type)

SOLIDWORKS API Enumerations

swTransparencyState_e Enumeration

See Also

[Send comments on this topic.](#)

 

SolidWorks.Interop.swconst Namespace : swTransparencyState_e Enumeration

Transparency states.

 Syntax

Visual Basic (Declaration)

Public Enum swTransparencyState_e
Inherits System.Enum

Visual Basic (Usage)  Copy Code

Dim instance As [swTransparencyState_e](#)

C#

public enum swTransparencyState_e : System.Enum

C++/CLI

public enum class swTransparencyState_e : public System.Enum

 Members

Member	Description
swTransparencyStateNonTransparent	1
swTransparencyStateTransparent	0
swTransparencyStateUnknown	-1

 See Also

[SolidWorks.Interop.swconst Namespace](#)

swTreeControlItemType_e (Type)

SOLIDWORKS API Enumerations

swTreeControlItemType_e Enumeration

See Also

[Send comments on this topic.](#)

 

[SolidWorks.Interop.swconst Namespace](#) : swTreeControlItemType_e Enumeration

Tree control item types.

 Syntax

Visual Basic (Declaration)

Public Enum swTreeControlItemType_e
Inherits System.Enum

Visual Basic (Usage)  Copy Code

Dim instance As [swTreeControlItemType_e](#)

C#

public enum swTreeControlItemType_e : System.Enum

C++/CLI

public enum class swTreeControlItemType_e : public System.Enum

 Members

Member	Description
swFeatureManagerItem_Component	2
swFeatureManagerItem_Feature	1
swFeatureManagerItem_Unsupported	0

 See Also

[SolidWorks.Interop.swconst Namespace](#)

swTriadManipulatorControlPoints_e (Type)

SOLIDWORKS API Enumerations

swTriadManipulatorControlPoints_e Enumeration

See Also

 

[SolidWorks.Interop.swconst Namespace](#) : swTriadManipulatorControlPoints_e Enumeration

Triad manipulator control points.

[Send comments on this topic.](#)

Syntax

Visual Basic (Declaration)

```
Public Enum swTriadManipulatorControlPoints_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swTriadManipulatorControlPoints\_e
```

C#

```
public enum swTriadManipulatorControlPoints_e : System.Enum
```

C++/CLI

```
public enum class swTriadManipulatorControlPoints_e : public System.Enum
```

Members

Member	Description
swTriadManipulatorOrigin	0 = Origin index
swTriadManipulatorXAxis	1 = x arrow index
swTriadManipulatorXYPlane	4 = xy plane index
swTriadManipulatorYAxis	2 = y arrow index
swTriadManipulatorYZPlane	5 = yz plane index
swTriadManipulatorZAxis	3 = z arrow index
swTriadManipulatorZXPlane	6 = zx plane index

See Also

[SolidWorks.Interop.swconst Namespace](#)

swTriadManipulatorDoNotShow_e (Type)

SOLIDWORKS API Enumerations

swTriadManipulatorDoNotShow_e Enumeration

See Also

 

[SolidWorks.Interop.swconst Namespace](#) : swTriadManipulatorDoNotShow_e Enumeration

Triad manipulator visibility options. [Bitmask](#).

[Send comments on this topic.](#)

Syntax

Visual Basic (Declaration)

```
Public Enum swTriadManipulatorDoNotShow_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swTriadManipulatorDoNotShow\_e
```

C#

```
public enum swTriadManipulatorDoNotShow_e : System.Enum
```

C++/CLI

```
public enum class swTriadManipulatorDoNotShow_e : public System.Enum
```

Members

Member	Description
swTriadManipulatorDoNotShowOrigin	1 or 0x1; Not used.
swTriadManipulatorDoNotShowXAxis	2 or 0x2; Do not show x axis
swTriadManipulatorDoNotShowXYPlane	16 or 0x10; Do not show xy plane
swTriadManipulatorDoNotShowXYRING	128 or 0x80; Do not show xy ring
swTriadManipulatorDoNotShowYAxis	4 or 0x4; Do not show y axis
swTriadManipulatorDoNotShowYZPlane	32 or 0x20; Do not show yz plane
swTriadManipulatorDoNotShowYZRING	256 or 0x100; Do not show yz ring
swTriadManipulatorDoNotShowZAxis	8 or 0x8; Do not show z axis
swTriadManipulatorDoNotShowZXPlane	64 or 0x40; Do not show zx plane
swTriadManipulatorDoNotShowZXRING	512 or 0x200; Do not show zx ring
swTriadManipulatorShowAll	0 or 0x0; Show all

See Also

[SolidWorks.Interop.swconst Namespace](#)

swTrimToolMemberObjectType_e (Type)

SOLIDWORKS API Enumerations

swTrimToolMemberObjectType_e Enumeration

[Send comments on this topic.](#)

[See Also](#)

 

[SolidWorks.Interop.swconst Namespace](#) : swTrimToolMemberObjectType_e Enumeration

Structure system complex corner treatment trim tools.

Syntax

Visual Basic (Declaration)

```
Public Enum swTrimToolMemberObjectType_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swTrimToolMemberObjectType\_e
```

C#

```
public enum swTrimToolMemberObjectType_e : System.Enum
```

C++/CLI

```
public enum class swTrimToolMemberObjectType_e : public System.Enum
```

Members

Member	Description
swTrimToolMemberObjectType_swCornerMember	0
swTrimToolMemberObjectType_swCornerTreatmentFeature	1

See Also

[SolidWorks.Interop.swconst Namespace](#)

swTwistControlType_e (Type)

SOLIDWORKS API Enumerations

swTwistControlType_e Enumeration

See Also

Send comments on this topic.

▼

SolidWorks.Interop.swconst Namespace : swTwistControlType_e Enumeration

Sweep twist control options.

Syntax

Visual Basic (Declaration)

Public Enum swTwistControlType_e
Inherits System.Enum

Visual Basic (Usage) Copy Code

Dim instance As [swTwistControlType_e](#)

C#

public enum swTwistControlType_e : System.Enum

C++/CLI

public enum class swTwistControlType_e : public System.Enum

Members

Member	Description
swTwistControlConstantTwistAlongPath	8 = Defines the twist of the profile along the sweep path; corresponds to Profile Twist > Specify Twist Value in the Sweep PropertyManager
swTwistControlFollowFirstSecondGuideCurves	3 = The twist of the intermediate sections is determined by the vector from the first guide curve to the second guide curve; the angle between the horizontal plane and the vector remains constant in the sketch planes of all of the intermediate sections; corresponds to Profile Twist > Follow First and Second Guide Curves in the Sweep PropertyManager (only valid if two guide curves are present)
swTwistControlFollowPath	0 = Corresponds to Profile orientation > Follow Path in the Sweep PropertyManager; after specifying this option, use ISweepFeatureData::PathAlignmentType to specify path alignment options as defined in swTangencyType_e
swTwistControlFollowPathFirstGuideCurve	2 = The twist of the intermediate sections is determined by the vector from the path to the first guide curve; the angle between the horizontal plane and the vector remains constant in the sketch planes of all of the intermediate sections; corresponds to Profile Twist > Follow Path and First Guide Curve in the Sweep PropertyManager (only valid if at least one guide curve is present)
swTwistControlKeepNormalConstant	1 = Twists the section along the sweep path, keeping the section parallel to the beginning section as it twists along the path; corresponds to Profile orientation > Keep Normal Constant in the Sweep PropertyManager
swTwistControlNormalConstantTwistAlongPath	9 = Defines the twist of the profile along the sweep path, keeping the section parallel to the beginning section as it twists along the path; corresponds to Profile orientation > Keep Normal Constant and Profile Twist > Specify Twist Value in the Sweep PropertyManager

See Also

[SolidWorks.Interop.swconst Namespace](#)

swUIStates_e (Type)

SOLIDWORKS API Enumerations

swUIStates_e Enumeration

See Also

[Send comments on this topic.](#)

 

[SolidWorks.Interop.swconst Namespace](#) : swUIStates_e Enumeration

User-interface state types.

 Syntax

Visual Basic (Declaration)

```
Public Enum swUIStates_e
    Inherits System.Enum
```

Visual Basic (Usage)  [Copy Code](#)

```
Dim instance As swUIStates\_e
```

C#

```
public enum swUIStates_e : System.Enum
```

C++/CLI

```
public enum class swUIStates_e : public System.Enum
```

 Members

Member	Description
swIsHiddenInFeatureMgr	1

 See Also

[SolidWorks.Interop.swconst Namespace](#)

swUnitsDecimalRounding_e (Type)

SOLIDWORKS API Enumerations

swUnitsDecimalRounding_e Enumeration

See Also

[Send comments on this topic.](#)

 

SolidWorks.Interop.swconst Namespace : swUnitsDecimalRounding_e Enumeration

Rounding options for decimal units.

 Syntax

Visual Basic (Declaration)

Public Enum swUnitsDecimalRounding_e
Inherits System.Enum

Visual Basic (Usage)  Copy Code

Dim instance As [swUnitsDecimalRounding_e](#)

C#

public enum swUnitsDecimalRounding_e : System.Enum

C++/CLI

public enum class swUnitsDecimalRounding_e : public System.Enum

 Members

Member	Description
swUnitsDecimalRounding_HalfAway	0 = Round up to the nearest decimal
swUnitsDecimalRounding_HalfToEven	2 = Round up or down to the next even decimal
swUnitsDecimalRounding_HalfTowards	1 = Round down to the nearest decimal
swUnitsDecimalRounding_Truncate	3 = Truncate the decimal without rounding

 See Also

[SolidWorks.Interop.swconst Namespace](#)

swUnitsEnergyUnit_e (Type)

SOLIDWORKS API Enumerations

swUnitsEnergyUnit_e Enumeration

See Also

[Send comments on this topic.](#)

 

[SolidWorks.Interop.swconst Namespace](#) : swUnitsEnergyUnit_e Enumeration

Energy unit types.

 Syntax

Visual Basic (Declaration)

```
Public Enum swUnitsEnergyUnit_e
    Inherits System.Enum
```

Visual Basic (Usage)  Copy Code

```
Dim instance As swUnitsEnergyUnit\_e
```

C#

```
public enum swUnitsEnergyUnit_e : System.Enum
```

C++/CLI

```
public enum class swUnitsEnergyUnit_e : public System.Enum
```

 Members

Member	Description
swUnitsEnergyUnit_BTU	3
swUnitsEnergyUnit_Ergs	2
swUnitsEnergyUnit_Joule	1
swUnitsEnergyUnit_KilowattHour	4

 See Also

[SolidWorks.Interop.swconst Namespace](#)

swUnitsForce_e (Type)

SOLIDWORKS API Enumerations

swUnitsForce_e Enumeration

See Also

[Send comments on this topic.](#)

 

[SolidWorks.Interop.swconst Namespace](#) : swUnitsForce_e Enumeration

Force units.

 Syntax

Visual Basic (Declaration)

Public Enum swUnitsForce_e
Inherits System.Enum

Visual Basic (Usage)  Copy Code

Dim instance As [swUnitsForce_e](#)

C#

public enum swUnitsForce_e : System.Enum

C++/CLI

public enum class swUnitsForce_e : public System.Enum

 Members

Member	Description
swUnitsForce_Dynes	1
swUnitsForce_KgForce	7
swUnitsForce_Kilonewtons	4
swUnitsForce_Meganewtons	5
swUnitsForce_Millinewtons	2
swUnitsForce_Newtons	3
swUnitsForce_OunceForce	8
swUnitsForce_Poundfeet	6

 See Also

[SolidWorks.Interop.swconst Namespace](#)

swUnitsMassPropMass_e (Type)

SOLIDWORKS API Enumerations

swUnitsMassPropMass_e Enumeration

See Also

[Send comments on this topic.](#)

 

[SolidWorks.Interop.swconst Namespace](#) : swUnitsMassPropMass_e Enumeration

Mass property units.

 Syntax

Visual Basic (Declaration)

```
Public Enum swUnitsMassPropMass_e
    Inherits System.Enum
```

Visual Basic (Usage)  Copy Code

```
Dim instance As swUnitsMassPropMass\_e
```

C#

```
public enum swUnitsMassPropMass_e : System.Enum
```

C++/CLI

```
public enum class swUnitsMassPropMass_e : public System.Enum
```

 Members

Member	Description
swUnitsMassPropMass_Grams	2
swUnitsMassPropMass_Kilograms	3
swUnitsMassPropMass_Milligrams	1
swUnitsMassPropMass_Pounds	4

 See Also

[SolidWorks.Interop.swconst Namespace](#)

swUnitsMassPropVolume_e (Type)

SOLIDWORKS API Enumerations

swUnitsMassPropVolume_e Enumeration

See Also

[SolidWorks.Interop.swconst Namespace](#) : swUnitsMassPropVolume_e Enumeration

Mass property per unit volumes.

Syntax

Visual Basic (Declaration)

```
Public Enum swUnitsMassPropVolume_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swUnitsMassPropVolume\_e
```

C#

```
public enum swUnitsMassPropVolume_e : System.Enum
```

C++/CLI

```
public enum class swUnitsMassPropVolume_e : public System.Enum
```

Members

Member	Description
swUnitsMassPropVolume_Angstroms3	1
swUnitsMassPropVolume_CentiLiters	13
swUnitsMassPropVolume_Centimeters3	5
swUnitsMassPropVolume_DeciLiters	14
swUnitsMassPropVolume_Feet3	10
swUnitsMassPropVolume_HectoLiters	16
swUnitsMassPropVolume_IMPCubicYards	21
swUnitsMassPropVolume_IMPGallons	20
swUnitsMassPropVolume_Inches3	9
swUnitsMassPropVolume_Liters	15
swUnitsMassPropVolume_Meters3	6
swUnitsMassPropVolume_Microinches3	7
swUnitsMassPropVolume_MicroLiters	11
swUnitsMassPropVolume_Microns3	3
swUnitsMassPropVolume_Milliliters	12
swUnitsMassPropVolume_Millimeters3	4
swUnitsMassPropVolume_Mils3	8
swUnitsMassPropVolume_Nanometers3	2
swUnitsMassPropVolume_USFluidOunce	17
swUnitsMassPropVolume_USGallons	19
swUnitsMassPropVolume_USPints	18

See Also

[SolidWorks.Interop.swconst Namespace](#)

swUnitsPowerUnit_e (Type)

SOLIDWORKS API Enumerations

swUnitsPowerUnit_e Enumeration

See Also

 

SolidWorks.Interop.swconst Namespace : swUnitsPowerUnit_e Enumeration

Types of power units.

[Send comments on this topic.](#)

Syntax

Visual Basic (Declaration)

```
Public Enum swUnitsPowerUnit_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swUnitsPowerUnit\_e
```

C#

```
public enum swUnitsPowerUnit_e : System.Enum
```

C++/CLI

```
public enum class swUnitsPowerUnit_e : public System.Enum
```

Members

Member	Description
swUnitsPowerUnit_Horsepower	2
swUnitsPowerUnit_Kilowatt	3
swUnitsPowerUnit_Watt	1

See Also

[SolidWorks.Interop.swconst Namespace](#)

swUnitsTimeUnit_e (Type)

SOLIDWORKS API Enumerations

swUnitsTimeUnit_e Enumeration

See Also

[Send comments on this topic.](#)

 

[SolidWorks.Interop.swconst Namespace](#) : swUnitsTimeUnit_e Enumeration

Types of time units.

 Syntax

Visual Basic (Declaration)

```
Public Enum swUnitsTimeUnit_e
    Inherits System.Enum
```

Visual Basic (Usage)  Copy Code

```
Dim instance As swUnitsTimeUnit\_e
```

C#

```
public enum swUnitsTimeUnit_e : System.Enum
```

C++/CLI

```
public enum class swUnitsTimeUnit_e : public System.Enum
```

 Members

Member	Description
swUnitsTimeUnit_Hour	4
swUnitsTimeUnit_Microsecond	5
swUnitsTimeUnit_Millisecond	2
swUnitsTimeUnit_Minute	3
swUnitsTimeUnit_Nanosecond	6
swUnitsTimeUnit_Second	1

 See Also

[SolidWorks.Interop.swconst Namespace](#)

swUnitSystem_e (Type)

SOLIDWORKS API Enumerations

swUnitSystem_e Enumeration

See Also

[Send comments on this topic.](#)

 SolidWorks.Interop.swconst Namespace : swUnitSystem_e Enumeration

System units.

 Syntax

Visual Basic (Declaration)

Public Enum swUnitSystem_e
Inherits System.Enum

Visual Basic (Usage)

Dim instance As [swUnitSystem_e](#)

C#

public enum swUnitSystem_e : System.Enum

C++/CLI

public enum class swUnitSystem_e : public System.Enum

 Members

Member	Description
swUnitSystem_CGS	1 = Centimeter, gram, second
swUnitSystem_Custom	4 = Lets you set length units, density units, and force
swUnitSystem_IPS	3 = Inch, pound, second
swUnitSystem_MKS	2 = Meter, kilogram, second
swUnitSystem_MMGS	5 = Millimeter, gram, second

 See Also

[SolidWorks.Interop.swconst Namespace](#)

swUpdateProgressError_e (Type)

SOLIDWORKS API Enumerations

swUpdateProgressError_e Enumeration

See Also

[Send comments on this topic.](#)

 [SolidWorks.Interop.swconst Namespace](#) : swUpdateProgressError_e Enumeration

User progress errors.

 Syntax

Visual Basic (Declaration)

Public Enum swUpdateProgressError_e
Inherits System.Enum

Visual Basic (Usage)

Dim instance As [swUpdateProgressError_e](#)



C#

public enum swUpdateProgressError_e : System.Enum

C++/CLI

public enum class swUpdateProgressError_e : public System.Enum

 Members

Member	Description
swUpdateProgressError_NotInitialized	4
swUpdateProgressError_OutOfBounds	3
swUpdateProgressError_Success	1
swUpdateProgressError_UnknownError	0
swUpdateProgressError_UserCancel	2 = User pressed the Esc key to cancel the progress indicator

 See Also

[SolidWorks.Interop.swconst Namespace](#)

swUserMessageBarResponseType_e (Type)

SOLIDWORKS API Enumerations

swUserMessageBarResponseType_e Enumeration

See Also

 

[SolidWorks.Interop.swconst Namespace](#) : swUserMessageBarResponseType_e Enumeration

Types of user response controls for message bars.

[Send comments on this topic.](#)

Syntax

Visual Basic (Declaration)

```
Public Enum swUserMessageBarResponseType_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swUserMessageBarResponseType\_e
```

C#

```
public enum swUserMessageBarResponseType_e : System.Enum
```

C++/CLI

```
public enum class swUserMessageBarResponseType_e : public System.Enum
```

Members

Member	Description
swUserMessageBarResponseType_Button	1 = Button control
swUserMessageBarResponseType_Link	2 = Command link control
swUserMessageBarResponseType_None	0 = No controls

See Also

[SolidWorks.Interop.swconst Namespace](#)

swUserMessageBarSeverity_e (Type)

SOLIDWORKS API Enumerations

swUserMessageBarSeverity_e Enumeration

[See Also](#)

 

[SolidWorks.Interop.swconst Namespace](#) : swUserMessageBarSeverity_e Enumeration

Types of severities for message bars.

[Send comments on this topic.](#)

Syntax

Visual Basic (Declaration)

```
Public Enum swUserMessageBarSeverity_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swUserMessageBarSeverity\_e
```

C#

```
public enum swUserMessageBarSeverity_e : System.Enum
```

C++/CLI

```
public enum class swUserMessageBarSeverity_e : public System.Enum
```

Members

Member	Description
swUserMessageBarSeverity_Acknowledgement	1
swUserMessageBarSeverity_Error	3
swUserMessageBarSeverity_Information	0 (default)
swUserMessageBarSeverity_Warning	2

See Also

[SolidWorks.Interop.swconst Namespace](#)

swUserNotificationPosition_e (Type)

SOLIDWORKS API Enumerations

swUserNotificationPosition_e Enumeration

See Also

[SolidWorks.Interop.swconst Namespace](#) : swUserNotificationPosition_e Enumeration

User notification display positions.

[Send comments on this topic.](#)

Syntax

Visual Basic (Declaration)

```
Public Enum swUserNotificationPosition_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swUserNotificationPosition\_e
```

C#

```
public enum swUserNotificationPosition_e : System.Enum
```

C++/CLI

```
public enum class swUserNotificationPosition_e : public System.Enum
```

Members

Member	Description
swUserNotificationPosition_BottomCenter	3 = Bottom-center of the parent window
swUserNotificationPosition_BottomRight	4 = Bottom-right of the parent window
swUserNotificationPosition_Default	0 = Use the system-defined default location in this parent window for user notifications
swUserNotificationPosition_TopCenter	1 = Top-center of the parent window
swUserNotificationPosition_TopRight	2 = Top-right of the parent window

See Also

[SolidWorks.Interop.swconst Namespace](#)

swUserNotificationResponseType_e (Type)

SOLIDWORKS API Enumerations

swUserNotificationResponseType_e Enumeration

[See Also](#)

 

[SolidWorks.Interop.swconst Namespace](#) : swUserNotificationResponseType_e Enumeration

User response controls for user notifications.

[Send comments on this topic.](#)

Syntax

Visual Basic (Declaration)

```
Public Enum swUserNotificationResponseType_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swUserNotificationResponseType\_e
```

C#

```
public enum swUserNotificationResponseType_e : System.Enum
```

C++/CLI

```
public enum class swUserNotificationResponseType_e : public System.Enum
```

Members

Member	Description
swUserNotificationResponseType_Button	1 = Button control
swUserNotificationResponseType_Link	2 = Command link control
swUserNotificationResponseType_None	0 = No control

See Also

[SolidWorks.Interop.swconst Namespace](#)

swUserNotificationSeverity_e (Type)

SOLIDWORKS API Enumerations

swUserNotificationSeverity_e Enumeration

[See Also](#)

[Send comments on this topic.](#)

 

[SolidWorks.Interop.swconst Namespace](#) : swUserNotificationSeverity_e Enumeration

User notification severities.

Syntax

Visual Basic (Declaration)

```
Public Enum swUserNotificationSeverity_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swUserNotificationSeverity\_e
```

C#

```
public enum swUserNotificationSeverity_e : System.Enum
```

C++/CLI

```
public enum class swUserNotificationSeverity_e : public System.Enum
```

Members

Member	Description
swUserNotificationSeverity_Acknowledgement	1
swUserNotificationSeverity_Error	3
swUserNotificationSeverity_Information	0 (default)
swUserNotificationSeverity_Warning	2

See Also

[SolidWorks.Interop.swconst Namespace](#)

swUserPreferenceDoubleValue_e (Type)

SOLIDWORKS API Enumerations

swUserPreferenceDoubleValue_e Enumeration

See Also

▼

[SOLIDWORKS.Interop.swconst Namespace](#) : swUserPreferenceDoubleValue_e Enumeration

User-preference enumerators for system options and document properties.

[Send comments on this topic.](#)

Syntax

Visual Basic (Declaration)

```
Public Enum swUserPreferenceDoubleValue_e
    Inherits System.Enum
```

Visual Basic (Usage)



```
Dim instance As swUserPreferenceDoubleValue\_e
```

C#

```
public enum swUserPreferenceDoubleValue_e : System.Enum
```

C++/CLI

```
public enum class swUserPreferenceDoubleValue_e : public System.Enum
```

Members

Member	Description
swAbsChordalErrorVal	See System Options and Document Properties .
swAbsEdgeLengthVal	See System Options and Document Properties .
swAbsNormalDeviationVal	See System Options and Document Properties .
swAnnotationTextScaleDenominator	See System Options and Document Properties .
swAnnotationTextScaleNumerator	See System Options and Document Properties .
swASMSLDPRT_ ExcludeComponentsByBBoxVolumeThreshold	See System Options and Document Properties .
swASMSLDPRT_ ExcludeComponentsByVisibilityThreshold	See System Options and Document Properties .
swBOMControlSplitHeight	See System Options and Document Properties .
swCurvatureValue1	See System Options and Document Properties .
swCurvatureValue2	See System Options and Document Properties .
swCurvatureValue3	See System Options and Document Properties .
swCurvatureValue4	See System Options and Document Properties .
swCurvatureValue5	See System Options and Document Properties .
swCustomizedImportTolerance	See System Options and Document Properties .
swDetailingAnnotationBentLeaderLength	See System Options and Document Properties .
swDetailingArrowHeight	See System Options and Document Properties .
swDetailingArrowLength	See System Options and Document Properties .
swDetailingArrowWidth	See System Options and Document Properties .
swDetailingBalloonBentLeaderLength	See System Options and Document Properties .
swDetailingBalloonFrameLineThicknessCustom	See System Options and Document Properties .
swDetailingBalloonLeaderLineThicknessCustom	See System Options and Document Properties .
swDetailingBalloonQtyGapDistance	See System Options and Document Properties .
swDetailingBOMBalloonCustomSize	See System Options and Document Properties .
swDetailingBOMBalloonPadding	See System Options and Document Properties .
swDetailingBOMStackedBalloonCustomSize	See System Options and Document Properties .
swDetailingBOMStackedBalloonPadding	See System Options and Document Properties .
swDetailingBorderAddPadding	See System Options and Document Properties .
swDetailingBorderInnerCenterZoneDividerLength	See System Options and Document Properties .
swDetailingBorderLeaderCustomLineThickness	See System Options and Document Properties .
swDetailingBorderOuterCenterZoneDividerLength	See System Options and Document Properties .
swDetailingBorderUserDefined	See System Options and Document Properties .
swDetailingBorderZoneDividerCustomLineThickness	See System Options and Document Properties .
swDetailingBorderZoneDividerLength	See System Options and Document Properties .
swDetailingBreakLineExtension	See System Options and Document Properties .
swDetailingBreakLineGap	See System Options and Document Properties .
swDetailingCenterlineExtension	See System Options and Document Properties .
swDetailingCenterMarkGap	See System Options and Document Properties .
swDetailingCenterMarkSize	See System Options and Document Properties .
swDetailingCenterOfMassSize	See System Options and Document Properties .
swDetailingDatumFrameLineThicknessCustom	See System Options and Document Properties .
swDetailingDatumLeaderLineThicknessCustom	See System Options and Document Properties .
swDetailingDimBentLeaderLength	See System Options and Document Properties .
swDetailingDimBreakGap	See System Options and Document Properties .
swDetailingDimFontHeight	See System Options and Document Properties .
swDetailingDimRadialSnapAngle	See System Options and Document Properties .
swDetailingDimToDimOffset	See System Options and Document Properties .
swDetailingGtolBentLeaderLength	See System Options and Document Properties .
swDetailingGtolFrameLineThicknessCustom	See System Options and Document Properties .
swDetailingGtolLeaderLineThicknessCustom	See System Options and Document Properties .
swDetailingHatchDensityLimit	See System Options and Document Properties .
swDetailingLocationLabelFrameLineThicknessCustom	See System Options and Document Properties .
swDetailingLocationLabelPadding	See System Options and Document Properties .
swDetailingLocationLabelStyleCustomSize	See System Options and Document Properties .
swDetailingMaxAngularToleranceValue	See System Options and Document Properties .
swDetailingMaxLinearToleranceValue	See System Options and Document Properties .
swDetailingMaxToleranceValue	See System Options and Document Properties .
swDetailingMaxWitnessLineLength	See System Options and Document Properties .

swDetailingMinAngularToleranceValue	See System Options and Document Properties .
swDetailingMinLinearToleranceValue	See System Options and Document Properties .
swDetailingMinToleranceValue	See System Options and Document Properties .
swDetailingNoteBentLeaderLength	See System Options and Document Properties .
swDetailingNoteFontHeight	See System Options and Document Properties .
swDetailingNoteLeaderLineThicknessCustom	See System Options and Document Properties .
swDetailingObjectToDimOffset	See System Options and Document Properties .
swDetailingOrdinateSize	See System Options and Document Properties .
swDetailingParaSpacing	See System Options and Document Properties .
swDetailingRevisionCloudLineThicknessCustom	See System Options and Document Properties .
swDetailingRevisionCloudMaxArcRadius	See System Options and Document Properties .
swDetailingSectionArrowHeight	See System Options and Document Properties .
swDetailingSectionArrowLength	See System Options and Document Properties .
swDetailingSectionArrowWidth	See System Options and Document Properties .
swDetailingSFSymbolBentLeaderLength	See System Options and Document Properties .
swDetailingSFSymbolLeaderLineThicknessCustom	See System Options and Document Properties .
swDetailingTablesHorizontalPadding	See System Options and Document Properties .
swDetailingTablesVerticalPadding	See System Options and Document Properties .
swDetailingToleranceFitToTextHeight	See System Options and Document Properties .
swDetailingToleranceFitToTextScale	See System Options and Document Properties .
swDetailingToleranceTextHeight	See System Options and Document Properties .
swDetailingToleranceTextScale	See System Options and Document Properties .
swDetailingWeldSymbolLeaderLineThicknessCustom	See System Options and Document Properties .
swDetailingWitnessLineExtension	See System Options and Document Properties .
swDetailingWitnessLineGap	See System Options and Document Properties .
swDimensionsExtensionLineStyleThicknessCustom	See System Options and Document Properties .
swDocumentColorAdvancedAmbient	See System Options and Document Properties .
swDocumentColorAdvancedDiffuse	See System Options and Document Properties .
swDocumentColorAdvancedEmission	See System Options and Document Properties .
swDocumentColorAdvancedShininess	See System Options and Document Properties .
swDocumentColorAdvancedSpecularity	See System Options and Document Properties .
swDocumentColorAdvancedTransparency	See System Options and Document Properties .
swDrawingAreaHatchAngle	See System Options and Document Properties .
swDrawingAreaHatchScale	See System Options and Document Properties .
swDrawingDefaultSheetScaleDenominator	See System Options and Document Properties .
swDrawingDefaultSheetScaleNumerator	See System Options and Document Properties .
swDrawingDetailViewScale	See System Options and Document Properties .
swDrawingKeyboardMovementIncrement	See System Options and Document Properties .
swDxMergingDistance	See System Options and Document Properties .
swDxOutputScaleFactor	See System Options and Document Properties .
swGridMajorSpacing	See System Options and Document Properties .
swHoleTableTagAngle	See System Options and Document Properties .
swHoleTableTagOffset	See System Options and Document Properties .
swImageQualityShadedDeviation	See System Options and Document Properties .
swLineFontAdjoiningComponentCustom	See System Options and Document Properties .
swLineFontBendLineDownThicknessCustom	See System Options and Document Properties .
swLineFontBendLineUpThicknessCustom	See System Options and Document Properties .
swLineFontBreakLineThicknessCustom	See System Options and Document Properties .
swLineFontConstructionCurvesThicknessCustom	See System Options and Document Properties .
swLineFontCosmeticThreadThicknessCustom	See System Options and Document Properties .
swLineFontCrosshatchThicknessCustom	See System Options and Document Properties .
swLineFontDetailBorderThicknessCustom	See System Options and Document Properties .
swLineFontDetailCircleThicknessCustom	See System Options and Document Properties .
swLineFontDimensionsThicknessCustom	See System Options and Document Properties .
swLineFontEmphasizedSectionThicknessCustom	See System Options and Document Properties .
swLineFontEnvelopeComponentThicknessCustom	See System Options and Document Properties .
swLineFontExplodedLinesThicknessCustom	See System Options and Document Properties .
swLineFontHiddenEdgesThicknessCustom	See System Options and Document Properties .
swLineFontHideTangentEdgeThicknessCustom	See System Options and Document Properties .
swLineFontSectionLineThicknessCustom	See System Options and Document Properties .
swLineFontSketchCurvesThicknessCustom	See System Options and Document Properties .
swLineFontSpeedPakDrawingsModelEdgesThicknessCustom	See System Options and Document Properties .
swLineFontTangentEdgesThicknessCustom	See System Options and Document Properties .
swLineFontViewArrowThicknessCustom	See System Options and Document Properties .
swLineFontVisibleEdgesThicknessCustom	See System Options and Document Properties .
swMateAnimationSpeed	See System Options and Document Properties .
swMaterialPropertyCrosshatchAngle	See System Options and Document Properties .
swMaterialPropertyCrosshatchScale	See System Options and Document Properties .
swMaterialPropertyDensity	See System Options and Document Properties .
swMatesMaximumDeviationForMisalignedMates	See System Options and Document Properties .
swPageSetupPrinterBottomMargin	See System Options and Document Properties .
swPageSetupPrinterDrawingScale	See System Options and Document Properties .
swPageSetupPrinterLeftMargin	See System Options and Document Properties .
swPageSetupPrinterNormalLineWeight	See System Options and Document Properties .
swPageSetupPrinterPartAsmScale	See System Options and Document Properties .
swPageSetupPrinterRightMargin	See System Options and Document Properties .
swPageSetupPrinterThick2LineWeight	See System Options and Document Properties .
swPageSetupPrinterThick3LineWeight	See System Options and Document Properties .
swPageSetupPrinterThick4LineWeight	See System Options and Document Properties .
swPageSetupPrinterThick5LineWeight	See System Options and Document Properties .
swPageSetupPrinterThick6LineWeight	See System Options and Document Properties .
swPageSetupPrinterThickLineWeight	See System Options and Document Properties .
swPageSetupPrinterThinLineWeight	See System Options and Document Properties .
swPageSetupPrinterTopMargin	See System Options and Document Properties .
swPartDimXpertAngularUnitToValue	See System Options and Document Properties .
swPartDimXpertChainInnerToLowerValue	See System Options and Document Properties .
swPartDimXpertChainInnerToUpperValue	See System Options and Document Properties .
swPartDimXpertChainPatternLocToLowerValue	See System Options and Document Properties .
swPartDimXpertChainPatternLocToUpperValue	See System Options and Document Properties .
swPartDimXpertChamferAngleToLowerValue	See System Options and Document Properties .
swPartDimXpertChamferAngleToUpperValue	See System Options and Document Properties .
swPartDimXpertChamferDistanceToLowerValue	See System Options and Document Properties .
swPartDimXpertChamferDistanceToUpperValue	See System Options and Document Properties .
swPartDimXpertChamferMaxWidth	See System Options and Document Properties .
swPartDimXpertChamferWidthRatio	See System Options and Document Properties .
swPartDimXpertGeometricPositionCompositeToValue	See System Options and Document Properties .
swPartDimXpertGeometricPositionToValue	See System Options and Document Properties .
swPartDimXpertGeometricPrimaryToValue	See System Options and Document Properties .
swPartDimXpertGeometricRunoutToValue	See System Options and Document Properties .
swPartDimXpertGeometricSecondFeatureSizeToValue	See System Options and Document Properties .
swPartDimXpertGeometricSecondPlaneFeatureToValue	See System Options and Document Properties .
swPartDimXpertGeometricSurfaceProfileCompositeToValue	See System Options and Document Properties .
swPartDimXpertGeometricSurfaceProfileToValue	See System Options and Document Properties .
swPartDimXpertGeometricThirdFeatureSizeToValue	See System Options and Document Properties .
swPartDimXpertGeometricThirdPlaneFeatureToValue	See System Options and Document Properties .
swPartDimXpertLengthUnitTo1Value	See System Options and Document Properties .
swPartDimXpertLengthUnitTo2Value	See System Options and Document Properties .
swPartDimXpertLengthUnitTo3Value	See System Options and Document Properties .

swPartDimXpertLocationAngleTolLowerValue	See System Options and Document Properties .
swPartDimXpertLocationAngleTolUpperValue	See System Options and Document Properties .
swPartDimXpertLocationDistanceTolLowerValue	See System Options and Document Properties .
swPartDimXpertLocationDistanceTolUpperValue	See System Options and Document Properties .
swPartDimXpertSizeCounterboreDiameterTolLowerValue	See System Options and Document Properties .
swPartDimXpertSizeCounterboreDiameterTolUpperValue	See System Options and Document Properties .
swPartDimXpertSizeCountersinkAngleTolLowerValue	See System Options and Document Properties .
swPartDimXpertSizeCountersinkAngleTolUpperValue	See System Options and Document Properties .
swPartDimXpertSizeCountersinkDiameterTolLowerValue	See System Options and Document Properties .
swPartDimXpertSizeCountersinkDiameterTolUpperValue	See System Options and Document Properties .
swPartDimXpertSizeDepthTolLowerValue	See System Options and Document Properties .
swPartDimXpertSizeDepthTolUpperValue	See System Options and Document Properties .
swPartDimXpertSizeDiameterTolLowerValue	See System Options and Document Properties .
swPartDimXpertSizeDiameterTolUpperValue	See System Options and Document Properties .
swPartDimXpertSizeFilletRadiusTolLowerValue	See System Options and Document Properties .
swPartDimXpertSizeFilletRadiusTolUpperValue	See System Options and Document Properties .
swPartDimXpertSizeLengthSlotTolLowerValue	See System Options and Document Properties .
swPartDimXpertSizeLengthSlotTolUpperValue	See System Options and Document Properties .
swPartDimXpertSizeWidthSlotTolLowerValue	See System Options and Document Properties .
swPartDimXpertSizeWidthSlotTolUpperValue	See System Options and Document Properties .
swPLYAngleTolerance	See System Options and Document Properties .
swPLYDeviation	See System Options and Document Properties .
swPrint3DBoxX	See System Options and Document Properties .
swPrint3DBoxY	See System Options and Document Properties .
swPrint3DBoxZ	See System Options and Document Properties .
swPunchTableTagAngle	See System Options and Document Properties .
swPunchTableTagOffset	See System Options and Document Properties .
swQuickViewTransparencyLevel	See System Options and Document Properties .
swSheetMetalBendNotesBorderSizeCustom	See System Options and Document Properties .
swSheetMetalBendNotesLeaderLength	See System Options and Document Properties .
swSheetMetalBendNotesLeaderLineThicknessCustom	See System Options and Document Properties .
swSheetMetalMBDBorderSizeCustom	See System Options and Document Properties .
swSheetMetalMBDLeaderLength	See System Options and Document Properties .
swSheetMetalMBDLeaderLineThicknessCustom	See System Options and Document Properties .
swSketchSnapsAngleValue	See System Options and Document Properties .
swSmartMateSensitivity	See System Options and Document Properties .
swSnapToAngleValue	See System Options and Document Properties .
swSpinBoxAngleIncrement	See System Options and Document Properties .
swSpinBoxEnglishLengthIncrement	See System Options and Document Properties .
swSpinBoxMetricLengthIncrement	See System Options and Document Properties .
swSpinBoxTimeIncrement	See System Options and Document Properties .
swSTLAngleTolerance	See System Options and Document Properties .
swSTLDeviation	See System Options and Document Properties .
swSystemTouchRotateVersusPanThreshold	See System Options and Document Properties .
swSystemTouchRotateWidth	See System Options and Document Properties .
swTiffPrintDrawingPaperHeight	See System Options and Document Properties .
swTiffPrintDrawingPaperWidth	See System Options and Document Properties .
swTiffPrintPaperHeight	See System Options and Document Properties .
swTiffPrintPaperWidth	See System Options and Document Properties .
swTwistCountValuePerMeter	See System Options and Document Properties .
swViewAnimationSpeed	See System Options and Document Properties .
swViewRotationArrowKeys	See System Options and Document Properties .
swViewSelectorSpeed	See System Options and Document Properties .
swViewTransitionHideShowComponent	See System Options and Document Properties .
swViewTransitionIsolate	See System Options and Document Properties .

See Also

[SolidWorks.Interop.swconst Namespace](#)
[swUserPreferenceStringListValue e Enumeration](#)
[swUserPreferenceStringValue e Enumeration](#)
[swUserPreferenceTextFormat e Enumeration](#)
[swUserPreferenceToggle e Enumeration](#)