

SOLIDWORKS Document Manager API (.NET) — Reference (9/19): ISwDMDimXpertDepthDimTol- ISwDMDimXpertFlatnessGeoTol

SOLIDWORKS API Documentation (converted from CHM)

ISwDMDimXpertDepthDimTol (Type)

ISwDMDimXpertDepthDimTol Interface

[See Also](#) [Members](#) [Example](#)



[SolidWorks.Interop.swdocumentmgr Namespace](#) : ISwDMDimXpertDepthDimTol Interface

Allows you to access tolerance information for DimXpert depth dimensions.

NOTE: Click the **Members** link, located near the top of the topic, to see this interface's methods and properties.

.NET Syntax

Visual Basic (Declaration)

```
Public Interface ISwDMDimXpertDepthDimTol
```

Visual Basic (Usage)



```
Dim instance As ISwDMDimXpertDepthDimTol
```

C#

```
public interface ISwDMDimXpertDepthDimTol
```

C++/CLI

```
public interface class ISwDMDimXpertDepthDimTol
```

Visual Basic for Applications (VBA) Syntax

See [SwDMDimXpertDepthDimTol](#).

Example

[Get DimXpert Tolerance \(VB.NET\)](#)
[Get DimXpert Tolerance \(C#\)](#)

Remarks

You can access more general information from [ISwDMDimXpertDimensionTolerance](#).

Accessors

[ISwDMDimXpertPart::GetAnnotations](#) and [ISwDMDimXpertPart::IGetAnnotations](#)

See Also

[ISwDMDimXpertDepthDimTol Members](#)
[SolidWorks.Interop.swdocumentmgr Namespace](#)

ISwDMDimXpertDepthDimTol Interface Methods

[See Also](#)



[SolidWorks.Interop.swdocumentmgr Namespace](#) : ISwDMDimXpertDepthDimTol Interface

For a list of all members of this type, see [ISwDMDimXpertDepthDimTol members](#).

Public Methods

Name	Description
 IsThreadDepth	Gets whether this dimension tolerance is for thread depth.

[Top](#)

See Also

[ISwMDimXpertDepthDimTol Interface](#)
[SolidWorks.Interop.swdocumentmgr Namespace](#)

SOLIDWORKS Document Manager API Help

[Send comments](#) on this topic.

ISwMDimXpertDepthDimTol Interface Members

[See Also](#) [Properties](#) [Methods](#)



[SolidWorks.Interop.swdocumentmgr Namespace](#) : ISwMDimXpertDepthDimTol Interface

The following tables list the members exposed by [ISwMDimXpertDepthDimTol](#).

Public Properties

Name	Description
 ReferenceFeature	Gets the DimXpert reference feature for this DimXpert depth dimension tolerance.

[Top](#)

Public Methods

Name	Description
 IsThreadDepth	Gets whether this dimension tolerance is for thread depth.

[Top](#)

See Also

[ISwMDimXpertDepthDimTol Interface](#)
[SolidWorks.Interop.swdocumentmgr Namespace](#)

SOLIDWORKS Document Manager API Help

[Send comments](#) on this topic.

ISwMDimXpertDepthDimTol Interface Properties

[See Also](#)



[SolidWorks.Interop.swdocumentmgr Namespace](#) : ISwMDimXpertDepthDimTol Interface

For a list of all members of this type, see [ISwMDimXpertDepthDimTol members](#).

Public Properties

Name	Description
 ReferenceFeature	Gets the DimXpert reference feature for this DimXpert depth dimension tolerance.

[Top](#)

See Also

[ISwMDimXpertDepthDimTol Interface](#)
[SolidWorks.Interop.swdocumentmgr Namespace](#)

SOLIDWORKS Document Manager API Help

[Send comments](#) on this topic.

IsThreadDepth Method (ISwMDimXpertDepthDimTol)

[See Also](#)



[SolidWorks.Interop.swdocumentmgr Namespace](#) > [ISwMDimXpertDepthDimTol Interface](#) : IsThreadDepth Method (ISwMDimXpertDepthDimTol)

Gets whether this dimension tolerance is for thread depth.

.NET Syntax

Visual Basic (Declaration)

Function IsThreadDepth() As System.Boolean

Visual Basic (Usage)



```
Dim instance As ISwMDimXpertDepthDimTol  
Dim value As System.Boolean
```

```
value = instance.IsThreadDepth()
```

C#

```
System.bool IsThreadDepth()
```

C++/CLI

```
System.bool IsThreadDepth();
```

Return Value

True if the tolerance is for thread depth; false otherwise

Visual Basic for Applications (VBA) Syntax

See [SwDMDimXpertDepthDimTol::IsThreadDepth](#).

Example

See the examples on the interface page.

See Also

[ISwDMDimXpertDepthDimTol Interface](#)
[ISwDMDimXpertDepthDimTol Members](#)

Availability

SOLIDWORKS 2010 FCS, Revision Number 18.0

SOLIDWORKS Document Manager API Help

[Send comments on this topic.](#)

ReferenceFeature Property (ISwDMDimXpertDepthDimTol)

[See Also](#)



[SolidWorks.Interop.swdocumentmgr Namespace](#) > [ISwDMDimXpertDepthDimTol Interface](#) : ReferenceFeature Property (ISwDMDimXpertDepthDimTol)

Gets the DimXpert reference feature for this DimXpert depth dimension tolerance.

.NET Syntax

Visual Basic (Declaration)

```
ReadOnly Property ReferenceFeature As SwDMDimXpertFeature
```

Visual Basic (Usage)



```
Dim instance As ISwDMDimXpertDepthDimTol  
Dim value As SwDMDimXpertFeature  
  
value = instance.ReferenceFeature
```

C#

```
SwDMDimXpertFeature ReferenceFeature {get;}
```

C++/CLI

```
property SwDMDimXpertFeature^ ReferenceFeature {  
    SwDMDimXpertFeature^ get();  
}
```

Property Value

[ISwDMDimXpertFeature](#)

Visual Basic for Applications (VBA) Syntax

See [SwMDimXpertDepthDimTol::ReferenceFeature](#).

Example

See the examples on the interface page.

See Also

[ISwMDimXpertDepthDimTol Interface](#)
[ISwMDimXpertDepthDimTol Members](#)

Availability

SOLIDWORKS 2010 FCS, Revision Number 18.0

ISwDMDimXpertDiameterDimTol (Type)

ISwDMDimXpertDiameterDimTol Interface

[See Also](#) [Members](#) [Example](#)



[SolidWorks.Interop.swdocumentmgr Namespace](#) : ISwDMDimXpertDiameterDimTol Interface

Allows you to access tolerance information for DimXpert diameter dimensions.

NOTE: Click the **Members** link, located near the top of the topic, to see this interface's methods and properties.

.NET Syntax

Visual Basic (Declaration)

```
Public Interface ISwDMDimXpertDiameterDimTol
```

Visual Basic (Usage)

```
Dim instance As ISwDMDimXpertDiameterDimTol
```

C#

```
public interface ISwDMDimXpertDiameterDimTol
```

C++/CLI

```
public interface class ISwDMDimXpertDiameterDimTol
```

Visual Basic for Applications (VBA) Syntax

See [SwDMDimXpertDiameterDimTol](#).

Example

[Get DimXpert Tolerance2 \(VB.NET\)](#)
[Get DimXpert Tolerance2 \(C#\)](#)

Remarks

You can access more general information from [ISwDMDimXpertDimensionTolerance](#).

Accessors

[ISwDMDimXpertPart::GetAnnotations](#) and [ISwDMDimXpertPart::!GetAnnotations](#)

See Also

[ISwDMDimXpertDiameterDimTol Members](#)
[SolidWorks.Interop.swdocumentmgr Namespace](#)

ISwDMDimXpertDiameterDimTol Interface Members

[See Also](#) [Properties](#)



[SolidWorks.Interop.swdocumentmgr Namespace](#) : ISwDMDimXpertDiameterDimTol Interface

The following tables list the members exposed by [ISwDMDimXpertDiameterDimTol](#).

Public Properties

Name	Description
 PatternTreatment	Gets the pattern treatment for this DimXpert diameter dimension tolerance.

[Top](#)

See Also

[ISwDMDimXpertDiameterDimTol Interface](#)
[SolidWorks.Interop.swdocumentmgr Namespace](#)

SOLIDWORKS Document Manager API Help

[Send comments](#) on this topic.

ISwDMDimXpertDiameterDimTol Interface Properties

[See Also](#)

[SolidWorks.Interop.swdocumentmgr Namespace](#) : ISwDMDimXpertDiameterDimTol Interface

For a list of all members of this type, see [ISwDMDimXpertDiameterDimTol members](#).

Public Properties

Name	Description
 PatternTreatment	Gets the pattern treatment for this DimXpert diameter dimension tolerance.

[Top](#)

See Also

[ISwDMDimXpertDiameterDimTol Interface](#)
[SolidWorks.Interop.swdocumentmgr Namespace](#)

SOLIDWORKS Document Manager API Help

[Send comments](#) on this topic.

PatternTreatment Property (ISwDMDimXpertDiameterDimTol)

[See Also](#)



[SolidWorks.Interop.swdocumentmgr Namespace](#) > [ISwDMDimXpertDiameterDimTol Interface](#) : PatternTreatment Property (ISwDMDimXpertDiameterDimTol)

Gets the pattern treatment for this DimXpert diameter dimension tolerance.

.NET Syntax

Visual Basic (Declaration)

ReadOnly Property PatternTreatment As [swDmDimXpertPatternTreatmentType_e](#)

Visual Basic (Usage)



```
Dim instance As ISwDMDimXpertDiameterDimTol  
Dim value As swDmDimXpertPatternTreatmentType\_e  
  
value = instance.PatternTreatment
```

C#

```
swDmDimXpertPatternTreatmentType\_e PatternTreatment {get;}
```

C++/CLI

```
property swDmDimXpertPatternTreatmentType\_e PatternTreatment {  
    swDmDimXpertPatternTreatmentType\_e get();  
}
```

Property Value

Pattern treatment for the diameter dimension tolerance as defined in [swDmDimXpertPatternTreatmentType_e](#)

Visual Basic for Applications (VBA) Syntax

See [SwDMDimXpertDiameterDimTol::PatternTreatment](#).

Example

See the examples on the interface page.

See Also

Availability

SOLIDWORKS 2010 FCS, Revision Number 18.0

ISwDMDimXpertDimensionTolerance (Type)

ISwDMDimXpertDimensionTolerance Interface

[See Also](#) [Members](#) [Example](#)



[SolidWorks.Interop.swdocumentmgr.Namespace](#) : ISwDMDimXpertDimensionTolerance Interface

Allows you to access general information about DimXpert dimension tolerances.

NOTE: Click the **Members** link, located near the top of the topic, to see this interface's methods and properties.

.NET Syntax

Visual Basic (Declaration)

Public Interface ISwDMDimXpertDimensionTolerance

Visual Basic (Usage)

Dim instance As [ISwDMDimXpertDimensionTolerance](#)

C#

public interface ISwDMDimXpertDimensionTolerance

C++/CLI

public interface class ISwDMDimXpertDimensionTolerance

Visual Basic for Applications (VBA) Syntax

See [SwDMDimXpertDimensionTolerance](#).

Example

[Get DimXpert Tolerance \(VB.NET\)](#)
[Get DimXpert Tolerance \(C#\)](#)

Remarks

This interface is the base class for several more specific interfaces. (See the **See Also** section.) You can access more general information from [ISwDMDimXpertAnnotation](#). Use the [ISwDMDimXpertAnnotation::type](#) property to find out which specific interface is needed to acquire more information for a given DimXpert tolerance type.

Accessors

[ISwDMDimXpertPart::GetAnnotations](#) and [ISwDMDimXpertPart::IGetAnnotations](#)

See Also

[ISwDMDimXpertDimensionTolerance Members](#)
[SolidWorks.Interop.swdocumentmgr.Namespace](#)
[ISwDMDimXpertAngleBetweenDimTol Interface](#)
[ISwDMDimXpertChamferDimTol Interface](#)
[ISwDMDimXpertCompositeDistanceBetweenDimTol Interface](#)
[ISwDMDimXpertConeAngleDimTol Interface](#)
[ISwDMDimXpertCounterBoreDimTol Interface](#)
[ISwDMDimXpertCounterSinkAngleDimTol Interface](#)
[ISwDMDimXpertCounterSinkDiameterDimTol Interface](#)
[ISwDMDimXpertDepthDimTol Interface](#)
[ISwDMDimXpertDiameterDimTol Interface](#)
[ISwDMDimXpertDistanceBetweenDimTol Interface](#)
[ISwDMDimXpertLengthDimTol Interface](#)
[ISwDMDimXpertRadiusDimTol Interface](#)
[ISwDMDimXpertWidthDimTol Interface](#)
[ISwDMDimXpertPatternAngleBetweenDimTol Interface](#)

ISwDMDimXpertDimensionTolerance Interface Members

[See Also](#) [Properties](#) [Methods](#)



The following tables list the members exposed by [ISwMDimXpertDimensionTolerance](#).

 Public Properties

Name	Description
 BlockToleranceDecimalPlaces	Gets the precision of the block tolerance of this DimXpert dimension tolerance.
 DimensionType	Gets the type of this DimXpert dimension tolerance.
 LimitsAndFitsCode	Gets the limits and fits code for this DimXpert dimension tolerance.

[Top](#)

 Public Methods

Name	Description
 GetNominalValue	Gets the value of this DimXpert dimension tolerance.
 GetPlusAndMinusTolerance	Gets the plus and minus tolerance values for this DimXpert dimension tolerance.
 GetUpperAndLowerLimit	Gets the upper and lower tolerance limits for this DimXpert dimension tolerance.

[Top](#)

 See Also

[ISwMDimXpertDimensionTolerance Interface](#)
[SolidWorks.Interop.swdocumentmgr Namespace](#)
[ISwMDimXpertAngleBetweenDimTol Interface](#)
[ISwMDimXpertChamferDimTol Interface](#)
[ISwMDimXpertCompositeDistanceBetweenDimTol Interface](#)
[ISwMDimXpertConeAngleDimTol Interface](#)
[ISwMDimXpertCounterBoreDimTol Interface](#)
[ISwMDimXpertCounterSinkAngleDimTol Interface](#)
[ISwMDimXpertCounterSinkDiameterDimTol Interface](#)
[ISwMDimXpertDepthDimTol Interface](#)
[ISwMDimXpertDiameterDimTol Interface](#)
[ISwMDimXpertDistanceBetweenDimTol Interface](#)
[ISwMDimXpertLengthDimTol Interface](#)
[ISwMDimXpertRadiusDimTol Interface](#)
[ISwMDimXpertWidthDimTol Interface](#)
[ISwMDimXpertPatternAngleBetweenDimTol Interface](#)

ISwMDimXpertDimensionTolerance Interface Methods

[See Also](#)

 [SolidWorks.Interop.swdocumentmgr Namespace](#) : ISwMDimXpertDimensionTolerance Interface

For a list of all members of this type, see [ISwMDimXpertDimensionTolerance members](#).

 Public Methods

Name	Description
 GetNominalValue	Gets the value of this DimXpert dimension tolerance.
 GetPlusAndMinusTolerance	Gets the plus and minus tolerance values for this DimXpert dimension tolerance.
 GetUpperAndLowerLimit	Gets the upper and lower tolerance limits for this DimXpert dimension tolerance.

[Top](#)

 See Also

[ISwMDimXpertDimensionTolerance Interface](#)
[SolidWorks.Interop.swdocumentmgr Namespace](#)
[ISwMDimXpertAngleBetweenDimTol Interface](#)
[ISwMDimXpertChamferDimTol Interface](#)
[ISwMDimXpertCompositeDistanceBetweenDimTol Interface](#)
[ISwMDimXpertConeAngleDimTol Interface](#)
[ISwMDimXpertCounterBoreDimTol Interface](#)
[ISwMDimXpertCounterSinkAngleDimTol Interface](#)
[ISwMDimXpertCounterSinkDiameterDimTol Interface](#)
[ISwMDimXpertDepthDimTol Interface](#)
[ISwMDimXpertDiameterDimTol Interface](#)
[ISwMDimXpertDistanceBetweenDimTol Interface](#)
[ISwMDimXpertLengthDimTol Interface](#)
[ISwMDimXpertRadiusDimTol Interface](#)
[ISwMDimXpertWidthDimTol Interface](#)
[ISwMDimXpertPatternAngleBetweenDimTol Interface](#)

ISwMDimXpertDimensionTolerance Interface Properties

[See Also](#)

[SolidWorks.Interop.swdocumentmgr Namespace](#) : ISwMDimXpertDimensionTolerance Interface

For a list of all members of this type, see [ISwMDimXpertDimensionTolerance members](#).

Public Properties

Name	Description
 BlockToleranceDecimalPlaces	Gets the precision of the block tolerance of this DimXpert dimension tolerance.
 DimensionType	Gets the type of this DimXpert dimension tolerance.
 LimitsAndFitsCode	Gets the limits and fits code for this DimXpert dimension tolerance.

[Top](#)

See Also

[ISwMDimXpertDimensionTolerance Interface](#)
[SolidWorks.Interop.swdocumentmgr Namespace](#)
[ISwMDimXpertAngleBetweenDimTol Interface](#)
[ISwMDimXpertChamferDimTol Interface](#)
[ISwMDimXpertCompositeDistanceBetweenDimTol Interface](#)
[ISwMDimXpertConeAngleDimTol Interface](#)
[ISwMDimXpertCounterBoreDimTol Interface](#)
[ISwMDimXpertCounterSinkAngleDimTol Interface](#)
[ISwMDimXpertCounterSinkDiameterDimTol Interface](#)
[ISwMDimXpertDepthDimTol Interface](#)
[ISwMDimXpertDiameterDimTol Interface](#)
[ISwMDimXpertDistanceBetweenDimTol Interface](#)
[ISwMDimXpertLengthDimTol Interface](#)
[ISwMDimXpertRadiusDimTol Interface](#)
[ISwMDimXpertWidthDimTol Interface](#)
[ISwMDimXpertPatternAngleBetweenDimTol Interface](#)

BlockToleranceDecimalPlaces Property (ISwMDimXpertDimensionTolerance)

[See Also](#)



[SolidWorks.Interop.swdocumentmgr Namespace](#) > [ISwMDimXpertDimensionTolerance Interface](#) : BlockToleranceDecimalPlaces Property (ISwMDimXpertDimensionTolerance)

Gets the precision of the block tolerance of this DimXpert dimension tolerance.

.NET Syntax

Visual Basic (Declaration)

ReadOnly Property BlockToleranceDecimalPlaces As System.Integer

Visual Basic (Usage)



```
Dim instance As ISwMDimXpertDimensionTolerance  
Dim value As System.Integer  
  
value = instance.BlockToleranceDecimalPlaces
```

C#

```
System.int BlockToleranceDecimalPlaces {get;}
```

C++/CLI

```
property System.int BlockToleranceDecimalPlaces {  
    System.int get();  
}
```

Property Value

Number of decimal places for block tolerance

Visual Basic for Applications (VBA) Syntax

See [SwMDimXpertDimensionTolerance::BlockToleranceDecimalPlaces](#).

Example

See the examples on the interface page.

See Also

[ISwDMDimXpertDimensionTolerance Interface](#)
[ISwDMDimXpertDimensionTolerance Members](#)

Availability

SOLIDWORKS 2010 FCS, Revision Number 18.0

SOLIDWORKS Document Manager API Help

[Send comments on this topic.](#)

DimensionType Property (ISwDMDimXpertDimensionTolerance)

[See Also](#)



[SolidWorks.Interop.swdocumentmgr Namespace](#) > [ISwDMDimXpertDimensionTolerance Interface](#) : DimensionType Property (ISwDMDimXpertDimensionTolerance)

Gets the type of this DimXpert dimension tolerance.

.NET Syntax

Visual Basic (Declaration)

```
ReadOnly Property DimensionType As swDmDimXpertDimensionToleranceType\_e
```

Visual Basic (Usage)



```
Dim instance As ISwDMDimXpertDimensionTolerance  
Dim value As swDmDimXpertDimensionToleranceType\_e  
  
value = instance.DimensionType
```

C#

```
swDmDimXpertDimensionToleranceType\_e DimensionType {get;}
```

C++/CLI

```
property swDmDimXpertDimensionToleranceType\_e DimensionType {  
    swDmDimXpertDimensionToleranceType\_e get();  
}
```

Property Value

Type of dimension tolerance as defined in [SwDmDimXpertDimensionToleranceType_e](#)

Visual Basic for Applications (VBA) Syntax

See [SwDMDimXpertDimensionTolerance::DimensionType](#).

Example

See the examples on the interface page.

See Also

[ISwDMDimXpertDimensionTolerance Interface](#)
[ISwDMDimXpertDimensionTolerance Members](#)

Availability

SOLIDWORKS 2010 FCS, Revision Number 18.0

SOLIDWORKS Document Manager API Help

[Send comments on this topic.](#)

GetNominalValue Method (ISwDMDimXpertDimensionTolerance)

[See Also](#)



[SolidWorks.Interop.swdocumentmgr Namespace](#) > [ISwMDimXpertDimensionTolerance Interface](#) : GetNominalValue Method (ISwMDimXpertDimensionTolerance)

Gets the value of this DimXpert dimension tolerance.

.NET Syntax

Visual Basic (Declaration)

```
Function GetNominalValue() As System.Double
```

Visual Basic (Usage)



```
Dim instance As ISwMDimXpertDimensionTolerance  
Dim value As System.Double  
  
value = instance.GetNominalValue()
```

C#

```
System.double GetNominalValue()
```

C++/CLI

```
System.double GetNominalValue();
```

Return Value

Tolerance value

Visual Basic for Applications (VBA) Syntax

See [SwMDimXpertDimensionTolerance::GetNominalValue](#).

Example

See the examples on the interface page.

See Also

[ISwMDimXpertDimensionTolerance Interface](#)
[ISwMDimXpertDimensionTolerance Members](#)

Availability

SOLIDWORKS 2010 FCS, Revision Number 18.0

SOLIDWORKS Document Manager API Help

[Send comments](#) on this topic.

GetPlusAndMinusTolerance Method (ISwMDimXpertDimensionTolerance)

[See Also](#)



[SolidWorks.Interop.swdocumentmgr Namespace](#) > [ISwMDimXpertDimensionTolerance Interface](#) : GetPlusAndMinusTolerance Method (ISwMDimXpertDimensionTolerance)

Gets the plus and minus tolerance values for this DimXpert dimension tolerance.

.NET Syntax

Visual Basic (Declaration)

```
Function GetPlusAndMinusTolerance( _  
    ByRef Plus As System.Double, _  
    ByRef Minus As System.Double _  
) As System.Boolean
```

Visual Basic (Usage)



```
Dim instance As ISwDMDimXpertDimensionTolerance
Dim Plus As System.Double
Dim Minus As System.Double
Dim value As System.Boolean

value = instance.GetPlusAndMinusTolerance(Plus, Minus)
```

C#

```
System.bool GetPlusAndMinusTolerance(
    out System.double Plus,
    out System.double Minus
)
```

C++/CLI

```
System.bool GetPlusAndMinusTolerance(
    & [Out] System.double Plus,
    & [Out] System.double Minus
)
```

Parameters

Plus
Plus tolerance value
Minus
Minus tolerance value

Return Value

True if method call is successful; false otherwise

Visual Basic for Applications (VBA) Syntax

See [SwDMDimXpertDimensionTolerance::GetPlusAndMinusTolerance](#).

Example

See the examples on the interface page.

See Also

[ISwDMDimXpertDimensionTolerance Interface](#)
[ISwDMDimXpertDimensionTolerance Members](#)

Availability

SOLIDWORKS 2010 FCS, Revision Number 18.0

SOLIDWORKS Document Manager API Help

[Send comments on this topic.](#)

GetUpperAndLowerLimit Method (ISwDMDimXpertDimensionTolerance)

[See Also](#)



[SolidWorks.Interop.swdocumentmgr Namespace](#) > [ISwDMDimXpertDimensionTolerance Interface](#) : GetUpperAndLowerLimit Method (ISwDMDimXpertDimensionTolerance)

Gets the upper and lower tolerance limits for this DimXpert dimension tolerance.

.NET Syntax

Visual Basic (Declaration)

```
Function GetUpperAndLowerLimit( _
    ByRef Upper As System.Double, _
    ByRef Lower As System.Double _
) As System.Boolean
```

Visual Basic (Usage)



```
Dim instance As ISwMDimXpertDimensionTolerance
Dim Upper As System.Double
Dim Lower As System.Double
Dim value As System.Boolean

value = instance.GetUpperAndLowerLimit(Upper, Lower)
```

C#

```
System.bool GetUpperAndLowerLimit(
    out System.double Upper,
    out System.double Lower
)
```

C++/CLI

```
System.bool GetUpperAndLowerLimit(
    & [Out] System.double Upper,
    & [Out] System.double Lower
)
```

Parameters

Upper
Upper tolerance limit
Lower
Lower tolerance limit

Return Value

True if method call is successful; false otherwise

Visual Basic for Applications (VBA) Syntax

See [SwMDimXpertDimensionTolerance::GetUpperAndLowerLimit](#).

Example

See the examples on the interface page.

See Also

[ISwMDimXpertDimensionTolerance Interface](#)
[ISwMDimXpertDimensionTolerance Members](#)

Availability

SOLIDWORKS 2010 FCS, Revision Number 18.0

SOLIDWORKS Document Manager API Help

[Send comments on this topic.](#)

LimitsAndFitsCode Property (ISwMDimXpertDimensionTolerance)

[See Also](#)



[SolidWorks.Interop.swdocumentmgr Namespace](#) > [ISwMDimXpertDimensionTolerance Interface](#) : LimitsAndFitsCode Property (ISwMDimXpertDimensionTolerance)

Gets the limits and fits code for this DimXpert dimension tolerance.

.NET Syntax

Visual Basic (Declaration)

```
ReadOnly Property LimitsAndFitsCode As System.String
```

Visual Basic (Usage)



```
Dim instance As ISwDMDimXpertDimensionTolerance  
Dim value As System.String  
  
value = instance.LimitsAndFitsCode
```

C#

```
System.string LimitsAndFitsCode {get;}
```

C++/CLI

```
property System.String^ LimitsAndFitsCode {  
    System.String^ get();  
}
```

Property Value

Limits and fits code

Visual Basic for Applications (VBA) Syntax

See [SwDMDimXpertDimensionTolerance::LimitsAndFitsCode](#).

Example

See the examples on the interface page.

See Also

[ISwDMDimXpertDimensionTolerance Interface](#)
[ISwDMDimXpertDimensionTolerance Members](#)

Availability

SOLIDWORKS 2010 FCS, Revision Number 18.0

ISwDMDimXpertDistanceBetweenDimTol (Type)

ISwDMDimXpertDistanceBetweenDimTol Interface

[See Also](#) [Members](#) [Example](#)



[SolidWorks.Interop.swdocumentmgr Namespace](#) : ISwDMDimXpertDistanceBetweenDimTol Interface

Allows you to access tolerance information for DimXpert distance-between dimensions.

NOTE: Click the **Members** link, located near the top of the topic, to see this interface's methods and properties.

.NET Syntax

Visual Basic (Declaration)

```
Public Interface ISwDMDimXpertDistanceBetweenDimTol
```

Visual Basic (Usage)

```
Dim instance As ISwDMDimXpertDistanceBetweenDimTol
```

C#

```
public interface ISwDMDimXpertDistanceBetweenDimTol
```

C++/CLI

```
public interface class ISwDMDimXpertDistanceBetweenDimTol
```

Visual Basic for Applications (VBA) Syntax

See [SwDMDimXpertDistanceBetweenDimTol](#).

Example

[Get DimXpert Tolerance2 \(VB.NET\)](#)
[Get DimXpert Tolerance2 \(C#\)](#)

Remarks

You can access more general information from [ISwDMDimXpertDimensionTolerance](#).

Accessors

[ISwDMDimXpertPart::GetAnnotations](#) and [ISwDMDimXpertPart::!GetAnnotations](#)

See Also

[ISwDMDimXpertDistanceBetweenDimTol Members](#)
[SolidWorks.Interop.swdocumentmgr Namespace](#)

ISwDMDimXpertDistanceBetweenDimTol Interface Methods

[See Also](#)



[SolidWorks.Interop.swdocumentmgr Namespace](#) : ISwDMDimXpertDistanceBetweenDimTol Interface

For a list of all members of this type, see [ISwDMDimXpertDistanceBetweenDimTol members](#).

Public Methods

Name	Description
 GetDirectionVector	Gets the direction vector for this DimXpert distance-between dimension tolerance.
 GetFeature	Gets the DimXpert feature to which this DimXpert distance-between dimension tolerance is applied.
 GetOriginFeature	Gets the DimXpert feature of origin for this DimXpert distance-between dimension tolerance.



[Top](#)

See Also

[ISwDMDimXpertDistanceBetweenDimTol Interface](#)
[SolidWorks.Interop.swdocumentmgr Namespace](#)

SOLIDWORKS Document Manager API Help

[Send comments](#) on this topic.

ISwDMDimXpertDistanceBetweenDimTol Interface Members

[See Also](#) [Properties](#) [Methods](#)



[SolidWorks.Interop.swdocumentmgr Namespace](#) : ISwDMDimXpertDistanceBetweenDimTol Interface

The following tables list the members exposed by [ISwDMDimXpertDistanceBetweenDimTol](#).

Public Properties

Name	Description
 PatternTreatment	Gets the pattern treatment for this DimXpert distance-between dimension tolerance.

[Top](#)

Public Methods

Name	Description
 GetDirectionVector	Gets the direction vector for this DimXpert distance-between dimension tolerance.
 GetFeature	Gets the DimXpert feature to which this DimXpert distance-between dimension tolerance is applied.
 GetOriginFeature	Gets the DimXpert feature of origin for this DimXpert distance-between dimension tolerance.

[Top](#)

See Also

[ISwDMDimXpertDistanceBetweenDimTol Interface](#)
[SolidWorks.Interop.swdocumentmgr Namespace](#)

SOLIDWORKS Document Manager API Help

[Send comments](#) on this topic.

ISwDMDimXpertDistanceBetweenDimTol Interface Properties

[See Also](#)



[SolidWorks.Interop.swdocumentmgr Namespace](#) : ISwDMDimXpertDistanceBetweenDimTol Interface

For a list of all members of this type, see [ISwDMDimXpertDistanceBetweenDimTol members](#).

Public Properties

Name	Description
 PatternTreatment	Gets the pattern treatment for this DimXpert distance-between dimension tolerance.

[Top](#)

See Also

[ISwDMDimXpertDistanceBetweenDimTol Interface](#)
[SolidWorks.Interop.swdocumentmgr Namespace](#)

SOLIDWORKS Document Manager API Help

[Send comments](#) on this topic.

GetDirectionVector Method (ISwDMDimXpertDistanceBetweenDimTol)

[See Also](#)



[SolidWorks.Interop.swdocumentmgr Namespace](#) > [ISwDMDimXpertDistanceBetweenDimTol Interface](#) : GetDirectionVector Method (ISwDMDimXpertDistanceBetweenDimTol)

Gets the direction vector for this DimXpert distance-between dimension tolerance.

.NET Syntax

Visual Basic (Declaration)

```
Function GetDirectionVector( _
    ByRef I As System.Double, _
    ByRef J As System.Double, _
    ByRef K As System.Double _
) As System.Boolean
```

Visual Basic (Usage)



```
Dim instance As ISwDMDimXpertDistanceBetweenDimTol
Dim I As System.Double
Dim J As System.Double
Dim K As System.Double
Dim value As System.Boolean

value = instance.GetDirectionVector(I, J, K)
```

C#

```
System.bool GetDirectionVector(
    out System.double I,
    out System.double J,
    out System.double K
)
```

C++/CLI

```
System.bool GetDirectionVector(
    & [Out] System.double I,
    & [Out] System.double J,
    & [Out] System.double K
)
```

Parameters

I
i component of direction vector
J
j component of direction vector
K
k component of direction vector

Return Value

True if method call is successful; false otherwise

Visual Basic for Applications (VBA) Syntax

See [SwDMDimXpertDistanceBetweenDimTol::GetDirectionVector](#).

Example

See the examples on the interface page.

See Also

[ISwDMDimXpertDistanceBetweenDimTol Interface](#)
[ISwDMDimXpertDistanceBetweenDimTol Members](#)

Availability

SOLIDWORKS 2010 FCS, Revision Number 18.0

SOLIDWORKS Document Manager API Help

[Send comments on this topic.](#)

GetFeature Method (ISwDMDimXpertDistanceBetweenDimTol)

[See Also](#)



[SolidWorks.Interop.swdocumentmgr Namespace](#) > [ISwDMDimXpertDistanceBetweenDimTol Interface](#) : GetFeature Method (ISwDMDimXpertDistanceBetweenDimTol)

Gets the DimXpert feature to which this DimXpert distance-between dimension tolerance is applied.

Visual Basic Syntax

Visual Basic (Declaration)

```
Function GetFeature( _  
    ByRef Feature As SwDMDimXpertFeature, _  
    ByRef FosUsage As swDmDimXpertDistanceFosUsage\_e _  
) As System.Boolean
```

Visual Basic (Usage)



```
Dim instance As ISwDMDimXpertDistanceBetweenDimTol  
Dim Feature As SwDMDimXpertFeature  
Dim FosUsage As swDmDimXpertDistanceFosUsage\_e  
Dim value As System.Boolean  
  
value = instance.GetFeature(Feature, FosUsage)
```

C#

```
System.bool GetFeature(  
    out SwDMDimXpertFeature Feature,  
    out swDmDimXpertDistanceFosUsage\_e FosUsage  
)
```

C++/CLI

```
System.bool GetFeature(  
& [Out] SwDMDimXpertFeature^ Feature,  
& [Out] swDmDimXpertDistanceFosUsage\_e FosUsage  
)
```

Parameters

Feature

[ISwDMDimXpertFeature](#)

FosUsage

How to treat the feature of size when applying this tolerance as defined in [swDmDimXpertDistanceFosUsage_e](#)

Return Value

True if method call is successful; false otherwise

Visual Basic for Applications (VBA) Syntax

See [SwDMDimXpertDistanceBetweenDimTol::GetFeature](#).

Example

See the examples on the interface page.

See Also

[ISwDMDimXpertDistanceBetweenDimTol Interface](#)

[ISwDMDimXpertDistanceBetweenDimTol Members](#)

Availability

SOLIDWORKS 2010 FCS, Revision Number 18.0

SOLIDWORKS Document Manager API Help

[Send comments on this topic.](#)

GetOriginFeature Method (ISwDMDimXpertDistanceBetweenDimTol)

[See Also](#)



[SolidWorks.Interop.swdocumentmgr Namespace](#) > [ISwDMDimXpertDistanceBetweenDimTol Interface](#) : GetOriginFeature Method (ISwDMDimXpertDistanceBetweenDimTol)

Gets the DimXpert feature of origin for this DimXpert distance-between dimension tolerance.

Visual Basic Syntax

Visual Basic (Declaration)

```
Function GetOriginFeature( _  
    ByRef Feature As SwMDimXpertFeature, _  
    ByRef FosUsage As swDmDimXpertDistanceFosUsage\_e _  
    ) As System.Boolean
```

Visual Basic (Usage)



```
Dim instance As ISwMDimXpertDistanceBetweenDimTol  
Dim Feature As SwMDimXpertFeature  
Dim FosUsage As swDmDimXpertDistanceFosUsage\_e  
Dim value As System.Boolean  
  
value = instance.GetOriginFeature(Feature, FosUsage)
```

C#

```
System.bool GetOriginFeature(  
    out SwMDimXpertFeature Feature,  
    out swDmDimXpertDistanceFosUsage\_e FosUsage  
)
```

C++/CLI

```
System.bool GetOriginFeature(  
& [Out] SwMDimXpertFeature^ Feature,  
& [Out] swDmDimXpertDistanceFosUsage\_e FosUsage  
)
```

Parameters

Feature

[ISwMDimXpertFeature](#)

FosUsage

How to treat the feature of size when applying this tolerance as defined in [swDmDimXpertDistanceFosUsage_e](#)

Return Value

True if method call is successful; false otherwise

Visual Basic for Applications (VBA) Syntax

See [SwMDimXpertDistanceBetweenDimTol::GetOriginFeature](#).

Example

See the examples on the interface page.

See Also

[ISwMDimXpertDistanceBetweenDimTol Interface](#)

[ISwMDimXpertDistanceBetweenDimTol Members](#)

Availability

SOLIDWORKS 2010 FCS, Revision Number 18.0

SOLIDWORKS Document Manager API Help

[Send comments on this topic.](#)

PatternTreatment Property (ISwMDimXpertDistanceBetweenDimTol)

[See Also](#)



[SolidWorks.Interop.swdocumentmgr Namespace](#) > [ISwMDimXpertDistanceBetweenDimTol Interface](#) : PatternTreatment Property (ISwMDimXpertDistanceBetweenDimTol)

Gets the pattern treatment for this DimXpert distance-between dimension tolerance.

.NET Syntax

Visual Basic (Declaration)

ReadOnly Property PatternTreatment As [swDmDimXpertPatternTreatmentType_e](#)

Visual Basic (Usage)



```
Dim instance As ISwDMDimXpertDistanceBetweenDimTol  
Dim value As swDmDimXpertPatternTreatmentType\_e
```

```
value = instance.PatternTreatment
```

C#

```
swDmDimXpertPatternTreatmentType\_e PatternTreatment {get;}
```

C++/CLI

```
property swDmDimXpertPatternTreatmentType\_e PatternTreatment {  
    swDmDimXpertPatternTreatmentType\_e get();  
}
```

Property Value

Pattern treatment for the diameter dimension tolerance as defined in [swDmDimXpertPatternTreatmentType_e](#)

Visual Basic for Applications (VBA) Syntax

See [SwDMDimXpertDistanceBetweenDimTol::PatternTreatment](#).

Example

See the examples on the interface page.

See Also

[ISwDMDimXpertDistanceBetweenDimTol Interface](#)
[ISwDMDimXpertDistanceBetweenDimTol Members](#)

Availability

SOLIDWORKS 2010 FCS, Revision Number 18.0

ISwDMDimXpertExtrudeFeature (Type)

ISwDMDimXpertExtrudeFeature Interface

[See Also](#) [Members](#) [Example](#)



[SolidWorks.Interop.swdocumentmgr Namespace](#) : ISwDMDimXpertExtrudeFeature Interface

Allows you to access specific information about DimXpert extrudes.

NOTE: Click the **Members** link, located near the top of the topic, to see this interface's methods and properties.

Visual Basic Syntax

Visual Basic (Declaration)

Public Interface ISwDMDimXpertExtrudeFeature

Visual Basic (Usage)

Dim instance As [ISwDMDimXpertExtrudeFeature](#)

C#

public interface ISwDMDimXpertExtrudeFeature

C++/CLI

public interface class ISwDMDimXpertExtrudeFeature

Visual Basic for Applications (VBA) Syntax

See [SwDMDimXpertExtrudeFeature](#).

Example

[Get DimXpert Extrude Feature \(VB.NET\)](#)
[Get DimXpert Extrude Feature \(C#\)](#)

Remarks

You can access more general information from [ISwDMDimXpertFeature](#).

Accessors

[ISwDMDimXpertPart::GetFeatures](#) and [ISwDMDimXpertPart::IGetFeatures](#)

See Also

[ISwDMDimXpertExtrudeFeature Members](#)
[SolidWorks.Interop.swdocumentmgr Namespace](#)

ISwDMDimXpertExtrudeFeature Interface Members

[See Also](#) [Properties](#) [Methods](#)



[SolidWorks.Interop.swdocumentmgr Namespace](#) : ISwDMDimXpertExtrudeFeature Interface

The following tables list the members exposed by [ISwDMDimXpertExtrudeFeature](#).

Public Properties

Name	Description
 Blind	Gets whether this DimXpert extrude is blind or through all.

[Top](#)

Public Methods

Name	Description
 GetBottomBlends	Gets the DimXpert blend feature at the bottom of this DimXpert extrude.
 GetBottomFeature	Gets the DimXpert feature at the bottom of this DimXpert extrude.
 GetReferenceFeature	Gets the DimXpert reference feature for this DimXpert extrude.
 GetSubFeatureCount	Gets the number of sub-features in this DimXpert extrude.
 GetSubFeatures	Gets all of the sub-features of this DimXpert extrude.
 GetTopBlends	Gets the DimXpert blend feature at the top of this DimXpert extrude.
 IGetSubFeatures	Gets all of the sub-features of this DimXpert extrude.

[Top](#)

See Also

[ISwMDMDimXpertExtrudeFeature Interface](#)
[SolidWorks.Interop.swdocumentmgr Namespace](#)

SOLIDWORKS Document Manager API Help

[Send comments on this topic.](#)

ISwMDMDimXpertExtrudeFeature Interface Methods

[See Also](#)



[SolidWorks.Interop.swdocumentmgr Namespace](#) : ISwMDMDimXpertExtrudeFeature Interface

For a list of all members of this type, see [ISwMDMDimXpertExtrudeFeature members](#).

Public Methods

Name	Description
 GetBottomBlends	Gets the DimXpert blend feature at the bottom of this DimXpert extrude.
 GetBottomFeature	Gets the DimXpert feature at the bottom of this DimXpert extrude.
 GetReferenceFeature	Gets the DimXpert reference feature for this DimXpert extrude.
 GetSubFeatureCount	Gets the number of sub-features in this DimXpert extrude.
 GetSubFeatures	Gets all of the sub-features of this DimXpert extrude.
 GetTopBlends	Gets the DimXpert blend feature at the top of this DimXpert extrude.
 IGetSubFeatures	Gets all of the sub-features of this DimXpert extrude.

[Top](#)

See Also

[ISwMDMDimXpertExtrudeFeature Interface](#)
[SolidWorks.Interop.swdocumentmgr Namespace](#)

SOLIDWORKS Document Manager API Help

[Send comments on this topic.](#)

ISwMDMDimXpertExtrudeFeature Interface Properties

[See Also](#)



[SolidWorks.Interop.swdocumentmgr Namespace](#) : ISwMDMDimXpertExtrudeFeature Interface

For a list of all members of this type, see [ISwMDMDimXpertExtrudeFeature members](#).

Public Properties

Name	Description
 Blind	Gets whether this DimXpert extrude is blind or through all.

[Top](#)

See Also

Blind Property (ISwMDimXpertExtrudeFeature)

[See Also](#)



[SolidWorks.Interop.swdocumentmgr Namespace](#) > [ISwMDimXpertExtrudeFeature Interface](#) : Blind Property (ISwMDimXpertExtrudeFeature)

Gets whether this DimXpert extrude is blind or through all.

.NET Syntax

Visual Basic (Declaration)

```
ReadOnly Property Blind As System.Boolean
```

Visual Basic (Usage)



```
Dim instance As ISwMDimXpertExtrudeFeature  
Dim value As System.Boolean  
  
value = instance.Blind
```

C#

```
System.bool Blind {get;}
```

C++/CLI

```
property System.bool Blind {  
    System.bool get();  
}
```

Property Value

True if the extrude is blind; false if through all

Visual Basic for Applications (VBA) Syntax

See [SwMDimXpertExtrudeFeature::Blind](#).

Example

See the examples on the interface page.

See Also

[ISwMDimXpertExtrudeFeature Interface](#)
[ISwMDimXpertExtrudeFeature Members](#)

Availability

SOLIDWORKS 2010 FCS, Revision Number 18.0

GetBottomBlends Method (ISwMDimXpertExtrudeFeature)

[See Also](#)



[SolidWorks.Interop.swdocumentmgr Namespace](#) > [ISwMDimXpertExtrudeFeature Interface](#) : GetBottomBlends Method (ISwMDimXpertExtrudeFeature)

Gets the DimXpert blend feature at the bottom of this DimXpert extrude.

.NET Syntax

Visual Basic (Declaration)

```
Function GetBottomBlends() As SwMDimXpertFeature
```

Visual Basic (Usage)

```
Dim instance As ISwDMDimXpertExtrudeFeature  
Dim value As SwDMDimXpertFeature  
  
value = instance.GetBottomBlends()
```

C#

```
SwDMDimXpertFeature GetBottomBlends()
```

C++/CLI

```
SwDMDimXpertFeature^ GetBottomBlends();
```

Return Value

[ISwDMDimXpertFeature](#)

Visual Basic for Applications (VBA) Syntax

See [SwDMDimXpertExtrudeFeature::GetBottomBlends](#).

Example

See the examples on the interface page.

Remarks

The bottom blend is typically an [ISwDMDimXpertFilletFeature](#).

See Also

[ISwDMDimXpertExtrudeFeature Interface](#)
[ISwDMDimXpertExtrudeFeature Members](#)

Availability

SOLIDWORKS 2010 FCS, Revision Number 18.0

SOLIDWORKS Document Manager API Help

[Send comments](#) on this topic.

GetBottomFeature Method (ISwDMDimXpertExtrudeFeature)

[See Also](#)



[SolidWorks.Interop.swdocumentmgr Namespace](#) > [ISwDMDimXpertExtrudeFeature Interface](#) : GetBottomFeature Method (ISwDMDimXpertExtrudeFeature)

Gets the DimXpert feature at the bottom of this DimXpert extrude.

.NET Syntax

Visual Basic (Declaration)

```
Function GetBottomFeature() As SwDMDimXpertFeature
```

Visual Basic (Usage)

```
Dim instance As ISwDMDimXpertExtrudeFeature  
Dim value As SwDMDimXpertFeature  
  
value = instance.GetBottomFeature()
```

C#

```
SwDMDimXpertFeature GetBottomFeature()
```

C++/CLI

```
SwDMDimXpertFeature^ GetBottomFeature();
```

Return Value

[ISwDMDimXpertFeature](#)

Visual Basic for Applications (VBA) Syntax

See [SwDMDimXpertExtrudeFeature::GetBottomFeature](#).

Example

See the examples on the interface page.

See Also

[ISwDMDimXpertExtrudeFeature Interface](#)
[ISwDMDimXpertExtrudeFeature Members](#)

Availability

SOLIDWORKS 2010 FCS, Revision Number 18.0

SOLIDWORKS Document Manager API Help

[Send comments on this topic.](#)

GetReferenceFeature Method (ISwDMDimXpertExtrudeFeature)

[See Also](#)



[SolidWorks.Interop.swdocumentmgr Namespace](#) > [ISwDMDimXpertExtrudeFeature Interface](#) : GetReferenceFeature Method (ISwDMDimXpertExtrudeFeature)

Gets the DimXpert reference feature for this DimXpert extrude.

.NET Syntax

Visual Basic (Declaration)

```
Function GetReferenceFeature() As SwDMDimXpertFeature
```

Visual Basic (Usage)



```
Dim instance As ISwDMDimXpertExtrudeFeature  
Dim value As SwDMDimXpertFeature  
  
value = instance.GetReferenceFeature()
```

C#

```
SwDMDimXpertFeature GetReferenceFeature()
```

C++/CLI

```
SwDMDimXpertFeature^ GetReferenceFeature();
```

Return Value

[ISwDMDimXpertFeature](#)

Visual Basic for Applications (VBA) Syntax

See [SwDMDimXpertExtrudeFeature::GetReferenceFeature](#).

Example

See the examples on the interface page.

See Also

[ISwDMDimXpertExtrudeFeature Interface](#)
[ISwDMDimXpertExtrudeFeature Members](#)

Availability

SOLIDWORKS 2010 FCS, Revision Number 18.0

SOLIDWORKS Document Manager API Help

[Send comments on this topic.](#)

GetSubFeatureCount Method (ISwDMDimXpertExtrudeFeature)

[See Also](#)



[SolidWorks.Interop.swdocumentmgr Namespace](#) > [ISwDMDimXpertExtrudeFeature Interface](#) : GetSubFeatureCount Method (ISwDMDimXpertExtrudeFeature)

Gets the number of sub-features in this DimXpert extrude.

.NET Syntax

Visual Basic (Declaration)

```
Function GetSubFeatureCount() As System.Integer
```

Visual Basic (Usage)



```
Dim instance As ISwDMDimXpertExtrudeFeature  
Dim value As System.Integer
```

```
value = instance.GetSubFeatureCount()
```

C#

```
System.int GetSubFeatureCount()
```

C++/CLI

```
System.int GetSubFeatureCount();
```

Return Value

Number of sub-features in the extrude

Visual Basic for Applications (VBA) Syntax

See [SwDMDimXpertExtrudeFeature::GetSubFeatureCount](#).

Example

See the examples on the interface page.

See Also

[ISwDMDimXpertExtrudeFeature Interface](#)
[ISwDMDimXpertExtrudeFeature Members](#)

Availability

SOLIDWORKS 2010 FCS, Revision Number 18.0

SOLIDWORKS Document Manager API Help

[Send comments on this topic.](#)

GetSubFeatures Method (ISwDMDimXpertExtrudeFeature)

[See Also](#)



[SolidWorks.Interop.swdocumentmgr Namespace](#) > [ISwDMDimXpertExtrudeFeature Interface](#) : GetSubFeatures Method (ISwDMDimXpertExtrudeFeature)

Gets all of the sub-features of this DimXpert extrude.

.NET Syntax

Visual Basic (Declaration)

```
Function GetSubFeatures() As System.Object
```

Visual Basic (Usage)



```
Dim instance As ISwMDimXpertExtrudeFeature  
Dim value As System.Object  
  
value = instance.GetSubFeatures()
```

C#

```
System.Object GetSubFeatures()
```

C++/CLI

```
System.Object^ GetSubFeatures();
```

Return Value

Array of [ISwMDimXpertFeatures](#)

Visual Basic for Applications (VBA) Syntax

See [SwMDimXpertExtrudeFeature::GetSubFeatures](#).

Example

See the examples on the interface page.

See Also

[ISwMDimXpertExtrudeFeature Interface](#)
[ISwMDimXpertExtrudeFeature Members](#)
[ISwMDimXpertExtrudeFeature::IGetSubFeatures Method](#)

Availability

SOLIDWORKS 2010 FCS, Revision Number 18.0

SOLIDWORKS Document Manager API Help

[Send comments](#) on this topic.

GetTopBlends Method (ISwMDimXpertExtrudeFeature)

[See Also](#)



[SolidWorks.Interop.swdocumentmgr Namespace](#) > [ISwMDimXpertExtrudeFeature Interface](#) : GetTopBlends Method (ISwMDimXpertExtrudeFeature)

Gets the DimXpert blend feature at the top of this DimXpert extrude.

.NET Syntax

Visual Basic (Declaration)

```
Function GetTopBlends() As SwMDimXpertFeature
```

Visual Basic (Usage)



```
Dim instance As ISwMDimXpertExtrudeFeature  
Dim value As SwMDimXpertFeature  
  
value = instance.GetTopBlends()
```

C#

```
SwMDimXpertFeature GetTopBlends()
```

C++/CLI

```
SwDMDimXpertFeature^ GetTopBlends();
```

Return Value

[ISwDMDimXpertFeature](#)

Visual Basic for Applications (VBA) Syntax

See [SwDMDimXpertExtrudeFeature::GetTopBlends](#).

Example

See the examples on the interface page.

Remarks

The top blend is typically an [ISwDMDimXpertFilletFeature](#).

See Also

[ISwDMDimXpertExtrudeFeature Interface](#)
[ISwDMDimXpertExtrudeFeature Members](#)

Availability

SOLIDWORKS 2010 FCS, Revision Number 18.0

SOLIDWORKS Document Manager API Help

[Send comments on this topic.](#)

IGetSubFeatures Method (ISwDMDimXpertExtrudeFeature)

[See Also](#)



[SolidWorks.Interop.swdocumentmgr Namespace](#) > [ISwDMDimXpertExtrudeFeature Interface](#) : IGetSubFeatures Method (ISwDMDimXpertExtrudeFeature)

Gets all of the sub-features of this DimXpert extrude.

.NET Syntax

Visual Basic (Declaration)

```
Function IGetSubFeatures( _  
    ByVal Count As System.Integer _  
) As SwDMDimXpertFeature
```

Visual Basic (Usage)



```
Dim instance As ISwDMDimXpertExtrudeFeature  
Dim Count As System.Integer  
Dim value As SwDMDimXpertFeature  
  
value = instance.IGetSubFeatures(Count)
```

C#

```
SwDMDimXpertFeature IGetSubFeatures(  
    System.int Count  
)
```

C++/CLI

```
SwDMDimXpertFeature^ IGetSubFeatures(  
& System.int Count  
)
```

Parameters

Count

Number of sub-features in the extrude

Return Value

- in-process, unmanaged C++: Pointer to an array of [SwMDimXpertFeatures](#)
- VBA, VB.NET, C#, and C++/CLI: Not supported

Remarks

Use [ISwMDimXpertExtrudeFeature::GetSubFeatureCount](#) to populate the Count argument.

See Also

[ISwMDimXpertExtrudeFeature Interface](#)
[ISwMDimXpertExtrudeFeature Members](#)
[ISwMDimXpertExtrudeFeature::GetSubFeatures Method](#)

Availability

SOLIDWORKS 2010 FCS, Revision Number 18.0

ISwDMDimXpertFeature (Type)

SOLIDWORKS Document Manager API Help

[Send comments](#) on this topic.

ISwDMDimXpertFeature Interface

[See Also](#) [Members](#) [Example](#)



[SolidWorks.Interop.swdocumentmgr.Namespace](#) : ISwDMDimXpertFeature Interface

Allows you to access general information about DimXpert features and sub-features.

NOTE: Click the **Members** link, located near the top of the topic, to see this interface's methods and properties.

.NET Syntax

Visual Basic (Declaration)

```
Public Interface ISwDMDimXpertFeature
```

Visual Basic (Usage)



```
Dim instance As ISwDMDimXpertFeature
```

C#

```
public interface ISwDMDimXpertFeature
```

C++/CLI

```
public interface class ISwDMDimXpertFeature
```

Visual Basic for Applications (VBA) Syntax

See [SwDMDimXpertFeature](#).

Example

[Get DimXpert Sphere and Datum \(VB.NET\)](#)
[Get DimXpert Sphere and Datum \(C#\)](#)

Remarks

This interface is the base class for several more specific DimXpert feature interfaces (see the **See Also** section). Use the [ISwDMDimXpertFeature::type](#) property to find out which specific feature interface is needed to acquire more information for a given DimXpert feature.

Accessors

[ISwDMDimXpertAngleBetweenDimTol::OriginFeature](#)

[ISwDMDimXpertAnnotation::Feature](#)

[ISwDMDimXpertBestFitPlaneFeature::GetSubFeatures](#) and [ISwDMDimXpertBestFitPlaneFeature::!GetSubFeatures](#)

[ISwDMDimXpertCompositeDistanceBetweenDimTol::GetFeature](#), [ISwDMDimXpertCompositeDistanceBetweenDimTol::GetIntraFeature](#),
[ISwDMDimXpertCompositeDistanceBetweenDimTol::GetOriginFeature](#)

[ISwDMDimXpertCompoundClosedSlot3DFeature::GetBottomFeature](#) and [ISwDMDimXpertCompoundClosedSlot3DFeature::GetEndFeatures](#)

[ISwDMDimXpertCompoundHoleFeature::GetBottomFeature](#), [ISwDMDimXpertCompoundHoleFeature::GetReferenceFeature](#),
[ISwDMDimXpertCompoundHoleFeature::GetSubFeatures](#), [ISwDMDimXpertCompoundHoleFeature::!GetSubFeatures](#)

[ISwDMDimXpertCompoundNotchFeature::GetBottomFeature](#), [ISwDMDimXpertCompoundNotchFeature::GetEndFeature](#),
[ISwDMDimXpertCompoundNotchFeature::GetOpenSideReferenceFeature](#), [ISwDMDimXpertCompoundNotchFeature::GetTopReferenceFeature](#)

[ISwDMDimXpertCounterBoreDimTol::ReferenceFeature](#) property

[ISwDMDimXpertCounterSinkAngleDimTol::ReferenceFeature](#) property

[ISwDMDimXpertCounterSinkDiameterDimTol::ReferenceFeature](#) property

[ISwDMDimXpertDepthDimTol::ReferenceFeature](#) property

[ISwDMDimXpertDistanceBetweenDimTol::GetFeature](#) and [ISwDMDimXpertDistanceBetweenDimTol::GetOriginFeature](#)

[ISwMDimXpertExtrudeFeature::GetBottomBlends](#), [ISwMDimXpertExtrudeFeature::GetTopBlends](#),
[ISwMDimXpertExtrudeFeature::GetBottomFeature](#), [ISwMDimXpertExtrudeFeature::GetReferenceFeature](#),
[ISwMDimXpertExtrudeFeature::GetSubFeatures](#), [ISwMDimXpertExtrudeFeature::!GetSubFeatures](#)

[ISwMDimXpertIntersectCircleFeature::GetIntersectFeature](#) and [ISwMDimXpertIntersectCircleFeature::GetPlaneFeature](#)

[ISwMDimXpertIntersectLineFeature::GetPlaneFeatures](#)

[ISwMDimXpertIntersectPlaneFeature::GetFeatures](#)

[ISwMDimXpertIntersectPointFeature::GetFeatures](#)

[ISwMDimXpertPart::GetFeatures](#) and [ISwMDimXpertPart::!GetFeatures](#)

[ISwMDimXpertPatternFeature::GetSubFeatures](#) and [ISwMDimXpertPatternFeature::!GetSubFeatures](#)

[ISwMDimXpertTangencyTolerance::GetOriginFeature](#) property

 See Also

- [ISwMDimXpertFeature Members](#)
- [SolidWorks.Interop.swdocumentmgr Namespace](#)
- [ISwMDimXpertBestFitPlaneFeature Interface](#)
- [ISwMDimXpertChamferFeature Interface](#)
- [ISwMDimXpertCompoundClosedSlot3dFeature Interface](#)
- [ISwMDimXpertCompoundHoleFeature Interface](#)
- [ISwMDimXpertCompoundNotchFeature Interface](#)
- [ISwMDimXpertCompoundWidthFeature Interface](#)
- [ISwMDimXpertConeFeature Interface](#)
- [ISwMDimXpertCylinderFeature Interface](#)
- [ISwMDimXpertExtrudeFeature Interface](#)
- [ISwMDimXpertFilletFeature Interface](#)
- [ISwMDimXpertIntersectCircleFeature Interface](#)
- [ISwMDimXpertIntersectLineFeature Interface](#)
- [ISwMDimXpertIntersectPlaneFeature Interface](#)
- [ISwMDimXpertIntersectPointFeature Interface](#)
- [ISwMDimXpertPatternFeature Interface](#)
- [ISwMDimXpertPlaneFeature Interface](#)
- [ISwMDimXpertSphereFeature Interface](#)
- [ISwMDimXpertSurfaceFeature Interface](#)

ISwMDimXpertFeature Interface Methods

[See Also](#)

 [SolidWorks.Interop.swdocumentmgr Namespace](#) : ISwMDimXpertFeature Interface

For a list of all members of this type, see [ISwMDimXpertFeature members](#).

 Public Methods

Name	Description
 GetCadIdentifierCount	Gets the number of CAD identifiers in this DimXpert feature.
 GetCadIdentifiers	Gets all of the CAD identifiers of this DimXpert feature.
 !GetCadIdentifiers	Gets all of the CAD identifiers of this DimXpert feature.
 IsSuppressed	Gets whether this DimXpert feature is suppressed from the view in the model.

[Top](#)

 See Also

- [ISwMDimXpertFeature Interface](#)
- [SolidWorks.Interop.swdocumentmgr Namespace](#)
- [ISwMDimXpertBestFitPlaneFeature Interface](#)
- [ISwMDimXpertChamferFeature Interface](#)
- [ISwMDimXpertCompoundClosedSlot3dFeature Interface](#)
- [ISwMDimXpertCompoundHoleFeature Interface](#)
- [ISwMDimXpertCompoundNotchFeature Interface](#)
- [ISwMDimXpertCompoundWidthFeature Interface](#)
- [ISwMDimXpertConeFeature Interface](#)
- [ISwMDimXpertCylinderFeature Interface](#)
- [ISwMDimXpertExtrudeFeature Interface](#)
- [ISwMDimXpertFilletFeature Interface](#)
- [ISwMDimXpertIntersectCircleFeature Interface](#)
- [ISwMDimXpertIntersectLineFeature Interface](#)
- [ISwMDimXpertIntersectPlaneFeature Interface](#)
- [ISwMDimXpertIntersectPointFeature Interface](#)
- [ISwMDimXpertPatternFeature Interface](#)
- [ISwMDimXpertPlaneFeature Interface](#)
- [ISwMDimXpertSphereFeature Interface](#)
- [ISwMDimXpertSurfaceFeature Interface](#)

ISwMDimXpertFeature Interface Members

[See Also](#) [Properties](#) [Methods](#)

[SolidWorks.Interop.swdocumentmgr Namespace](#) : ISwMDMDimXpertFeature Interface

The following tables list the members exposed by [ISwMDMDimXpertFeature](#).

 Public Properties

Name	Description
 Name	Gets the name of this DimXpert feature.
 type	Gets the type of this DimXpert feature.

[Top](#)

 Public Methods

Name	Description
 GetCadIdentifierCount	Gets the number of CAD identifiers in this DimXpert feature.
 GetCadIdentifiers	Gets all of the CAD identifiers of this DimXpert feature.
 ICadIdentifiers	Gets all of the CAD identifiers of this DimXpert feature.
 IsSuppressed	Gets whether this DimXpert feature is suppressed from the view in the model.

[Top](#)

 See Also

[ISwMDMDimXpertFeature Interface](#)
[SolidWorks.Interop.swdocumentmgr Namespace](#)
[ISwMDMDimXpertBestFitPlaneFeature Interface](#)
[ISwMDMDimXpertChamferFeature Interface](#)
[ISwMDMDimXpertCompoundClosedSlot3dFeature Interface](#)
[ISwMDMDimXpertCompoundHoleFeature Interface](#)
[ISwMDMDimXpertCompoundNotchFeature Interface](#)
[ISwMDMDimXpertCompoundWidthFeature Interface](#)
[ISwMDMDimXpertConeFeature Interface](#)
[ISwMDMDimXpertCylinderFeature Interface](#)
[ISwMDMDimXpertExtrudeFeature Interface](#)
[ISwMDMDimXpertFilletFeature Interface](#)
[ISwMDMDimXpertIntersectCircleFeature Interface](#)
[ISwMDMDimXpertIntersectLineFeature Interface](#)
[ISwMDMDimXpertIntersectPlaneFeature Interface](#)
[ISwMDMDimXpertIntersectPointFeature Interface](#)
[ISwMDMDimXpertPatternFeature Interface](#)
[ISwMDMDimXpertPlaneFeature Interface](#)
[ISwMDMDimXpertSphereFeature Interface](#)
[ISwMDMDimXpertSurfaceFeature Interface](#)

ISwMDMDimXpertFeature Interface Properties

[See Also](#)

[SolidWorks.Interop.swdocumentmgr Namespace](#) : ISwMDMDimXpertFeature Interface

For a list of all members of this type, see [ISwMDMDimXpertFeature members](#).

 Public Properties

Name	Description
 Name	Gets the name of this DimXpert feature.
 type	Gets the type of this DimXpert feature.

[Top](#)

 See Also

[ISwMDMDimXpertFeature Interface](#)
[SolidWorks.Interop.swdocumentmgr Namespace](#)
[ISwMDMDimXpertBestFitPlaneFeature Interface](#)
[ISwMDMDimXpertChamferFeature Interface](#)
[ISwMDMDimXpertCompoundClosedSlot3dFeature Interface](#)
[ISwMDMDimXpertCompoundHoleFeature Interface](#)
[ISwMDMDimXpertCompoundNotchFeature Interface](#)
[ISwMDMDimXpertCompoundWidthFeature Interface](#)
[ISwMDMDimXpertConeFeature Interface](#)
[ISwMDMDimXpertCylinderFeature Interface](#)
[ISwMDMDimXpertExtrudeFeature Interface](#)
[ISwMDMDimXpertFilletFeature Interface](#)

[ISwDMDimXpertIntersectCircleFeature Interface](#)
[ISwDMDimXpertIntersectLineFeature Interface](#)
[ISwDMDimXpertIntersectPlaneFeature Interface](#)
[ISwDMDimXpertIntersectPointFeature Interface](#)
[ISwDMDimXpertPatternFeature Interface](#)
[ISwDMDimXpertPlaneFeature Interface](#)
[ISwDMDimXpertSphereFeature Interface](#)
[ISwDMDimXpertSurfaceFeature Interface](#)

SOLIDWORKS Document Manager API Help

[Send comments on this topic.](#)

GetCadIdentifierCount Method (ISwDMDimXpertFeature)

[See Also](#)



[SolidWorks.Interop.swdocumentmgr Namespace](#) > [ISwDMDimXpertFeature Interface](#) : GetCadIdentifierCount Method (ISwDMDimXpertFeature)

Gets the number of CAD identifiers in this DimXpert feature.

.NET Syntax

Visual Basic (Declaration)

```
Function GetCadIdentifierCount() As System.Integer
```

Visual Basic (Usage)



```
Dim instance As ISwDMDimXpertFeature  
Dim value As System.Integer
```

```
value = instance.GetCadIdentifierCount()
```

C#

```
System.int GetCadIdentifierCount()
```

C++/CLI

```
System.int GetCadIdentifierCount();
```

Return Value

Number of CAD identifiers

Visual Basic for Applications (VBA) Syntax

See [SwDMDimXpertFeature::GetCadIdentifierCount](#).

Example

See the examples on the interface page.

See Also

[ISwDMDimXpertFeature Interface](#)
[ISwDMDimXpertFeature Members](#)

Availability

SOLIDWORKS 2010 FCS, Revision Number 18.0

SOLIDWORKS Document Manager API Help

[Send comments on this topic.](#)

GetCadIdentifiers Method (ISwDMDimXpertFeature)

[See Also](#)



[SolidWorks.Interop.swdocumentmgr Namespace](#) > [ISwDMDimXpertFeature Interface](#) : GetCadIdentifiers Method (ISwDMDimXpertFeature)

Gets all of the CAD identifiers of this DimXpert feature.

.NET Syntax

Visual Basic (Declaration)

```
Function GetCadIdentifiers() As System.Object
```

Visual Basic (Usage)



```
Dim instance As ISwDMDimXpertFeature  
Dim value As System.Object
```

```
value = instance.GetCadIdentifiers()
```

C#

```
System.object GetCadIdentifiers()
```

C++/CLI

```
System.Object^ GetCadIdentifiers();
```

Return Value

Array of strings; the format of each string is bodyid:faceid

Visual Basic for Applications (VBA) Syntax

See [SwDMDimXpertFeature::GetCadIdentifiers](#).

Example

See the examples on the interface page.

See Also

[ISwDMDimXpertFeature Interface](#)
[ISwDMDimXpertFeature Members](#)
[ISwDMDimXpertFeature::IGetCadIdentifiers Method](#)

Availability

SOLIDWORKS 2010 FCS, Revision Number 18.0

SOLIDWORKS Document Manager API Help

[Send comments](#) on this topic.

IGetCadIdentifiers Method (ISwDMDimXpertFeature)

[See Also](#)



[SolidWorks.Interop.swdocumentmgr Namespace](#) > [ISwDMDimXpertFeature Interface](#) : IGetCadIdentifiers Method (ISwDMDimXpertFeature)

Gets all of the CAD identifiers of this DimXpert feature.

.NET Syntax

Visual Basic (Declaration)

```
Function IGetCadIdentifiers( _  
    ByVal Count As System.Integer _  
) As System.String
```

Visual Basic (Usage)



```
Dim instance As ISwDMDimXpertFeature  
Dim Count As System.Integer  
Dim value As System.String
```

```
value = instance.IGetCadIdentifiers(Count)
```

C#

```
System.string IGetCadIdentifiers(  
    System.int Count
```

)

C++/CLI

```
System.String^ IGetCadIdentifiers(  
& System.int Count  
)
```

Parameters

Count
Number of CAD identifiers

Return Value

- in-process, unmanaged C++: Pointer to an array of strings; the format of each string is bodyid:faceid
- VBA, VB.NET, C#, and C++/CLI: Not supported

Remarks

Use [ISwDMDimXpertFeature::GetCadIdentifierCount](#) to populate the Count argument.

See Also

[ISwDMDimXpertFeature Interface](#)
[ISwDMDimXpertFeature Members](#)
[ISwDMDimXpertFeature::GetCadIdentifiers Method](#)

Availability

SOLIDWORKS 2010 FCS, Revision Number 18.0

SOLIDWORKS Document Manager API Help

[Send comments on this topic.](#)

IsSuppressed Method (ISwDMDimXpertFeature)

[See Also](#)



[SolidWorks.Interop.swdocumentmgr Namespace](#) > [ISwDMDimXpertFeature Interface](#) : IsSuppressed Method (ISwDMDimXpertFeature)

Gets whether this DimXpert feature is suppressed from the view in the model.

.NET Syntax

Visual Basic (Declaration)

```
Function IsSuppressed() As System.Boolean
```

Visual Basic (Usage)



```
Dim instance As ISwDMDimXpertFeature  
Dim value As System.Boolean  
  
value = instance.IsSuppressed()
```

C#

```
System.bool IsSuppressed()
```

C++/CLI

```
System.bool IsSuppressed();
```

Return Value

True if the feature is suppressed from view; false if not

Visual Basic for Applications (VBA) Syntax

See [SwDMDimXpertFeature::IsSuppressed](#).

Example

See the examples on the interface page.

See Also

[ISwDMDimXpertFeature Interface](#)
[ISwDMDimXpertFeature Members](#)

Availability

SOLIDWORKS 2010 FCS, Revision Number 18.0

SOLIDWORKS Document Manager API Help

[Send comments on this topic.](#)

Name Property (ISwDMDimXpertFeature)

[See Also](#)



[SolidWorks.Interop.swdocumentmgr Namespace](#) > [ISwDMDimXpertFeature Interface](#) : Name Property (ISwDMDimXpertFeature)

Gets the name of this DimXpert feature.

.NET Syntax

Visual Basic (Declaration)

```
ReadOnly Property Name As System.String
```

Visual Basic (Usage)



```
Dim instance As ISwDMDimXpertFeature  
Dim value As System.String
```

```
value = instance.Name
```

C#

```
System.string Name {get;}
```

C++/CLI

```
property System.String^ Name {  
    System.String^ get();  
}
```

Property Value

Name of the feature

Visual Basic for Applications (VBA) Syntax

See [SwDMDimXpertFeature::Name](#).

Example

See the examples on the interface page.

See Also

[ISwDMDimXpertFeature Interface](#)
[ISwDMDimXpertFeature Members](#)

Availability

SOLIDWORKS 2010 FCS, Revision Number 18.0

SOLIDWORKS Document Manager API Help

[Send comments on this topic.](#)

type Property (ISwDMDimXpertFeature)

[See Also](#)



Gets the type of this DimXpert feature.

.NET Syntax

Visual Basic (Declaration)

ReadOnly Property type As [swDmDimXpertFeatureType_e](#)

Visual Basic (Usage)



```
Dim instance As ISwDMDimXpertFeature  
Dim value As swDmDimXpertFeatureType\_e  
  
value = instance.type
```

C#

```
swDmDimXpertFeatureType\_e type {get;}
```

C++/CLI

```
property swDmDimXpertFeatureType\_e type {  
    swDmDimXpertFeatureType\_e get();  
}
```

Property Value

Type of feature as defined in [swDmDimXpertFeatureType_e](#)

Visual Basic for Applications (VBA) Syntax

See [SwDMDimXpertFeature::type](#).

Example

See the examples on the interface page.

See Also

[ISwDMDimXpertFeature Interface](#)
[ISwDMDimXpertFeature Members](#)

Availability

SOLIDWORKS 2010 FCS, Revision Number 18.0

ISwDMDimXpertFilletFeature (Type)

ISwDMDimXpertFilletFeature Interface

[See Also](#) [Members](#) [Example](#)



[SolidWorks.Interop.swdocumentmgr Namespace](#) : ISwDMDimXpertFilletFeature Interface

Allows you to access specific information about DimXpert fillets.

NOTE: Click the **Members** link, located near the top of the topic, to see this interface's methods and properties.

.NET Syntax

Visual Basic (Declaration)

Public Interface ISwDMDimXpertFilletFeature

Visual Basic (Usage)



Dim instance As [ISwDMDimXpertFilletFeature](#)

C#

public interface ISwDMDimXpertFilletFeature

C++/CLI

public interface class ISwDMDimXpertFilletFeature

Visual Basic for Applications (VBA) Syntax

See [SwDMDimXpertFilletFeature](#).

Example

[Get DimXpert Feature \(VB.NET\)](#)
[Get DimXpert Feature \(C#\)](#)

Remarks

You can access more general information from [ISwDMDimXpertFeature](#).

Accessors

[ISwDMDimXpertPart::GetFeatures](#) and [ISwDMDimXpertPart::IGetFeatures](#)

See Also

[ISwDMDimXpertFilletFeature Members](#)
[SolidWorks.Interop.swdocumentmgr Namespace](#)

ISwDMDimXpertFilletFeature Interface Members

[See Also](#) [Properties](#)



[SolidWorks.Interop.swdocumentmgr Namespace](#) : ISwDMDimXpertFilletFeature Interface

The following tables list the members exposed by [ISwDMDimXpertFilletFeature](#).

Public Properties

Name	Description
Inner	Gets whether this DimXpert fillet is for a hole or a pin.
Radius	Gets the radius of this DimXpert fillet.

[Top](#)

See Also

[ISwDMDimXpertFilletFeature Interface](#)
[SolidWorks.Interop.swdocumentmgr Namespace](#)

SOLIDWORKS Document Manager API Help

[Send comments](#) on this topic.

ISwDMDimXpertFilletFeature Interface Properties

[See Also](#)



[SolidWorks.Interop.swdocumentmgr Namespace](#) : ISwDMDimXpertFilletFeature Interface

For a list of all members of this type, see [ISwDMDimXpertFilletFeature members](#).

Public Properties

Name	Description
 Inner	Gets whether this DimXpert fillet is for a hole or a pin.
 Radius	Gets the radius of this DimXpert fillet.

[Top](#)

See Also

[ISwDMDimXpertFilletFeature Interface](#)
[SolidWorks.Interop.swdocumentmgr Namespace](#)

SOLIDWORKS Document Manager API Help

[Send comments](#) on this topic.

Inner Property (ISwDMDimXpertFilletFeature)

[See Also](#)



[SolidWorks.Interop.swdocumentmgr Namespace](#) > [ISwDMDimXpertFilletFeature Interface](#) : Inner Property (ISwDMDimXpertFilletFeature)

Gets whether this DimXpert fillet is for a hole or a pin.

.NET Syntax

Visual Basic (Declaration)

```
ReadOnly Property Inner As System.Boolean
```

Visual Basic (Usage)



```
Dim instance As ISwDMDimXpertFilletFeature  
Dim value As System.Boolean  
  
value = instance.Inner
```

C#

```
System.bool Inner {get;}
```

C++/CLI

```
property System.bool Inner {  
    System.bool get();  
}
```

Property Value

True if the fillet is for a hole; false if for a pin

Visual Basic for Applications (VBA) Syntax

See [SwDMDimXpertFilletFeature::Inner](#).

Example

See the examples on the interface page.

See Also

[ISwDMDimXpertFilletFeature Interface](#)
[ISwDMDimXpertFilletFeature Members](#)

Availability

SOLIDWORKS 2010 FCS, Revision Number 18.0

SOLIDWORKS Document Manager API Help

[Send comments on this topic.](#)

Radius Property (ISwDMDimXpertFilletFeature)

[See Also](#)



[SolidWorks.Interop.swdocumentmgr Namespace](#) > [ISwDMDimXpertFilletFeature Interface](#) : Radius Property (ISwDMDimXpertFilletFeature)

Gets the radius of this DimXpert fillet.

.NET Syntax

Visual Basic (Declaration)

```
ReadOnly Property Radius As System.Double
```

Visual Basic (Usage)



```
Dim instance As ISwDMDimXpertFilletFeature  
Dim value As System.Double
```

```
value = instance.Radius
```

C#

```
System.double Radius {get;}
```

C++/CLI

```
property System.double Radius {  
    System.double get();  
}
```

Property Value

Radius of the fillet

Visual Basic for Applications (VBA) Syntax

See [SwDMDimXpertFilletFeature::Radius](#).

Example

See the examples on the interface page.

See Also

[ISwDMDimXpertFilletFeature Interface](#)
[ISwDMDimXpertFilletFeature Members](#)

Availability

SOLIDWORKS 2010 FCS, Revision Number 18.0

ISwDMDimXpertFlatnessGeoTol (Type)

ISwDMDimXpertFlatnessGeoTol Interface

[See Also](#) [Members](#) [Example](#)



[SolidWorks.Interop.swdocumentmgr.Namespace](#) : ISwDMDimXpertFlatnessGeoTol Interface

Allows you to access DimXpert flatness geometric tolerance information.

NOTE: Click the **Members** link, located near the top of the topic, to see this interface's methods and properties.

.NET Syntax

Visual Basic (Declaration)

```
Public Interface ISwDMDimXpertFlatnessGeoTol
```

Visual Basic (Usage)

```
Dim instance As ISwDMDimXpertFlatnessGeoTol
```

C#

```
public interface ISwDMDimXpertFlatnessGeoTol
```

C++/CLI

```
public interface class ISwDMDimXpertFlatnessGeoTol
```

Visual Basic for Applications (VBA) Syntax

See [SwDMDimXpertFlatnessGeoTol](#).

Example

[Get DimXpert Tolerance1 \(VB.NET\)](#)
[Get DimXpert Tolerance1 \(C#\)](#)

Remarks

You can access more general information from [ISwDMDimXpertGeometricTolerance](#).

Accessors

[ISwDMDimXpertPart::GetAnnotations](#) and [ISwDMDimXpertPart::!GetAnnotations](#)

See Also

[ISwDMDimXpertFlatnessGeoTol Members](#)
[SolidWorks.Interop.swdocumentmgr.Namespace](#)

ISwDMDimXpertFlatnessGeoTol Interface Members

[See Also](#) [Methods](#)



[SolidWorks.Interop.swdocumentmgr.Namespace](#) : ISwDMDimXpertFlatnessGeoTol Interface

The following tables list the members exposed by [ISwDMDimXpertFlatnessGeoTol](#).

Public Methods

Name	Description
GetPerUnitArea	Gets the per unit area of this flatness geometric tolerance.

[Top](#)

See Also

[ISwDMDimXpertFlatnessGeoTol Interface](#)
[SolidWorks.Interop.swdocumentmgr Namespace](#)

SOLIDWORKS Document Manager API Help

[Send comments](#) on this topic.

ISwDMDimXpertFlatnessGeoTol Interface Methods

[See Also](#)

[SolidWorks.Interop.swdocumentmgr Namespace](#) : ISwDMDimXpertFlatnessGeoTol Interface

For a list of all members of this type, see [ISwDMDimXpertFlatnessGeoTol members](#).

Public Methods

Name	Description
 GetPerUnitArea	Gets the per unit area of this flatness geometric tolerance.

[Top](#)

See Also

[ISwDMDimXpertFlatnessGeoTol Interface](#)
[SolidWorks.Interop.swdocumentmgr Namespace](#)

SOLIDWORKS Document Manager API Help

[Send comments](#) on this topic.

GetPerUnitArea Method (ISwDMDimXpertFlatnessGeoTol)

[See Also](#)



[SolidWorks.Interop.swdocumentmgr Namespace](#) > [ISwDMDimXpertFlatnessGeoTol Interface](#) : GetPerUnitArea Method (ISwDMDimXpertFlatnessGeoTol)

Gets the per unit area of this flatness geometric tolerance.

.NET Syntax

Visual Basic (Declaration)

```
Function GetPerUnitArea( _  
    ByRef Enabled As System.Boolean, _  
    ByRef Length As System.Double, _  
    ByRef width As System.Double, _  
    ByRef I As System.Double, _  
    ByRef J As System.Double, _  
    ByRef K As System.Double _  
) As System.Boolean
```

Visual Basic (Usage)



```
Dim instance As ISwDMDimXpertFlatnessGeoTol  
Dim Enabled As System.Boolean  
Dim Length As System.Double  
Dim width As System.Double  
Dim I As System.Double  
Dim J As System.Double  
Dim K As System.Double  
Dim value As System.Boolean  
  
value = instance.GetPerUnitArea(Enabled, Length, width, I, J, K)
```

C#

```
System.bool GetPerUnitArea(  
    out System.bool Enabled,  
    out System.double Length,  
    out System.double width,  
    out System.double I,  
    out System.double J,  
    out System.double K  
)
```

```

System.bool GetPerUnitArea(
& [Out] System.bool Enabled,
& [Out] System.double Length,
& [Out] System.double width,
& [Out] System.double I,
& [Out] System.double J,
& [Out] System.double K
)

```

Parameters

Enabled

True if per unit area flatness tolerance is in effect; false if not

Length

Length for per unit area

width

Width for per unit area

I

i component of length direction vector used to compute flatness per unit area

J

j component of length direction vector used to compute flatness per unit area

K

k component of length direction vector used to compute flatness per unit area

Return Value

True if method call is successful; false otherwise

Visual Basic for Applications (VBA) Syntax

See [SwDMDimXpertFlatnessGeoTol::GetPerUnitArea](#).

Example

See the examples on the interface page.

See Also

[ISwDMDimXpertFlatnessGeoTol Interface](#)

[ISwDMDimXpertFlatnessGeoTol Members](#)

Availability

SOLIDWORKS 2010 FCS, Revision Number 18.0