



Whisper Bridge

Talk anywhere. Type everywhere.


Android macOS Ubuntu Windows

ANDROID WALKTHROUGH

Talk on your phone. Type on your computer.

A five-step setup for Wispr Flow, Tailscale, and Whisper Bridge. Pair once, then send dictated text to your Mac, Ubuntu, or Windows computer from

THE SIMPLE VERSION



Secure anywhere with Tailscale. No port forwarding.

Unofficial companion for Wispr Flow. Whisper Bridge does not include a Wispr Flow subscription or Tailscale account.

whisperbridge.app | [Open source setup guide](#)



Install the three pieces.

Set these up once. The rest of this guide connects them together.

1

Wispr Flow

Voice dictation on your Android phone. Sign in and complete its onboarding before you continue.

[GET WISPR FLOW](#)

2

Tailscale

The secure private network for your phone and computer. Sign in to the same tailnet on both.

[GET TAILSCALE](#)

3

Whisper Bridge

Install the Android APK plus the matching receiver ZIP for your Mac, Ubuntu, or Windows computer.

[OPEN RELEASES](#)

Before moving on

- Wispr Flow creates text when you dictate.
- Tailscale says Connected on your phone and computer.
- The Whisper Bridge receiver is downloaded for your computer.

Tip: Tailscale is optional on a trusted home Wi-Fi network, but it is the recommended path for every remote connection.



Prepare your computer.

The receiver runs locally, accepts your paired phone, and places text in the field you selected on the computer.

macOS

DOUBLE-CLICK

```
mac-server/install.command
```

Approve Accessibility when macOS asks.

Ubuntu

RUN

```
./ubuntu-server/install.sh
```

The installer sets up the user service.

Windows

RUN IN POWERSHELL

```
windows-server\install.ps1
```

Allow it only on trusted Private networks.

1

Open the local receiver console

In a browser on the computer, visit:

```
http://localhost:9877
```

macOS needs Accessibility permission


When prompted, allow the receiver or its terminal in System Settings > Privacy & Security > Accessibility. This is what lets it paste into the field you clicked.

Keep the receiver running. The macOS installer creates a durable login item; Ubuntu uses a user-level service.



Pair once. Use anywhere.

Use the receiver's Tailscale pairing QR. It carries the private host, port, and token so you do not have to enter sensitive details by hand.



- 1 Open Whisper Bridge on Android and tap the gear.
- 2 Tap Scan, then scan the Tailscale QR from the receiver console.
- 3 Tap Test, then Save. Return to the Compose screen.

No camera scan?

Use Paste pairing link in Settings and paste the link copied from the receiver console.

Keep Tailscale Funnel off. Whisper Bridge should stay private to your tailnet.



Dictate. Share. Type.

Once paired, this is the whole routine. Switch profiles from the top of Whisper Bridge whenever you want to send text to a different computer.

1

Dictate

Speak into Wispr Flow.

2

Share

Use Android's Share action, then choose Whisper Bridge.

3

Select

Choose the target computer profile at the top of Compose.

4

Focus

Click the text field on the computer where the words should land.

5

Send

Tap Type. Use Enter for Return or Clipboard for copy only.

Quick fixes

Test fails: Confirm Tailscale is connected on both devices and scan the Tailscale QR again.

No text appears: Click the destination field first; on macOS, recheck Accessibility permission.

No share option: Reinstall Whisper Bridge, then check Android's More menu in the share sheet.

Need more help? Visit github.com/BrandonKNguyen192/whisperflow-bridge