



Whisper Bridge

Talk anywhere. Type everywhere.

Android macOS Ubuntu Windows

ANDROID WALKTHROUGH

Talk on your phone. Type on your computer.

A clean step-by-step setup for Wispr Flow, Tailscale, and Whisper Bridge. Pair once, then send dictated text — or steer the cursor — on your Mac, Ubuntu, or Windows computer.

THE SIMPLE VERSION

1

Speak

Wispr Flow

2

Share

Whisper Bridge

3

Type

Your computer

Secure anywhere with Tailscale. No port forwarding.

Unofficial companion for Wispr Flow. No Wispr Flow subscription or Tailscale account is included.

whisperbridge.app | [Open source setup guide](#)

Install the three pieces.

Set these up once. The rest of this guide connects them together.

1

Wispr Flow

Voice dictation on your Android phone. Finish onboarding first.

2

Tailscale

Sign in to the same tailnet on your phone and computer.

3

Whisper Bridge

Install the Android APK and the matching receiver ZIP.

[OPEN GITHUB RELEASES](#)

Before moving on

- Wispr Flow creates text when you dictate.
- Tailscale says Connected on both devices.
- The receiver ZIP is downloaded for your computer.

Tip: Tailscale is optional on trusted home Wi-Fi, but recommended for every remote connection.

Prepare your computer.

The receiver runs locally, accepts your paired phone, and places text in the field you selected.

macOS

DOUBLE-CLICK

`mac-server/
install.command`

Approve Accessibility.

Ubuntu

RUN

`./ubuntu-server/
install.sh`

Creates a user service.

Windows

RUN IN POWERSHELL

`windows-
server\install.ps1`

Python 3.12+; no console windows in v1.3.

1

Open the receiver console

Visit <http://localhost:9877> in a browser on the computer.

Permission and focus

macOS needs Accessibility permission. On every platform, click the destination text field before sending.

Keep the receiver running. macOS uses a login item; Ubuntu and Windows start at sign-in.


Pair once. Use anywhere.

Use the receiver's Tailscale pairing QR. It carries the private host, port, and token.

ON YOUR ANDROID

- 1 Open Whisper Bridge and tap the gear.
- 2 Tap Scan and scan the Tailscale QR.
- 3 Tap Test, then Save.

ON YOUR COMPUTER



Receiver console

Select the Tailscale QR at localhost:9877.

No camera scan?

Use Paste pairing link in Settings and paste the link copied from the receiver console.

Keep Tailscale Funnel off. Whisper Bridge should stay private to your tailnet.

Dictate. Share. Type.

Once paired, this is the whole routine. Switch profiles at the top whenever you want another computer.

1

Dictate

Speak into Wispr Flow.

2

Share

Use Android's Share action, then choose Whisper Bridge.

3

Select

Choose the target computer profile at the top.

4

Focus

Click the destination text field on the computer.

5

Send

Tap Type. Use Enter for Return or Clipboard for copy only.

Quick fixes

- | | |
|-------------------------|---|
| Test fails: | Confirm Tailscale is connected on both devices and scan the QR again. |
| No text appears: | Click the destination field first; on macOS, recheck Accessibility. |
| No share option: | Reinstall Whisper Bridge, then check Android's More menu. |

Need more help? github.com/BrandonKNguyen192/whisperflow-bridge

Trackpad + air mouse.

Steer the computer's cursor from the phone: move, click, drag, scroll, or tilt for air mouse.

Trackpad

Drag one finger to move. Tap to click, hold to drag, two fingers to scroll.

Mouse buttons

Left, Right, and Double send clicks. Drag holds the button; Up and Down scroll.

Air mouse

Press and hold Hold for air mouse, tilt the phone to steer, release to stop.

Tune the feel

Trackpad speed and air mouse sensitivity live in Settings; invert direction if needed.

If the cursor does not move, click a destination field first and confirm the receiver has mouse permissions.

Release the air mouse button to stop gyro control immediately.