

Install Docker Desktop on Windows

>Go to Google and type docker and here you will see docker documentation.

>From here you can download and install docker desktop.

>Click below and download that file and after that install it.

Docker Desktop for Windows - x86_64

System Requirements

- WSL version 2.1.5 or later. To check your version, see [WSL: Verification and setup](#)
- If you intend to use Enhanced Container Isolation, ensure you're using WSL version 2.6 or later. This is required because ECI depends on a Linux kernel version of at least 6.3.0, and WSL 2.6+ bundles Linux kernel version 6.6.
- Windows 10 64-bit: Enterprise, Pro, or Education version 22H2 (build 19045).
- Windows 11 64-bit: Enterprise, Pro, or Education version 23H2 (build 22631) or higher.
- Turn on the WSL 2 feature on Windows. For detailed instructions, refer to the [Microsoft documentation](#).
- The following hardware prerequisites are required to successfully run WSL 2 on Windows 10 or Windows 11:
 - 64-bit processor with [Second Level Address Translation \(SLAT\)](#)
 - 8GB system RAM
 - Enable hardware virtualization in BIOS/UEFI. For more information, see [Virtualization](#).

How to check WSL is installed or not


- Go to command prompt or power shell.
- Use command `wsl - --version`
- If wsl not installed then use below command
- `Wsl -- install`

```
Microsoft Windows [Version 10.0.19045.5737]
(c) Microsoft Corporation. All rights reserved.

C:\Users\kceprhwl --version
WSL version: 2.4.13.0
Kernel version: 5.15.167.4-1
WSLg version: 1.0.65
MSRDC version: 1.2.5716
Direct3D version: 1.611.1-81528511
DXCore version: 10.0.26100.1-240331-1435.ge-release
Windows version: 10.0.19045.5737


C:\Users\kceprhwl --install
```

- Next step turn on wsl 2 feature on windows.
- Click Control panel
- Select programs
- Select programs and features
- Click windows features on/off and check box windows subsystem for Linux follow screen shot below.




How to Check Virtualization is enabled or not

- Next step Enable hardware virtualization in BIOS.
- To check its enabled or not right click and select task manager and click performance and then see below screen either virtualization is enabled or not.



If virtualization is not enabled then you have to enable it from BIOS.

>When docker desktop is installed then it will look like this



Docker Interface look like this as you can see below.

