

EMS — Roles and Approvals

How roles, reporting and approvals work in the CareerMap Solutions Employee Management System · 5
October 2026

This document explains, in simple words, how EMS handles roles, reporting and approvals.

It is built the way you described:

- everybody works under somebody,
- the person above approves,
- and the Super Admin controls all of it.

Please read it, and tell us in the last section if anything should be different.

1. What you wanted, and how EMS does it


What you wanted	How EMS does it
The Super Admin controls roles and permissions. Nothing is fixed.	The Super Admin creates roles and decides what each role can do on one screen, gives roles to people, and sets who reports to whom (section 7).
Everybody works under somebody, and the person above decides.	The Super Admin sets who reports to whom. Approvals follow that (section 2).
Only the reporting manager approves leave. HR does not.	Leave always goes to the person the employee reports to (section 3).
Nobody does their own work, even if they are HR or Accounts.	Their own work goes to the person above them (section 4).
Every person with a role is also an employee, with two separate logins.	The Super Admin adds a role login on the employee's page, beside their employee login. Both are the same person (section 5).
HR negotiates salaries, so HR should see them.	HR can see salaries, but not change them, and not see their seniors' salaries. Accounts enters salaries (section 6).
The owner does not need anybody's approval.	The owner's leave is recorded directly (section 3).
Follow every employee from joining to leaving.	Each profile shows where the person is: onboarding, probation, confirmed, resigned, serving notice or left. HR takes each step; the reporting manager accepts a resignation (section 9).

Corrections, work from home, overtime and profile changes need an approval, and the company sets the rules.

Employees send these as Requests; the reporting manager or HR approves. Shift, overtime and leave rules are settings the company can change (section 10).

2. Everybody works under somebody

Every person in the company reports to **one** person. The Super Admin decides who reports to whom. People with a role, like HR, Accounts and managers, are part of this too.



An example. Each line goes up to the person who decides. An agent's leave goes to the Team Lead. The Team Lead's leave goes to the Sales Manager. The Sales Manager's leave goes to the Owner.

- **Only one person is marked as the owner.** Somebody whose manager has simply not been set yet is not treated as the owner.
- **Nobody gets missed.** If somebody has nobody above them, they show on a list for the Super Admin. Until the Super Admin places them, the Super Admin handles their requests.
- **The chart cannot go in a loop.** EMS stops "A reports to B" if B already reports to A.
- **Only the Super Admin moves people.** When HR adds a new joiner, HR chooses who they report to. After that, any change is made by the Super Admin, so nobody can take over somebody else's approvals by moving them.
- **Moving people is safe.** If somebody gets a new manager, their waiting requests go to the new manager, who is told. If a manager leaves the company, their team shows on the Super Admin's list until they are placed under somebody else. If a manager's login is turned off, their team's requests go to the Super Admin.

3. Who approves leave

Whose leave	Who approves it
Any employee	Their reporting manager , the person directly above them

A manager	The person above that manager
Somebody with nobody above them, or whose manager has left or cannot sign in	The Super Admin
When the manager is away	The Super Admin can approve instead of the manager, at any time
Cancelling leave that was already approved	The reporting manager, or the Super Admin
The owner	Nobody. It is recorded directly

- **HR does not approve leave.** HR can see all leave requests, give everybody their yearly leave, and correct a balance when needed.
- **Any person with people under them approves their leave**, whatever their role. For example, the Accounts Head approves the accountant's leave.
- Who approves when there is no manager, who stands in for the manager (the Super Admin, the manager's own manager, or nobody), and who can cancel approved leave can all be changed later by the Super Admin.

4. Nobody does their own work

The rule. A person who does HR, Accounts or Admin work can **never** do that work for themselves. People at the same level or below cannot do it for them either. **Only the people above them can.**

If the person directly above cannot do that kind of work, it goes up to the next person who can, and finally to the Super Admin. Nothing gets stuck. The owner's own items need nobody: they are recorded directly.

Work	For a normal employee	For somebody who does this work
Checking a bank account	Accounts	The person above that accountant, e.g. the Accounts Head. Not themselves, not another accountant
Correcting a leave balance	HR	The person above that HR person. Not another HR person at the same level
Checking a document (Aadhaar, PAN...)	HR or Admin	The person above them
Marking or correcting attendance	HR	The person above that HR person
Entering the monthly incentive	HR or Accounts	The person above them

Entering or changing a salary	Accounts	The person above that accountant
Confirming, extending probation, transferring, promoting, or completing the exit	HR	The person above that HR person
Approving leave	Their reporting manager	Their reporting manager

This rule applies to every role, including new roles the Super Admin creates. It cannot be turned off.

5. Two logins for people with a role

A person with a role (HR, Accounts, Admin, Manager or Reporting Manager) gets two logins:

Login	What it is for
Employee login	Their own things only: punch in and out, see their attendance, apply for leave, upload their documents, download their payslips, give their bank account.
Role login	The work of their role, for example HR work or Accounts work. Approving their team's leave is done here too.

- **Both logins belong to the same person.** The Super Admin adds the role login on that person's page (Employees → the person → Logins). This is how EMS knows it is the same person, so the rule in section 4 works from both logins.
- **Each login needs its own email address** and its own password. The person gets a one-time link to set it.
- **Signing in:** somebody with two logins signs in with the email of the login they want. Their Employee ID cannot choose between the two.
- The top of the screen always shows which login is open, for example "Signed in as HR" or "Signed in as Employee". On a phone it shows the role as a small label.
- The Super Admin can turn one login off; the other keeps working. When somebody leaves the company, **both logins are closed together**, and they stay closed.
- A login added by mistake, for example with a wrongly typed email, can be withdrawn before anybody uses it, and then added again correctly.
- Normal employees have just one login.

6. Salaries

Who	What they can do
HR	Agrees the salary with the employee. Can see salaries, but cannot change them, and cannot see the salaries of the people above them.

Accounts	Enters and changes salaries in EMS.
Everybody	Sees their own salary on their own payslips.

HR agrees a salary with the employee, and Accounts enters it. Every change is recorded in the audit log, and nobody can change their own salary.

Documents. HR checks everybody's documents, including those of the people above them. An offer letter shows the salary, so HR can read it there. The Super Admin can change whose documents HR sees on the Roles & Permissions screen.

7. The Super Admin controls roles

The Super Admin has a **Roles & Permissions** screen in Settings. From there, the Super Admin can:

- **Create a new role** with any name, for example "Finance Head" or "Team Lead".
- **Decide what each role can do** by ticking boxes, grouped by area: Employees, Salaries, Attendance, Leave, Payroll, Payslips, Documents, Reports, and Settings and users.
- **Decide whose information each role can see**, for employee records, salaries, attendance, leave, documents and payslips:

Choice	The role can see
Only their own	Only their own information
Their team	The people directly under them
Everybody under them	Everybody below them, at every level
Their department	Everybody in their department
Whole company, except seniors	Everybody, except the people above them. Useful for salaries
Whole company	Everybody

Payslips offer "Only their own" or "Whole company". Payroll and Reports always show the whole company, every salary included, so give them only to roles that should see every salary.

- **Give any role to any person**, in Settings → Users & Roles. A second login is added on the person's page (section 5).
- **Set who reports to whom** on the Company Tree screen, and the approval choices on the Approvals screen.
- **Set the order of roles**, for example HR comes under the Super Admin. A person can only give roles that are below their own.
- **Changes work straight away.** Nobody needs to log in again. Before saving, the screen shows what the role will be able to do.
- **"Reset to default"** puts one of the seven starting roles back to how it started.

Built-in safety. These are always on:

- The Super Admin role cannot be changed or deleted, and there is always at least one Super Admin.
- Nobody can change a role they have themselves.
- Nobody can give somebody a role that would let that person see more than they can see themselves.
- Nobody can reset the password of, or turn off, the login of somebody above them in the company tree.
- The seven starting roles cannot be deleted, only changed or reset. A role that somebody still has, or that other roles come under, cannot be deleted.
- EMS warns if one role could both prepare and approve the payroll.
- Every change is saved in the audit log: who changed what, and when.

8. The roles EMS starts with

EMS starts with these seven roles. The Super Admin can change any of them, except the Super Admin role itself.

Role	What they do
Super Admin	Everything: approves the payroll, sees reports and the audit log, manages settings, users, roles and who reports to whom.
Admin	Looks after employee records and documents.
HR	Employees from joining to leaving: onboarding, probation, transfers, promotions and exits. Attendance, documents and holidays. Sees all leave, gives the yearly leave and corrects balances, but does not approve leave. Enters monthly incentives. Sees salaries, except seniors' salaries.
Manager	Sees their team's attendance and leave. Approves the leave of the people under them, as everybody with people under them does.
Reporting Manager	The same as Manager.
Accounts	Enters salaries, prepares the monthly payroll, checks bank accounts, and downloads the bank transfer file.
Employee	Their own attendance, leave, payslips, documents and bank account.

Everybody with a role also gets an employee login for their own things (section 5). Anybody with people under them approves those people's leave. A login for somebody who is not on the staff, for example an outside administrator, can be made in Settings → Users; it is not part of the company tree.

9. From joining to leaving

EMS follows every employee from the day they join to the day they leave. Each employee's profile shows the stage they are at, and a history of every step.

Stage	What it means	Who moves them on
Joining soon	Their joining date is still ahead. They cannot punch in or apply for leave before it.	Nobody: it moves on by itself on the joining day
Onboarding	They have joined. Their profile shows a short checklist: login, documents, bank account, PAN and reporting manager. HR marks onboarding complete.	HR
On probation	Probation runs 6 months from joining. HR can extend it, with a reason the employee sees.	HR confirms or extends
Confirmed	Probation is over.	—
Transfer and promotion	HR moves them to another department, or gives them a new designation. Who they report to is still changed only by the Super Admin. A pay rise is entered by Accounts.	HR
Resigned	The employee hands in their resignation in EMS (My Profile), or HR records a resignation letter. They can take it back until it is accepted.	The employee
Serving notice	The person they report to accepts the resignation and sets the last working day. The notice period is 30 days to start.	Their reporting manager
Left	On or after the last working day, HR completes the exit and records why they left. (HR can also do it earlier, if the company relieves them early.) All their logins close, and payroll pays them up to their last working day.	HR

- **HR does not accept resignations.** The person the employee reports to does, as with leave. That person, or HR, can also call a resignation off if the employee decides to stay.
- **People already working here** when EMS starts are added as Confirmed, with the date they were confirmed.
- **HR's own steps**, like confirming or promoting an HR person, are done by the person above them (section 4). HR also cannot change the record of anybody above them in the company tree; the Super Admin does that.
- **A resignation stays private until it is accepted.** Only the employee, HR, their reporting manager and the Super Admin can see it. An HR person who works under that employee does not see it, and when an HR person resigns, the other HR people do not see it either. Everybody else sees it once it is accepted.
- **Somebody who was to join but does not come:** HR closes their record. No working day is recorded for them.

- **The dashboard helps.** HR sees who is joining, who is still being onboarded, whose probation ends within 30 days, who has resigned and who is past their last day. A manager sees the resignations waiting for them.
- The employee is told about every step, and every step is saved in the audit log.
- The Super Admin can change the probation length and the notice period in Settings → Employee Lifecycle.

10. Requests, shifts and pay extras

Besides leave, employees ask for other things in one place: **Requests**. Each kind goes to one person, who approves or rejects it. A rejection always says why.

Request	What it is for	Who decides, to start
Attendance correction	A check-in or check-out that is missing or wrong. Once approved, the day is corrected.	Their reporting manager
Work from home / On duty	Days away from the office (home, a client visit, travel). On those days they check in without the office location.	Their reporting manager
Overtime	Time worked past the shift. Only overtime that is approved is paid, with that month's salary.	Their reporting manager
Leave encashment	Unused leave turned into pay, for leave types that allow it.	HR
Profile change	A change to their own phone, address, emergency contact and other personal details.	HR

- **The Super Admin chooses** who decides each kind (the reporting manager or HR) in Settings → Approvals, and whether working from home still needs a location reading.
- **Shifts have rules.** For each shift: a grace period, when coming late or leaving early makes it a half day, the hours a full day and a half day need, and when overtime starts (after 30 minutes past the shift, to start). Late arrivals and overtime show on the attendance screen and in the reports.
- **Overtime pay** is off until you turn it on in Settings → Payroll Config, so nobody is paid overtime by surprise. Once on, it is twice an hour's pay to start; the rate, and whether it is worked out on the full salary or on Basic and DA, are set there too.
- **Each leave type has its own rules:** days of notice, the most days in one go, who can take it (for example, maternity leave for women), when a new joiner can use it, whether it is earned all at once or a little each month, half days (first half or second half), and whether it can be encashed and how many days a year. All of these are off until HR sets them.
- **Salary parts:** Accounts can add new earnings or deductions (a Site Allowance, a Bonus) and choose whether each counts for PF, ESI and professional tax. Bonus and Commission are there to start.
- **Loans and salary advances:** Accounts records the amount and how much to take back each month. It comes off the payslip every month until it is paid back.
- **Email:** every notice can also go by email, once the company's email account is connected to EMS. The Super Admin can keep any notice to the app only.

- **Reports** show each person only what their role lets them see. HR does not see payroll reports.

11. Other safety rules

- **Everything important is recorded.** Sign-ins, role changes, salary changes, payroll steps, documents opened and files downloaded all go into the audit log. Nobody can edit or delete it.
- **Everybody sets their own password.** There are no shared passwords. Each person gets a one-time link, valid for 72 hours, to set theirs.
- **Yearly leave is given in one step.** New joiners get leave for the months left in the year. People who have left get none. Unused leave carries forward, up to the limit set for each leave type.
- **Payroll is approved by the Super Admin.** Accounts prepares it; only the Super Admin approves it. Once approved, that month cannot be changed.
- **PF and the Labour Codes.** The new labour codes say PF must be worked out on at least half of the pay. EMS has a switch for this in Settings → Payroll Config, off to start. When your accountant confirms it applies, the Super Admin turns it on. The share (50%) can be changed if the government announces a new one. It applies from the next month's payroll. The Super Admin also chooses there which parts of the salary count for PF (Accounts can set it too, under Payroll → Components) (Basic and DA to start; Special Allowance too, if your accountant says so). HR records on each employee's record whether they are in the pension scheme (EPS), from their PF record, so these settings never change it.
- **Bank accounts are checked** before any salary is paid into them (a setting, on to start). An account an employee sends in needs a photo of a cancelled cheque or passbook page.

12. What happens next

1. Everything in this document is built, and tested for every role, on computer and on phone.
2. EMS goes live. The Super Admin then sets up who reports to whom, the roles, and the role logins, directly in EMS. You do not need to send us any data.

Is this what you wanted? If yes, please just confirm. If anything should be different, write it below, even small things.

Section	What should change