


AN Image of the completed topology



48. Back up the running configuration to a TFTP server (or equivalent), and back up the IOS image to a TFTP server.

```
Router>enable
Router#copy-config tftp
      ^
% Invalid input detected at '^' marker.

Router# copy running-config tftp
Address or name of remote host []? 10.10.10.10
Destination filename [Router-config]? r1-backup

Writing running-config....!!
[OK - 701 bytes]

701 bytes copied in 3.004 secs (233 bytes/sec)
Router#show flash:

System flash directory:
File      Length  Name/status
  3    33591768  c2900-universalk9-mz.SPA.151-4.M4.bin
  2     28282   sigdef-category.xml
  1     227537   sigdef-default.xml
[33847587 bytes used, 221896413 available, 255744000 total]
249856K bytes of processor board System flash (Read/Write)

Router#copy flash:
% Incomplete command.
Router#copy flash:c1900-universalk9-mz.SPA.152-4.M3.bin tftp
      ^
% Invalid input detected at '^' marker.

Router#copy flash:c2900-universalk9-mz.SPA.151-4.M4.bin tftp
      ^
% Invalid input detected at '^' marker.

Router#
```

Password Recovery

49. Simulate a lost enable/console password and carry out the password recovery procedure to regain access.

```
Router#reload
System configuration has been modified. Save? [yes/no]:yes
Building configuration...
[OK]
Proceed with reload? [confirm]c
Router#
Router#reload
Proceed with reload? [confirm]c
Router#
Router#reload
Proceed with reload? [confirm]c
Router#config t
Enter configuration commands, one per line.  End with CNTL/Z.
Router(config)#line console 0
Router(config-line)#password my password
Router(config-line)#login
Router(config-line)#line vty 0 4
Router(config-line)#password remotepass
Router(config-line)#login
Router(config-line)#end
Router#
%SYS-5-CONFIG_I: Configured from console by console

Router#reload
System configuration has been modified. Save? [yes/no]:yes
Building configuration...
[OK]
Proceed with reload? [confirm]c
Router#
```

Factory Reset

50. Perform a factory reset on the assigned device and confirm it boots with no saved configuration.

```
Router#copy running-config startup-config
Destination filename [startup-config]? work
%Error copying nvram:work (Invalid argument)
Router#write erase
Erasing the nvram filesystem will remove all configuration files! Continue?
[confirm]c
Router#
Router#write erase
Erasing the nvram filesystem will remove all configuration files! Continue?
[confirm]
[OK]
Erase of nvram: complete
%SYS-7-NV_BLOCK_INIT: Initialized the geometry of nvram
Router#reload
Proceed with reload? [confirm]
System Bootstrap, Version 15.1(4)M4, RELEASE SOFTWARE (fc1)
Technical Support: http://www.cisco.com/techsupport
Copyright (c) 2010 by cisco Systems, Inc.
Total memory size = 512 MB - On-board = 512 MB, DIMM0 = 0 MB
CISCO2911/K9 platform with 524288 Kbytes of main memory
Main memory is configured to 72/-1(On-board/DIMM0) bit mode with ECC disabled

Readonly ROMMON initialized

program load complete, entry point: 0x80803000, size: 0x1b340
program load complete, entry point: 0x80803000, size: 0x1b340

IOS Image Load Test

Digitally Signed Release Software
program load complete, entry point: 0x81000000, size: 0x3bcd3d8
Self decompressing the image :
##### [OK]
Smart Init is enabled
smart init is sizing iomem
      TYPE      MEMORY_REQ
Onboard devices &
  buffer pools  0x022F6000
-----
TOTAL:         0x022F6000
Rounded IOMEM up to: 36Mb.
Using 6 percent iomem. [36Mb/512Mb]

      Restricted Rights Legend

Use, duplication, or disclosure by the Government is
subject to restrictions as set forth in subparagraph
(c) of the Commercial Computer Software - Restricted
Rights clause at FAR sec. 52.227-19 and subparagraph
(c) (1) (ii) of the Rights in Technical Data and Computer
Software clause at DFARS sec. 252.227-7013.

      cisco Systems, Inc.
      170 West Tasman Drive
      San Jose, California 95134-1706
```

Restore

51. Restore the configuration and IOS image from your Task 48 backups, and confirm the device matches the original.

```
Router#copy tftp running-config
Address or name of remote host []? 10.10.10.10
Source filename []? r1-backup
Destination filename [running-config]?
```
