


TOPOLOGY



User EXEC Mode

```
PC0
Physical Config Desktop Programming Attributes
Terminal
170 West Tasman Drive
San Jose, California 95134-1706

Cisco IOS Software, C2900 Software (C2900-UNIVERSALK9-M), Version 15.1(4)M5, RELEASE
SOFTWARE (fc2) Technical Support: http://www.cisco.com/techsupport
Copyright (c) 1986-2007 by Cisco Systems, Inc.
Compiled Wed 18-Jul-07 04:52 by pt_team
Image text-base: 0x2100F918, data-base: 0x24729040

This product contains cryptographic features and is subject to United
States and local country laws governing import, export, transfer and
use. Delivery of Cisco cryptographic products does not imply
third-party authority to import, export, distribute or use encryption.
Importers, exporters, distributors and users are responsible for
compliance with U.S. and local country laws. By using this product you
agree to comply with applicable laws and regulations. If you are unable
to comply with U.S. and local laws, return this product immediately.

A summary of U.S. laws governing Cisco cryptographic products may be found at:
http://www.cisco.com/wwl/export/crypto/tool/stqrg.html

If you require further assistance please contact us by sending email to
export@cisco.com.

Cisco CISC02911/K9 (revision 1.0) with 491520K/32768K bytes of memory.
Processor board ID FTX162400KS
3 Gigabit Ethernet interfaces
DRAM configuration is 64 bits wide with parity disabled.
255K bytes of non-volatile configuration memory.
249856K bytes of ATA System CompactFlash 0 (Read/Write)


--- System Configuration Dialog ---

Would you like to enter the initial configuration dialog? [yes/no]: no

Press RETURN to get started!


Router>
```

SHOW COMMANDS



The screenshot shows a PC0 terminal window with a blue title bar and tabs for Physical, Config, Desktop, Programming, and Attributes. The Desktop tab is active, displaying a terminal window with a black background and white text. The terminal shows the command 'tracert' followed by a space and 'trace route to destination'. Below this, the prompt 'Router>' is followed by the command 'show ?'. This command displays a list of available show commands and their descriptions, including 'arp', 'cdp', 'class-map', 'clock', 'controllers', 'crypto', 'dot11', 'flash:', 'frame-relay', 'history', 'hosts', 'interfaces', 'ip', 'ipv6', 'lldp', 'policy-map', 'pppoe', 'privilege', 'protocols', 'queue', 'queueing', 'sessions', 'ssh', 'tcp', 'terminal', 'users', 'version', 'vlan-switch', and 'vtp'.

```
tracert trace route to destination
Router>
Router>show ?
  arp           Arp table
  cdp           CDP information
  class-map     Show QoS Class Map
  clock         Display the system clock
  controllers   Interface controllers status
  crypto        Encryption module
  dot11         IEEE 802.11 show information
  flash:        display information about flash: file system
  frame-relay   Frame-Relay information
  history       Display the session command history
  hosts         IP domain-name, lookup style, nameservers, and host table
  interfaces    Interface status and configuration
  ip            IP information
  ipv6          IPv6 information
  lldp          LLDP information
  policy-map    Show QoS Policy Map
  pppoe         PPPoE information
  privilege     Show current privilege level
  protocols     Active network routing protocols
  queue         Show queue contents
  queueing      Show queueing configuration
  sessions      Information about Telnet connections
  ssh           Status of SSH server connections
  tcp           Status of TCP connections
  terminal      Display terminal configuration parameters
  users         Display information about terminal lines
  version       System hardware and software status
  vlan-switch   VTP VLAN status
  vtp           Configure VLAN database
```



The screenshot shows a PC0 terminal window with a blue title bar and tabs for Physical, Config, Desktop, Programming, and Attributes. The Desktop tab is active, displaying a terminal window with a black background and white text. The terminal shows the command 'show version' followed by its output. The output includes information about the Cisco IOS Software version (C2900 Software (C2900-UNIVERSALK9-M), Version 15.1(4)M4, RELEASE SOFTWARE (fc2)), technical support URL, copyright information, ROM version, system uptime, system image file, last reload type, and a summary of U.S. laws governing Cisco cryptographic products. It also includes information about the processor board ID, memory, and license information.

```
% Incomplete command.
Router>show version
Cisco IOS Software, C2900 Software (C2900-UNIVERSALK9-M), Version 15.1(4)M4, RELEASE
SOFTWARE (fc2)
Technical Support: http://www.cisco.com/techsupport
Copyright (c) 1986-2012 by Cisco Systems, Inc.
Compiled Thurs 5-Jan-12 15:41 by pt_team

ROM: System Bootstrap, Version 15.1(4)M4, RELEASE SOFTWARE (fc1)
cisco2911 uptime is 6 minutes, 26 seconds
System returned to ROM by power-on
System image file is "flash0:c2900-universalk9-mz.SPA.151-1.M4.bin"
Last reload type: Normal Reload

This product contains cryptographic features and is subject to United
States and local country laws governing import, export, transfer and
use. Delivery of Cisco cryptographic products does not imply
third-party authority to import, export, distribute or use encryption.
Importers, exporters, distributors and users are responsible for
compliance with U.S. and local country laws. By using this product you
agree to comply with applicable laws and regulations. If you are unable
to comply with U.S. and local laws, return this product immediately.

A summary of U.S. laws governing Cisco cryptographic products may be found at:
http://www.cisco.com/wll/export/crypto/tool/stqrg.html

If you require further assistance please contact us by sending email to
export@cisco.com.
Cisco CISC02911/K9 (revision 1.0) with 491520K/32768K bytes of memory.
Processor board ID FTX152400KS
3 Gigabit Ethernet interfaces
DRAM configuration is 64 bits wide with parity disabled.
255K bytes of non-volatile configuration memory.
249856K bytes of ATA System CompactFlash 0 (Read/Write)

License Info:

License UDI:

-----
Device# PID SN
-----
```

Privileged EXEC Mode

```
Router>
Router>show history
show
show version
show history
Router>enable
Router#
```

Global Configuration Mode

```
Router(config)#?
Configure commands:
aaa                Authentication, Authorization and Accounting.
access-list        Add an access list entry
banner             Define a login banner
bba-group          Configure BBA Group
boot              Modify system boot parameters
cdp               Global CDP configuration subcommands
class-map          Configure Class Map
clock             Configure time-of-day clock
config-register    Define the configuration register
crypto            Encryption module
default           Set a command to its defaults
do               To run exec commands in config mode
dot11             IEEE 802.11 config commands
enable            Modify enable password parameters
end              Exit from configure mode
exit             Exit from configure mode
flow             Global Flow configuration subcommands
hostname          Set system's network name
interface         Select an interface to configure
ip              Global IP configuration subcommands
ipv6            Global IPv6 configuration commands
--More--
```

```
Router#copy running-config startup-config
Destination filename [startup-config]?
Building configuration...
[OK]
```

[illegible]