


Week 7

Topology Screen Shot



IP for PCs

PC1

Physical

Config

Desktop

Programming

Attributes

IP Configuration

X

Interface

FastEthernet0

IP Configuration

DHCP

Static

IPv4 Address

10.0.1.10

Subnet Mask

255.0.0.0

Default Gateway

0.0.0.0

DNS Server

0.0.0.0

IPv6 Configuration

Automatic

Static

IPv6 Address

/

Link Local Address

FE80::240:BFF:FE20:946

Default Gateway

DNS Server

802.1X

Use 802.1X Security

Authentication

MD5

Username

Password

Top

PC2

Physical

Config

Desktop

Programming

Attributes

IP Configuration

X

Interface

FastEthernet0

IP Configuration

DHCP

Static

IPv4 Address

10.0.2.10

Subnet Mask

255.0.0.0

Default Gateway

0.0.0.0

DNS Server

0.0.0.0

IPv6 Configuration

Automatic

Static

IPv6 Address

/

Link Local Address

FE80::240:BFF:FEE5:5528

Default Gateway

DNS Server

802.1X

Use 802.1X Security


Authentication

MD5


Username



Password



Top



Task 52: Hostname change







Task 53: Configure IP on R1

```
Router>enable
Router#configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#hostname R1
R1(config)#
R1(config)#
R1(config)#enable
% Incomplete command.
R1(config)#configure terminal
      ^
% Invalid input detected at '^' marker.

R1(config)#interface fastethernet 0/0
R1(config-if)#ip address 10.0.0.1 255.255.255.0
R1(config-if)#no shutdown

R1(config-if)#exit
%LINK-5-CHANGED: Interface FastEthernet0/0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0, changed state to up

R1(config)#interface fastethernet 0/1
R1(config-if)#ip address 10.0.1.1 255.255.255.0
R1(config-if)#no shutdown

R1(config-if)#exit
%LINK-5-CHANGED: Interface FastEthernet0/1, changed state to up

R1(config)#interface fastethernet 1/0
R1(config-if)#ip address 10.0.2.1 255.255.255.0
      ^
% Invalid input detected at '^' marker.

R1(config-if)#no shutdown

R1(config-if)#exit
%LINK-5-CHANGED: Interface FastEthernet1/0, changed state to up

R1(config)#interface fastethernet 1/1
R1(config-if)#ip address 10.0.3.1 255.255.255.0
      ^
% Invalid input detected at '^' marker.

R1(config-if)#no shutdown

R1(config-if)#exit
R1(config)#end
%LINK-3-UPDOWN: Interface FastEthernet1/1, changed state to down
```

%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0, changed state to up

```
R1(config)#interface fastethernet 0/1
R1(config-if)#ip address 10.0.1.1 255.255.255.0
R1(config-if)#no shutdown
```

```
R1(config-if)#exit
%LINK-5-CHANGED: Interface FastEthernet0/1, changed state to up
```

```
R1(config)#interface fastethernet 1/0
R1(config-if)#ip address 10.0.2.1 255.255.255.0
      ^
```

% Invalid input detected at '^' marker.

```
R1(config-if)#no shutdown
```

```
R1(config-if)#exit
%LINK-5-CHANGED: Interface FastEthernet1/0, changed state to up
```

```
R1(config)#interface fastethernet 1/1
R1(config-if)#ip address 10.0.3.1 255.255.255.0
      ^
```

% Invalid input detected at '^' marker.


```
R1(config-if)#no shutdown
```

```
R1(config-if)#exit
R1(config)#end
%LINK-3-UPDOWN: Interface FastEthernet1/1, changed state to down
```

```
R1#
%SYS-5-CONFIG_I: Configured from console by console
```

```
R1#show ip interface brief
Interface      IP-Address      OK? Method Status      Protocol
FastEthernet0/0 10.0.0.1        YES manual up          up
FastEthernet0/1 10.0.1.1        YES manual up          down
Serial0/0/0      unassigned      YES unset administratively down down
Serial0/0/1      unassigned      YES unset administratively down down
Serial0/1/0      unassigned      YES unset administratively down down
Serial0/1/1      unassigned      YES unset administratively down down
FastEthernet1/0  unassigned      YES unset up          down
FastEthernet1/1  unassigned      YES unset down         down
FastEthernet1/2  unassigned      YES unset administratively down down
FastEthernet1/3  unassigned      YES unset administratively down down
FastEthernet1/4  unassigned      YES unset administratively down down
FastEthernet1/5  unassigned      YES unset administratively down down
FastEthernet1/6  unassigned      YES unset administratively down down
FastEthernet1/7  unassigned      YES unset administratively down down
FastEthernet1/8  unassigned      YES unset administratively down down
FastEthernet1/9  unassigned      YES unset administratively down down
FastEthernet1/10 unassigned      YES unset administratively down down
FastEthernet1/11 unassigned      YES unset administratively down down
FastEthernet1/12 unassigned      YES unset administratively down down
FastEthernet1/13 unassigned      YES unset administratively down down
FastEthernet1/14 unassigned      YES unset administratively down down
--More--
```

Task 57:



```
R2>enable
R2#configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
R2(config)#
R2(config)#interface fastethernet 0/0
R2(config-if)#ip address 10.0.0.2 255.255.255.0
R2(config-if)#no shutdown

R2(config-if)#exit
R2(config)#
R2(config)#interface fastethernet 0/1
R2(config-if)#ip address 10.1.0.2 255.255.255.0
R2(config-if)#no shutdown

R2(config-if)#exit
R2(config)#
R2(config)#end
%LINK-5-CHANGED: Interface FastEthernet0/0, changed state to up


%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0,
changed state to up

%LINK-5-CHANGED: Interface FastEthernet0/1, changed state to up

R2#
%SYS-5-CONFIG_I: Configured from console by console
```

Copy Paste

Top



The image shows a window titled 'R3' with a dark header bar. Below the header, there are four tabs: 'Physical', 'Config', 'CLI', and 'Attributes'. The 'CLI' tab is selected and highlighted. The main area of the window contains a terminal-like interface with a white background and black text. The text shows a sequence of commands and their outputs in a network device configuration session. At the bottom of the window, there are two buttons: 'Copy' and 'Paste'.

```
R3>enable
R3#configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
R3(config)#
R3(config)#interface fastethernet 0/0
R3(config-if)#ip address 10.1.1.2 255.255.255.0
R3(config-if)#no shutdown

R3(config-if)#exit
R3(config)#
R3(config)#interface fastethernet 0/1
R3(config-if)#ip address 10.1.0.1 255.255.255.0
R3(config-if)#no shutdown

R3(config-if)#exit
R3(config)#
R3(config)#end
%LINK-5-CHANGED: Interface FastEthernet0/0, changed state to up

%LINK-5-CHANGED: Interface FastEthernet0/1, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/1,
changed state to up
```

Copy Paste

```
R4
R4>enable
R4#configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
R4(config)#
R4(config)#interface fastethernet 0/0
R4(config-if)#ip address 10.1.1.1 255.255.255.0
R4(config-if)#no shutdown

R4(config-if)#exit
R4(config)#
R4(config)#interface fastethernet 0/1
R4(config-if)#ip address 10.1.2.1 255.255.255.0
R4(config-if)#no shutdown

R4(config-if)#exit
R4(config)#
R4(config)#interface fastethernet 1/0
%Invalid interface type and number
R4(config)#ip address 10.1.3.1 255.255.255.0
^
% Invalid input detected at '^' marker.

R4(config)#no shutdown
^
% Invalid input detected at '^' marker.

R4(config)#exit
R4#
```

Copy Paste

Top

Task 58:

```
Cisco Packet Tracer PC Command Line 1.0
C:\>ping 10.1.2.1

Pinging 10.1.2.1 with 32 bytes of data:

Reply from 10.1.2.1: bytes=32 time<1ms TTL=255
Reply from 10.1.2.1: bytes=32 time<1ms TTL=255
Reply from 10.1.2.1: bytes=32 time<1ms TTL=255
Reply from 10.1.2.1: bytes=32 time<1ms TTL=255

Ping statistics for 10.1.2.1:
    Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
    Approximate round trip times in milli-seconds:
        Minimum = 0ms, Maximum = 1ms, Average = 0ms
```

Task 59:

```
R1>enable
R1#configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
R1(config)#
R1(config)#ip route 10.1.0.0 255.255.255.0 10.0.0.2
R1(config)#ip route 10.1.1.0 255.255.255.0 10.0.0.2
R1(config)#ip route 10.1.2.0 255.255.255.0 10.0.0.2
R1(config)#ip route 10.1.3.0 255.255.255.0 10.0.0.2
R1(config)#
R1(config)#end
```

```

R2>enable
R2#configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
R2(config)#
R2(config)#ip route 10.0.1.0 255.255.255.0 10.0.0.1
R2(config)#ip route 10.0.2.0 255.255.255.0 10.0.0.1
R2(config)#ip route 10.0.3.0 255.255.255.0 10.0.0.1
R2(config)#
R2(config)#ip route 10.1.1.0 255.255.255.0 10.1.0.1
R2(config)#ip route 10.1.2.0 255.255.255.0 10.1.0.1
R2(config)#ip route 10.1.3.0 255.255.255.0 10.1.0.1
R2(config)#

```

```

R3>enable
R3#configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
R3(config)#
R3(config)#ip route 10.0.0.0 255.255.255.0 10.1.0.2
R3(config)#ip route 10.0.1.0 255.255.255.0 10.1.0.2
R3(config)#ip route 10.0.2.0 255.255.255.0 10.1.0.2
R3(config)#ip route 10.0.3.0 255.255.255.0 10.1.0.2
R3(config)#
R3(config)#ip route 10.1.2.0 255.255.255.0 10.1.1.1
R3(config)#ip route 10.1.3.0 255.255.255.0 10.1.1.1
R3(config)#

```


```

R4>enable
R4#configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
R4(config)#
R4(config)#ip route 10.0.0.0 255.255.255.0 10.1.1.2
R4(config)#ip route 10.0.1.0 255.255.255.0 10.1.1.2
R4(config)#ip route 10.0.2.0 255.255.255.0 10.1.1.2
R4(config)#ip route 10.0.3.0 255.255.255.0 10.1.1.2
R4(config)#

```

Task 60:

Task 61:



```

C:\>ping 10.1.2.10

Pinging 10.1.2.10 with 32 bytes of data:

Request timed out.
Request timed out.
Request timed out.
Request timed out.

Ping statistics for 10.1.2.10:
    Packets: Sent = 4, Received = 0, Lost = 4 (100% loss),

C:\>

```


Task 62:

```


R1#enable
R1#configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
R1(config)#ip route 10.1.0.0 255.255.252.0 10.0.0.2
R1(config)#end

```

Task 63:



Task 64:



Task 65:

```
C:\>tracert 10.1.3.2

Tracing route to 10.1.3.2 over a maximum of 30 hops:

  1  *          *          *          Request timed out.
  2  *          *          *          Request timed out.
  3  *          *          *          Request timed out.
  4  *          *          *          Request timed out.
  5  *          *          *          Request timed out.
  6  *          *          *          Request timed out.
  7  *          *          *          Request timed out.
  8  *          *          *          Request timed out.
```

Task 66:

```
R1(config)#ip route 10.1.3.0 255.255.255.0 10.0.3.2
```

Task 67:

Task 68:

```
R4(config-if)#ip address 203.0.113.1 255.255.255.0
R4(config-if)#no shutdown

R4#show ip interface brief
Interface          IP-Address      OK? Method Status          Protocol
GigabitEthernet0/1 unassigned      YES NVRAM   administratively down  down
FastEthernet2/3    unassigned      YES unset    up              up
FastEthernet2/4    10.1.2.1        YES manual  up              up
FastEthernet2/5    203.0.113.1    YES manual  up              up
FastEthernet2/6    10.1.3.1        YES manual  up              up
GigabitEthernet2/1 unassigned      YES unset   down            down
GigabitEthernet2/2 unassigned      YES unset   down            down
Dot11Radio2/1      unassigned      YES NVRAM   administratively down  down
Vlan1              unassigned      YES NVRAM   up              up
R4#
```