

Screenshots showing you in User EXEC mode, Privileged EXEC mode, and Global Configuration mode (with the prompt visible in each).

```
Terminal
Switch> ?
Exec commands:
  connect      Open a terminal connection
  disable      Turn off privileged commands
  disconnect    Disconnect an existing network connection
  enable        Turn on privileged commands
  exit          Exit from the EXEC
  logout        Exit from the EXEC
  ping          Send echo messages
  resume        Resume an active network connection
  show          Show running system information
  ssh           Open a secure shell client connection
  telnet        Open a telnet connection
  terminal      Set terminal line parameters
  traceroute    Trace route to destination
Switch> t?
telnet terminal traceroute
Switch> te?
telnet terminal
Switch> ?
Exec commands:
  connect      Open a terminal connection
  disable      Turn off privileged commands
  disconnect    Disconnect an existing network connection
  enable        Turn on privileged commands
  exit          Exit from the EXEC
  logout        Exit from the EXEC
  ping          Send echo messages
  resume        Resume an active network connection
  show          Show running system information
  ssh           Open a secure shell client connection
  telnet        Open a telnet connection
  terminal      Set terminal line parameters
  traceroute    Trace route to destination
Switch> en
Switch> enable
Switch#?
Exec commands:
  clear        Reset functions
  clock         Manage the system clock
  configure     Enter configuration mode
  connect       Open a terminal connection
  copy          Copy from one file to another
  debug         Debugging functions (see also 'undebug')
  delete        Delete a file
  dir           List files on a filesystem
  disable       Turn off privileged commands
  disconnect    Disconnect an existing network connection
  enable        Turn on privileged commands
  erase         Erase a filesystem
  exit          Exit from the EXEC
  logout        Exit from the EXEC
  more          Display the contents of a file
  no           Disable debugging informations
  ping          Send echo messages
  reload        Halt and perform a cold restart
  resume        Resume an active network connection
  setup         Run the SETUP command facility
  show          Show running system information
Switch#configure
Configuring from terminal, memory, or network [terminal]?
Enter configuration commands, one per line. End with CNTL/Z.
Switch(config)#
```

```

Exec commands:
connect      Open a terminal connection
disable      Turn off privileged commands
disconnect   Disconnect an existing network connection
enable       Turn on privileged commands
exit         Exit from the EXEC
logout       Exit from the EXEC
ping         Send echo messages
resume       Resume an active network connection
show         Show running system information
ssh          Open a secure shell client connection
telnet       Open a telnet connection
terminal     Set terminal line parameters
traceroute   Trace route to destination

Switch> en
Switch> enable
Switch#?
Exec commands:
clear        Reset functions
clock        Manage the system clock
configure    Enter configuration mode
connect      Open a terminal connection
copy         Copy from one file to another
debug        Debugging functions (see also 'undebug')
delete       Delete a file
dir          List files on a filesystem
disable      Turn off privileged commands
disconnect   Disconnect an existing network connection
enable       Turn on privileged commands
erase        Erase a filesystem
exit         Exit from the EXEC
logout       Exit from the EXEC
more         Display the contents of a file
no           Disable debugging informations
ping         Send echo messages
reload       Halt and perform a cold restart
resume       Resume an active network connection
setup        Run the SETUP command facility
show         Show running system information

Switch#configure
Configuring from terminal, memory, or network [terminal]?
Enter configuration commands, one per line.  End with CNTL/Z.
Switch(config)#exit
Switch#
*SYS-5-CONFIG_I: Configured from console by console

Switch#show clock
*0:31:10.983 UTC Mon Mar 1 1993
Switch#clock
% Incomplete command.
Switch#clock set
% Incomplete command.
Switch#clock ?
    set  Set the time and date
Switch#clock set ?
    hh:mm:ss  Current Time
Switch#clock set 15:00:00 ?
    <1-31>  Day of the month
    MONTH  Month of the year
Switch#clock set 15:00:00 31 jan 2035
Switch#show clock
15:0:16.577 UTC Wed Jan 31 2035
Switch#

```

```
Terminal
Importers, exporters, distributors and users are responsible for
compliance with U.S. and local country laws. By using this product you
agree to comply with applicable laws and regulations. If you are unable
to comply with U.S. and local laws, return this product immediately.
A summary of U.S. laws governing Cisco cryptographic products may be found at:
http://www.cisco.com/wwl/export/crypto/tool/stqrg.html
If you require further assistance please contact us by sending email to
export@cisco.com.
Cisco WS-C2960-24TT-L (PowerPC405) processor (revision B0) with 65536K bytes of
memory.
Processor board ID FOC1010X104
Last reset from power-on
1 Virtual Ethernet interface
24 FastEthernet interfaces
2 Gigabit Ethernet interfaces
The password-recovery mechanism is enabled.
64K bytes of flash-simulated non-volatile configuration memory.
Base ethernet MAC Address      : 00:00:0C:07:37:A2
Motherboard assembly number    : 73-10390-03
Power supply part number       : 341-0097-02
Motherboard serial number      : FOC10093R12
Power supply serial number     : AZS1007032H
Model revision number          : B0
Motherboard revision number    : B0
Model number                   : WS-C2960-24TT-L
System serial number           : FOC1010X104
Top Assembly Part Number       : 800-27221-02
Top Assembly Revision Number   : A0
Version ID                     : V02
CLEI Code Number               : COM3L00BRA
Hardware Board Revision Number : 0x01

Switch Ports Model          SW Version        SW Image
-----
* 1 26 WS-C2960-24TT-L 15.0(2)SE4       C2960-LANBASEK9-M

Cisco IOS Software, C2960 Software (C2960-LANBASEK9-M), Version 15.0(2)SE4, RELEASE
SOFTWARE (rcl)
Technical Support: http://www.cisco.com/techsupport
Copyright (c) 1986-2013 by Cisco Systems, Inc.
Compiled Wed 26-Jun-13 02:49 by mnguyen

Press RETURN to get started!

Switch> ?
Exec commands:
connect      Open a terminal connection
disable      Turn off privileged commands
disconnect   Disconnect an existing network connection
enable       Turn on privileged commands
exit         Exit from the EXEC
logout       Exit from the EXEC
ping         Send echo messages
resume       Resume an active network connection
show         Show running system information
ssh          Open a secure shell client connection
telnet       Open a telnet connection
terminal     Set terminal line parameters
traceroute   Trace route to destination
Switch>
```

A screenshot of your completed topology in Packet Tracer/GNS3.

