

```

24 FastEthernet interfaces
2 Gigabit Ethernet interfaces
The password-recovery mechanism is enabled.
64K bytes of flash-simulated non-volatile configuration memory.
Base ethernet MAC Address       : 00:01:43:53:0B:A1
Motherboard assembly number     : 73-10390-03
Power supply part number        : 341-0097-02
Motherboard serial number       : FOC10093R12
Power supply serial number      : AZS1007032H
Model revision number           : B0
Motherboard revision number     : B0
Model number                    : WS-C2960-24TT-L
System serial number            : FOC1010X104
Top Assembly Part Number        : 800-27221-02
Top Assembly Revision Number    : A0
Version ID                     : V02
CLEI Code Number               : COM3L00BRA
Hardware Board Revision Number  : 0x01

Switch Ports Model          SW Version  SW Image
-----
*    1 26 WS-C2960-24TT-L  15.0(2)SE4  C2960-LANBASEK9-M

Cisco IOS Software, C2960 Software (C2960-LANBASEK9-M), Version 15.0(2)SE4, RELEASE SOFTWARE (fc1)
Technical Support: http://www.cisco.com/techsupport
Copyright (c) 1986-2013 by Cisco Systems, Inc.
Compiled Wed 26-Jun-13 02:49 by mnnguyen

```

Press RETURN to get started!

Switch>

```

Switch>?
Exec commands:
  connect      Open a terminal connection
  disable      Turn off privileged commands
  disconnect   Disconnect an existing network connection
  enable       Turn on privileged commands
  exit         Exit from the EXEC
  logout       Exit from the EXEC
  ping         Send echo messages
  resume       Resume an active network connection
  show         Show running system information
  ssh          Open a secure shell client connection
  telnet       Open a telnet connection
  terminal     Set terminal line parameters
  traceroute   Trace route to destination

Switch>t?
telnet terminal traceroute
Switch>tte?
% Unrecognized command
Switch>te?
telnet terminal
Switch>te|

```

```

Switch>en
Switch>enable
Switch#?
Exec commands:
clear          Reset functions
clock          Manage the system clock
configure      Enter configuration mode
connect        Open a terminal connection
copy           Copy from one file to another
debug          Debugging functions (see also 'undebug')
delete         Delete a file
dir            List files on a filesystem
disable        Turn off privileged commands
disconnect     Disconnect an existing network connection
enable         Turn on privileged commands
erase          Erase a filesystem
exit           Exit from the EXEC
logout         Exit from the EXEC
more           Display the contents of a file
no             Disable debugging informations
ping           Send echo messages
reload         Halt and perform a cold restart
resume         Resume an active network connection
setup          Run the SETUP command facility
show           Show running system information
ssh            Open a secure shell client connection
telnet         Open a telnet connection
terminal       Set terminal line parameters
traceroute     Trace route to destination
undebug        Disable debugging functions (see also 'debug')
write          Write running configuration to memory, network, or terminal
Switch#
Switch#
Switch#configure
Configuring from terminal, memory, or network [terminal]?
Enter configuration commands, one per line.  End with CNTL/Z.
Switch(config)#

```

```

Switch#show clock
*0:8:34.511 UTC Mon Mar 1 1993
Switch#clock
% Incomplete command.
Switch#clock ?
    set  Set the time and date
Switch#clock clock set?
% Unrecognized command
Switch#clock set?
set
Switch#clock set ?
    hh:mm:ss  Current Time
Switch#clock set 19:11:00
% Incomplete command.
Switch#clock set 19:11:00 ?
    <1-31>    Day of the month
    MONTH    Month of the year
Switch#clock set 19:11:00 02 Aug 2026
Switch#

```

