


Screenshots

1) User EXEC mode:



The screenshot shows a terminal window titled "Switch0" with tabs for Physical, Config, CLI, and Attributes. The CLI tab is active, displaying the following text:

```
Processor board ID FHK0610Z0WC
Running Standard Image
6 FastEthernet/IEEE 802.3 interface(s)

63488K bytes of flash-simulated non-volatile configuration memory.
Base ethernet MAC Address: 00E0.F917.B1B1
Motherboard assembly number: 73-5781-09
Power supply part number: 34-0965-01
Motherboard serial number: FOC061004SZ
Power supply serial number: DAB0609127D
Model revision number: C0
Motherboard revision number: A0
Model number: WS-CSwitch-PT
System serial number: FHK0610Z0WC

Cisco Internetwork Operating System Software
IOS (tm) PT3000 Software (PT3000-I6Q4L2-M), Version 12.1(22)EA4, RELEASE SOFTWARE
(fc1)
Copyright (c) 1986-2006 by cisco Systems, Inc.
Compiled Fri 12-May-06 17:19 by pt_team

Press RETURN to get started!

Switch>?
Exec commands:
  connect      Open a terminal connection
  disable      Turn off privileged commands
  disconnect   Disconnect an existing network connection
  enable       Turn on privileged commands
  exit         Exit from the EXEC
  logout       Exit from the EXEC
  ping         Send echo messages
  resume       Resume an active network connection
  show         Show running system information
  telnet       Open a telnet connection
  terminal     Set terminal line parameters
  traceroute   Trace route to destination
Switch>
```

At the bottom of the window, there are "Copy" and "Paste" buttons, and a "Top" link in the footer.

2) Privileged EXEC mode:

The screenshot shows a web-based CLI interface for a device named 'Switch0'. The interface has a top navigation bar with tabs for 'Physical', 'Config', 'CLI', and 'Attributes'. The 'CLI' tab is active. The main content area displays the command-line interface. It starts with a list of 'Exec commands' and their descriptions. The user enters 'en' to enter privileged EXEC mode, followed by 'enable' twice. The prompt changes from 'Switch>' to 'Switch#'. A second list of 'Exec commands' is shown, followed by '--More--'. At the bottom right, there are 'Copy' and 'Paste' buttons. At the bottom left, there is a 'Top' link.

```
Switch0
Physical Config CLI Attributes

Exec commands:
connect      Open a terminal connection
disable      Turn off privileged commands
disconnect   Disconnect an existing network connection
enable       Turn on privileged commands
exit         Exit from the EXEC
logout       Exit from the EXEC
ping         Send echo messages
resume       Resume an active network connection
show         Show running system information
telnet       Open a telnet connection
terminal     Set terminal line parameters
traceroute   Trace route to destination

Switch>en
Switch>enable
Switch>enable
Switch#?
Exec commands:
clear        Reset functions
clock        Manage the system clock
configure    Enter configuration mode
connect      Open a terminal connection
copy         Copy from one file to another
debug        Debugging functions (see also 'undebug')
delete       Delete a file
dir          List files on a filesystem
disable      Turn off privileged commands
disconnect   Disconnect an existing network connection
enable       Turn on privileged commands
erase        Erase a filesystem
exit         Exit from the EXEC
logout       Exit from the EXEC
more         Display the contents of a file
no           Disable debugging informations
ping         Send echo messages
reload       Halt and perform a cold restart
resume       Resume an active network connection
setup        Run the SETUP command facility
show         Show running system information
--More--
```

Copy Paste

Top

3) Global configuration mode

Switch0

PhysicalConfigCLIAttributes

Exec commands:

clear

Reset functions

clock

Manage the system clock

configure

Enter configuration mode

connect

Open a terminal connection

copy

Copy from one file to another

debug

Debugging functions (see also 'undebug')

delete

Delete a file

dir

List files on a filesystem

disable

Turn off privileged commands

disconnect

Disconnect an existing network connection

enable

Turn on privileged commands

erase

Erase a filesystem

exit

Exit from the EXEC

logout

Exit from the EXEC

more

Display the contents of a file

no

Disable debugging informations

ping

Send echo messages

reload

Halt and perform a cold restart

resume

Resume an active network connection

setup

Run the SETUP command facility

show

Show running system information

ssh

Open a secure shell client connection

Switch>en

Switch>enable

Switch>enable

Switch#?

Switch#

Switch#

Switch#configure

Configuring from terminal, memory, or network [terminal]?

Enter configuration commands, one per line. End with CNTL/Z.

Switch(config)#

CopyPaste

Top

4.) Complete topology

