Installation and first launch

This page is for the person who installs the program (usually the shop owner). It is done once.


1. Download the program

Latest version: **Kassa-Setup — download** (the `Kassa-Setup-….exe` file).

2. Install

1. Open the `Kassa-Setup-….exe` file.
2. If Windows says "unrecognized app": **"More info"** → **"Run anyway"**.
3. Choose the language (Azərbaycanca, Русский, English).
4. Choose the installation mode:
   - **"Install for all users" (recommended for a shop)** — Windows asks for the administrator password. The program runs in protected mode: the cashier cannot remove the program or the data. See **Windows accounts**.
   - **"Install for me only"** — no administrator password needed. For trying it out or a home computer.
5. **Next** → **Install** → **Finish**. A green **Kassa** icon appears on the desktop.

3. First launch



1. **Installation password** — get it from the person who gave you the program. It is asked only the first time.
2. Choose the language, enter the **shop name**, **your name** and **your password** (at least 8 characters, letters and digits). You become the shop's **admin**.
3. **Set up**.

4. Recovery code — write it on paper

After setup, a **recovery code** appears on the screen.

- **Write it on paper** and keep it at home or in a safe. Do not store it as a file on the computer.
- If the computer breaks or is stolen, the data can be brought back **only with this code**.
- You can see it later too: **Backup** → **Recovery code** → your password.

Tick **"I have written down the code..."** → **Continue**.

5. Windows accounts: a separate account for the cashier

The safest setup (when installed "for all users"):

1. For the **owner**: a Windows **administrator account with a password** — they install and update Kassa from it.

2. For the **cashier**: a **standard** (non-administrator) account: Settings → Accounts → Other users → **Add account** → account type **"Standard User"**.
3. Every day the computer is used in the **cashier's account**. Kassa works there too, but the cashier cannot delete or change the program or the data files.
4. Everyone logs in to Kassa with their own **Kassa name and password** (separate from the Windows password).

In this mode closing the window does not stop the program completely — it keeps running in the background (Telegram report, backup). This is normal.

6. What to do next

Step	Where
Shop details (address, phone, tax ID (VÖEN) — shown on the receipt)	Settings
Cashier account	Users
Entering products	Products, Receiving goods
Receipt and label printer	Printer
Daily report and backup to your phone	Telegram
Weekly USB backup	Backup