Upgrade room for loyalty members (flow)



Overview

The **Upgrade Room for Loyalty Members** flow automates the process of upgrading rooms for arriving guests based on loyalty status and configurable criteria. It runs on a schedule (daily by default), identifies today's eligible arrivals, attempts to upgrade their assigned room category, and then handles the results — sending an SMS to guests whose rooms were successfully upgraded, and adding a note to reservations where the upgrade could not be completed so that hotel staff are informed.

This flow is designed to be nearly ready to use out of the box. Most fields come pre-configured with sensible defaults. **Only one setting is mandatory before the flow can run:** you must configure the **Upgrade Path** in the Upgrade Assigned Room Category component to define which room categories should be upgraded and to which target categories.

Before You Start

Required setup: Before starting the flow, you must configure the **Upgrade Path** in the **Upgrade Assigned Room Category** component. This defines which room categories are eligible for an upgrade and what the target category is for each. Without this configuration, the flow will not know how to upgrade rooms.

All other settings in the flow come pre-filled with default values and are ready to use. You can customize any of them to match your property's needs — see the component-by-component breakdown below for details on what can be adjusted.

How the Flow Works

The flow consists of seven components connected in sequence, with branching logic to handle successful and failed upgrades separately:

Step	Component	Connects to	Description
1	Cron Scheduler	→ Step 2	Triggers the flow on a recurring schedule (daily at noon by default).
2	Check Occupancy	*Below threshold* → Step 3	Checks whether the property's occupancy is below a configured threshold. If occupancy is at or above the threshold, the flow stops — no upgrades are attempted when the property is fully occupied.
3	Get Eligible Arrivals	→ Step 4	Retrieves confirmed reservations arriving on the target date, optionally filtered by loyalty program membership, behavioral signals, or rate codes.
4	Upgrade Assigned Room Category	*Upgraded* → Step 5 *Failed* → Step 7	Attempts to upgrade the room category for each eligible reservation based on the configured upgrade paths and real-time availability. Results are split into two branches.
5	Each (Iterator)	→ Step 6	Iterates over the list of successfully upgraded reservations and triggers the next step for each one individually.
6	Send SMS	*End of branch*	Sends an SMS notification to each guest whose room was successfully upgraded.
7	Add Note to Reservation	*End of branch*	Adds a note to all reservations where the upgrade failed, so hotel staff can see which guests were not upgraded and why.

Component Details

Below is a detailed breakdown of each component in the flow, including which fields are pre-configured and which can be customized.

1. Cron Scheduler

The Cron Scheduler is a time-based trigger that starts the flow at regular intervals using standard cron syntax.

Field	Default Value	Status	Description
Trigger immediately	`False`	**Pre-filled**	When set to true, the flow triggers once immediately when started, in addition to the scheduled runs. Default is false — the flow waits until the next scheduled time.
Minute	`*`	**Pre-filled**	The minute of the hour to run. `*` means every minute (combined with the Hour setting, it runs at 12:00). Allowed values: `*`, `-`, `/`, `0-59`.
Hour	`12`	**Pre-filled**	The hour of the day to run. Set to `12` (noon). Allowed values: `*`, `-`, `/`, `0-23`.
Day of the Month	`*`	**Pre-filled**	Which day(s) of the month to run. `*` means every day. Allowed values: `*`, `-`, `/`, `1-31`.
Day of the Week	`*`	**Pre-filled**	Which day(s) of the week to run. `*` means every day. Allowed values: `*`, `-`, `/`, `0-6`, `SUN-SAT`.
Timezone	*Empty*	**Pre-filled**	The timezone for the schedule. When left empty, the schedule uses your local time. To use a specific timezone, enter a timezone identifier (e.g., `Europe/Prague`). By default it uses GMT.

Default schedule: The flow is pre-configured to run every day at 12:00 (noon). You can adjust the schedule by changing the cron fields. For example, to run at 8:00 AM, change the Hour to `8`. To run only on weekdays, set Day of the Week to `1-5` (Monday through Friday). If you want the schedule to run in your local time, leave the Timezone field empty. To run in a specific timezone, enter the timezone identifier (e.g., `Europe/Prague`).

---

2. Check Occupancy

Calculates the current occupancy percentage for your property and determines whether there is enough capacity to proceed with upgrades. If occupancy is at or above the threshold, the flow stops and no upgrades are attempted.

Field	Default Value	Status	Description
Date	Today's date	**Pre-filled**	The date to check occupancy for. Pre-filled to use the current date.

Occupancy Percentage Threshold	`100`	**Pre-filled**	The occupancy percentage above which upgrades should not be attempted. Set to `100` by default, meaning upgrades are only blocked when the property is completely full. You can lower this to be more conservative — for example, setting it to `90` would stop upgrades when 90% or more of rooms are occupied.
Bookable Services	*None selected*	**Optional**	Filter the occupancy calculation to specific bookable services. If none are selected, all bookable services at the property are included. Select specific services if you want the occupancy check to consider only certain types of accommodations.

How it connects: If occupancy is *below* the threshold, the flow continues to **Get Eligible Arrivals**. If occupancy is *at or above* the threshold, the flow stops — no further components are executed.

---

3. Get Eligible Arrivals

Retrieves confirmed reservations arriving on the specified date. You can optionally filter guests by loyalty program membership, behavioral signals (stay frequency, revenue, recency), or rate codes to narrow down which reservations are eligible for an upgrade.

Field	Default Value	Status	Description
Arrival Date	Today's date	**Pre-filled**	The date to search for arriving reservations. Pre-filled to use the current date so the flow always checks today's arrivals. This can be adjusted if you need to look ahead to a future date.
Loyalty Programs	*None selected*	**Optional**	Filter arrivals to guests enrolled in specific loyalty programs. If no programs are selected, loyalty membership is not used as a filter criterion.
Loyalty Tiers	*None selected*	**Optional**	Further narrow the loyalty filter to specific tiers within the selected programs (e.g., Gold, Platinum). Only visible after a loyalty program is selected.
Stay Count Threshold	*Not set*	**Optional**	Minimum number of past stays a guest must have to qualify. This is a behavioral signal — guests who do not meet the loyalty criteria can still qualify if they meet all configured behavioral thresholds.

Revenue Threshold	*Not set*	**Optional**	Minimum total revenue (in the property's default currency) a guest must have generated to qualify.
Recency Threshold	*Not set*	**Optional**	Maximum number of days since the guest's most recent stay. Guests whose last stay was more recent than this threshold qualify.
Rates	*None selected*	**Optional**	Filter reservations by the rate they were booked under. Only reservations matching the selected rates are included.

Filtering logic: Guests are first evaluated against loyalty criteria (hard signals). If a guest is not part of a selected loyalty program or tier, they are then evaluated against the behavioral thresholds (soft signals). A guest must meet *all* configured behavioral thresholds to qualify. If no filters are configured, all confirmed reservations with assigned rooms arriving on the specified date are included.

---

4. Upgrade Assigned Room Category

The core component of this flow. It takes the list of eligible reservation IDs and attempts to upgrade each guest's assigned room category based on the upgrade paths you define. It checks real-time availability and respects buffer limits to ensure the property retains enough rooms in each category.

Required configuration: You must configure the **Upgrade Paths** before the flow can run. This is the only mandatory setup step for the entire flow.

Field	Default Value	Status	Description
Reservation IDs	*From previous step*	**Pre-filled**	Automatically populated from the Get Eligible Arrivals output. Contains the list of reservation IDs to process for upgrades.
Upgrade Paths	*Not configured*	**Required**	Defines how room categories should be upgraded. Each row maps a source room category to a target room category (e.g., Standard → Deluxe). You can define multiple paths for cascading upgrades (e.g., Standard → Deluxe → Suite). Each source category can only appear once. This must be configured before running the flow.

Availability Buffer	`0`	**Pre-filled**	The minimum number of rooms to keep available in the target category. Upgrades are only performed when enough rooms remain above this buffer. Set to `0` by default, meaning all available rooms can be used for upgrades. Increase this to reserve rooms for direct bookings.
Max Rooms to Upgrade	*Not set*	**Optional**	Maximum number of rooms to upgrade per run. Once this limit is reached, remaining reservations are marked as failed with a `CAP_REACHED` reason. Leave empty for no limit.
Per-Category Availability Overrides	*Not set*	**Optional**	Found in the Advanced section. Override the global availability buffer for specific room categories. Useful if some categories need a larger reserve than others.

Output ports:

- **Upgraded:** Fires when at least one reservation was successfully upgraded. Passes the list of upgraded reservation IDs to the **Each** iterator.
- **Failed:** Fires when at least one reservation could not be upgraded. Passes the list of failed reservation IDs and failure reasons to **Add Note to Reservation**.
- **Cooldown:** Fires when the component's cooldown period is active, preventing duplicate upgrade attempts.

---

5. Each (Iterator)

The Each component receives the list of successfully upgraded reservation IDs and iterates over them one by one. For each reservation, it triggers the **Send SMS** component so that each guest receives an individual notification.

Field	Default Value	Status	Description
Field	Upgraded Reservation IDs	**Pre-filled**	The list to iterate over. Pre-configured to use the Upgraded Reservation IDs array from the Upgrade Assigned Room Category component.
Delay	*Not set*	**Optional**	Delay between processing each item, in milliseconds. Can be used to add a pause between sending SMS messages if needed.

---

6. Send SMS

Sends an SMS message to the guest for each successfully upgraded reservation. The guest is notified about their room upgrade.

Field	Default Value	Status	Description
Guest ID	*From previous step*	**Pre-filled**	Automatically populated from the upstream workflow data. Identifies which guest should receive the SMS.
Reservation ID	*From previous step*	**Pre-filled**	Automatically populated from the Each iterator. Links the SMS to the specific reservation.
Message body	*Pre-filled template*	**Pre-filled**	The text content of the SMS. A default message is included that informs the guest about their room upgrade. You can customize this message to match your property's tone and branding.
Sender	Hotel	**Pre-filled**	Who the message is sent on behalf of. Set to **Hotel** by default. Can be changed to **Guest** if needed.

Note: The SMS is sent to the phone number associated with the guest's profile. Ensure that guest profiles have valid phone numbers for SMS delivery to succeed.

---

7. Add Note to Reservation

For reservations where the upgrade failed, this component adds a note to each reservation. This ensures hotel staff can see which reservations were eligible for an upgrade but could not be processed, along with the reason for the failure.

Field	Default Value	Status	Description
Reservation IDs	*From previous step*	**Pre-filled**	Automatically populated with the list of reservation IDs that failed to upgrade from the Upgrade Assigned Room Category component.
Note Text	*Pre-filled template*	**Pre-filled**	The text of the note added to each reservation. A default message is included that describes the failed upgrade attempt. You can customize this to include additional instructions or context for your team. Maximum 1,000 characters.

Setup Checklist

Use the following checklist to set up the flow before running it for the first time:

#	Status	Step	Details
1	**Required**	**Configure Upgrade Paths**	Open the **Upgrade Assigned Room Category** component and define your upgrade paths. Map each source room category to its target category (e.g., Standard → Deluxe). You can add multiple rows for cascading upgrades.
2	**Optional**	Adjust the schedule	The flow runs daily at 12:00 (noon) by default. Modify the **Cron Scheduler** if you prefer a different time or frequency.
3	**Optional**	Set occupancy threshold	The default is 100% (only stops when fully occupied). Lower this in **Check Occupancy** if you want to be more conservative.
4	**Optional**	Configure loyalty & behavioral filters	By default, all arriving guests are eligible. Add filters in **Get Eligible Arrivals** to target specific loyalty programs, tiers, or behavioral segments.
5	**Optional**	Set availability buffer	The default buffer is `0` (no rooms reserved). Increase this in **Upgrade Assigned Room Category** to retain rooms for direct bookings.
6	**Optional**	Customize SMS message	Edit the message body in **Send SMS** to match your property's tone and branding.
7	**Optional**	Customize reservation note	Edit the note text in **Add Note to Reservation** to include additional context for your staff.

Example Use Cases

- **Loyalty-based upgrades:** Configure the Get Eligible Arrivals component to filter by your loyalty program and Gold/Platinum tiers. Only your most loyal guests receive automatic upgrades.
- **High-value guest recognition:** Use the behavioral signal filters (revenue threshold, stay count) to automatically upgrade frequent or high-spending guests, even if they are not enrolled in a loyalty program.
- **Conservative upgrade policy:** Set the occupancy threshold to 80% and the availability buffer to 2 to ensure upgrades only happen when the property has plenty of capacity and at least 2 rooms remain available in each target category.
- **Weekday-only upgrades:** Modify the Cron Scheduler to run only Monday through Friday by setting Day of the Week to `1-5`, avoiding upgrades during peak weekend periods.

Troubleshooting

The flow runs but no upgrades happen

- Check that the **Upgrade Paths** are configured correctly and match existing room categories in your property.
- Verify that there are arrivals for the current date with assigned rooms in the source categories of your upgrade paths.
- Check the **Check Occupancy** component — if occupancy is above the threshold, the flow stops before reaching the upgrade step.
- If you configured loyalty or behavioral filters, ensure that arriving guests meet the criteria.

Some reservations fail to upgrade

Reservations may fail for the following reasons:

- **NO_AVAILABILITY:** There are no available rooms in the target category (above the buffer threshold).
- **CAP_REACHED:** The maximum number of upgrades per run has been reached.
- **NO_CATEGORY_FOUND:** The reservation's current room category does not have a defined upgrade path.

Failed reservations will have a note added automatically so your team can follow up manually if needed.

SMS messages are not delivered

- Ensure that the guest profiles have valid phone numbers configured.
- Check that SMS messaging is enabled for your property.