BuildTrack roles and responsibilities

PRODUCT REVIEW | 26 OCTOBER 2026

Review the role responsibilities, default choices and access boundaries below. These are the current shared role templates; organizations can enable, remove or create roles, so actual access can differ.

Platform administration

Platform administrator: onboard and manage organizations, invite or remove users, block access, configure pricing and manage the shared role catalog. Pricing records and estimates do not collect payments. Platform access does not itself grant access to an organization’s field work.

Organization and field management

Role	Scope	What they can do
Organization administrator Default	Org	Manage members and roles, divisions and homes, vendors and rosters, settings and audit history. Field-work permissions require an additional role.
Area construction manager	Area / home	Create, review, assign and verify work; manage inspections, reports and audit; approve milestones; add internal and shared comments and evidence.
Superintendent Default	Area / home	Create, assign, perform and verify work; manage inspections; view reports; approve milestones; add internal and shared comments and evidence.
Assistant superintendent	Area / home	Create, review, assign and perform work; manage inspections; add internal and shared comments and evidence.
Operations coordinator	Area / home	Create, review and assign work; manage inspections; add internal and shared comments and evidence.
Internal field contributor	Area / home	Read and create work, perform assigned work, and add internal and shared comments and evidence.

Inspection trade and read only roles

Role	Scope	What they can do
Internal quality inspector Default	Area / home	Read and create work; perform inspections; add internal and shared comments and evidence.
External inspector	Area / home	Perform authorized inspections, create findings, and add shared comments and evidence. Access is limited to authorized inspection work.
Independent verifier	Area / home	Read work, verify corrections and add shared comments. Verification rules apply.
Trade company manager Default	Area	Act on work assigned to their company; delegate to eligible technicians; add shared comments and evidence.
Trade technician Default	Area	Act on work assigned to them; add shared comments and evidence.
Leadership viewer Default	Org / area / home	View scoped work, reports and exports.
Auditor	Org / area / home	View scoped work, reports, exports and audit history.

What each persona can do on the site

This section lists the pages and actions each shared role template actually gets in BuildTrack today. Every action is limited to the person's assigned location scope. Everyone can also open My account (profile and password), Notifications and the organization switcher.

Quick reference

Role	Create work	Assign & triage	Do assigned work	Verify fixes	Schedule inspect.	Fill in inspect.	Internal comments	Reports & export	Audit history	Approve milestones	People & setup
Organization administrator	—	—	—	—	—	—	—	—	✓	—	✓
Area construction manager	✓	✓	—	✓	✓	—	✓	✓	✓	✓	—
Superintendent	✓	✓	✓	✓	✓	—	✓	✓	—	✓	—
Assistant superintendent	✓	✓	✓	—	✓	—	✓	—	—	—	—
Operations coordinator	✓	✓	—	—	✓	—	✓	—	—	—	—
Internal field contributor	✓*	—	✓	—	—	—	✓	—	—	—	—
Internal quality inspector	✓*	—	—	—	—	✓	✓	—	—	—	—
External inspector	✓*	—	—	—	—	✓	—	—	—	—	—
Independent verifier	—	—	—	✓	—	—	—	—	—	—	—
Trade company manager	—	—	✓†	—	—	—	—	—	—	—	—
Trade technician	—	—	✓	—	—	—	—	—	—	—	—
Leadership viewer	—	—	—	—	—	—	—	✓	—	—	—
Auditor	—	—	—	—	—	—	—	✓	✓	—	—

* Can create work drafts and submit them for review, but cannot assign them. † Can also delegate company work to its technicians. "Do assigned work" means acknowledge, start, report blockers, upload photos and submit corrections.

Organization administrator

Opens on: Administration

Menu: Properties, Vendor management, Administration, My account

- Invite people and give each one a role and a location (whole organization, neighborhood or home).
- Change a member's roles, suspend or reactivate them, and revoke pending invitations (requires MFA).
- Enable, remove or create the organization's own roles in Manage role catalog.
- Create divisions, neighborhoods, homes and rooms; bulk-import homes; plan home milestones.
- Add trade companies, specialties and neighborhood rosters, and invite trade company members.

- Set up work categories, business calendars, checklists, inspector engagements, escalation routes, notification rules and required inspections.
- View activity/audit history and notification delivery health.

Cannot: See My work, Inspections or Reports, or create, assign or verify work. Add a field role if the administrator also works in the field.

Area construction manager

Opens on: Administration (activity view)

Menu: My work, Neighborhoods, Inspections, Reports, Administration, My account

- See all work and homes in their neighborhoods or homes.
- Create work items and assign them in the same step, or save drafts.
- Set category and priority, cancel work, assign or reassign to staff or a trade company, change due dates, and bulk-assign.
- Allow a correction to be submitted without photos (evidence exception).
- Report and clear blockers on active work.
- Review submitted corrections: accept them or send them back for rework; reopen verified work.
- Schedule inspections and start amendments to submitted inspections.
- View reports, export CSV, and view audit history.
- Approve a home milestone when the home shows Ready for review.
- Post shared comments or internal-only comments.

Cannot: Acknowledge, start or submit corrections; fill in inspection checklists; manage people, properties or settings.

Superintendent

Opens on: My work

Menu: My work, Neighborhoods, Inspections, Reports, Sync center, My account

- See all work and homes in their neighborhoods or homes.
- Create, categorize, prioritize, cancel, assign, reassign and bulk-assign work; change due dates; grant evidence exceptions.
- Work on items assigned to them: acknowledge, start, report or clear blockers, upload photos and submit the correction.
- Review other people's corrections: accept, send back for rework, or reopen verified work.
- Schedule inspections and start amendments.
- View reports and export CSV.
- Approve home milestones.
- Post shared or internal-only comments; capture work offline and sync it later.

Cannot: Verify a correction they submitted themselves; view audit history; use Administration.

Assistant superintendent

Opens on: My work

Menu: My work, Neighborhoods, Inspections, Sync center, My account

- See all work and homes in their neighborhoods or homes.
- Create, categorize, prioritize, cancel, assign, reassign and bulk-assign work; change due dates; grant evidence exceptions.
- Work on items assigned to them: acknowledge, start, report or clear blockers, upload photos and submit the correction.
- Schedule inspections and start amendments.
- Post shared or internal-only comments; capture work offline.

Cannot: Verify corrections, view reports, approve milestones or view audit history.

Operations coordinator

Opens on: My work

Menu: My work, Neighborhoods, Inspections, Sync center, My account

- See all work and homes in their neighborhoods or homes.
- Create, categorize, prioritize, cancel, assign, reassign and bulk-assign work; change due dates; grant evidence exceptions.
- Report and clear blockers on active work.
- Schedule inspections and start amendments.

- Post shared or internal-only comments.

Cannot: Do the work itself, verify corrections, view reports or approve milestones.

Internal field contributor

Opens on: My work

Menu: My work, Neighborhoods, Sync center, My account

- See work and homes in their neighborhoods or homes.
- Create work drafts, edit them and choose Submit work item so a manager can assign it.
- Work on items assigned to them: acknowledge, start, report or clear blockers, upload photos and submit the correction.
- Post shared or internal-only comments; capture work offline.

Cannot: Assign, categorize or cancel work; verify corrections; use inspections or reports.

Internal quality inspector

Opens on: Inspections

Menu: My work, Neighborhoods, Inspections, Sync center, My account

- Open inspections in their scope, fill in the checklist, record findings and submit the inspection.
- Create work drafts and submit them for assignment.
- See work and homes in their neighborhoods or homes.
- Post shared or internal-only comments.

Cannot: Schedule inspections, assign work, do correction work or verify corrections.

External inspector

Opens on: Inspections

Menu: My work, Neighborhoods, Inspections, Sync center, My account

- Open only the inspections they are engaged for (limited by home and time window), fill in the checklist, record findings and submit.
- Create findings or work drafts and submit them.
- Post shared comments.

Cannot: Browse other work in the neighborhood, read or write internal comments, assign or verify work.

Independent verifier

Opens on: My work

Menu: My work, Neighborhoods, My account

- See work and homes in their neighborhoods or homes.
- Open corrections that are Ready for verification, review the photos and notes, then accept or send back for rework. Safety-flagged work must be checked on site.
- Reopen verified work if a problem comes back.
- Post shared comments.

Cannot: Verify a correction they or their own trade company submitted; create or assign work; see internal comments, inspections or reports.

Trade company manager

Opens on: My work

Menu: My work, Sync center, My account

- See only work assigned to their company.
- Acknowledge and start work, report or clear blockers, upload photos and submit the correction (also offline).
- Delegate a company work item to one of their active technicians; the company stays accountable.
- Post shared comments.

Cannot: See unassigned or other companies' work, create work, see internal comments, or verify their own company's fixes. Requires an active company membership and neighborhood roster.

Trade technician

Opens on: My work

Menu: My work, Sync center, My account

- See only work assigned or delegated to them.
- Acknowledge and start work, report or clear blockers, upload photos and submit the correction (also offline).
- Post shared comments.

Cannot: Delegate work, create work, see internal comments or verify fixes.

Leadership viewer

Opens on: My work

Menu: My work, Neighborhoods, Reports, My account

- Browse work, neighborhoods and homes in their scope (read only).
- Use Reports with filters and export CSV.

Cannot: Change anything, post comments or see internal-only comments.

Auditor

Opens on: Administration (activity view)

Menu: My work, Neighborhoods, Reports, Administration, My account

- Browse work, neighborhoods and homes in their scope (read only).
- Use Reports with filters and export CSV.
- View audit history in Administration > Activity & policies.

Cannot: Change anything, post comments, or manage people or settings.

Gaps found while mapping personas

- Area construction managers and auditors open on Administration rather than My work or Reports, because audit history is treated as an administration permission. The persona guide says they start on My work or Reports.
- Area construction managers, operations coordinators and both inspector roles are granted evidence upload, but the site only shows Upload evidence to people who can do assigned work, so they cannot attach photos today.
- Organization administrators see no field pages by default. Anyone who administers and also works in the field needs a second role.

How access works

Default marks roles enabled for a new organization; enabling a role does not assign it to anyone. Area means a neighborhood. A person can hold multiple roles, and their location scope limits access. Trade roles also require active company membership; company assignment requires an active neighborhood roster.

Administrative changes require an MFA-verified session. A ready organization must retain an active organization-wide access administrator. All users can complete and edit their own profile.

Questions for product review

Are the six default roles appropriate? Should organization administrators receive field permissions by default? Are the differences between field managers, inspectors and trade roles right for the intended workflow?