Dummies install for KW Redux

1. **Download the Mod from either of these locations**

   http://spacedock.info/mod/531/KW%20Rocketry%20Redux

   https://github.com/linuxgurugamer/KWRocketryRedux/releases

2. **Unzip the package into a temporary directory, Windows users can use their download directory, you should have a folder like this.**

   KWRocketry   File folder

   With these folders

   Extras
   GameData
   Changelog.txt
   Credits.txt
   Installation Instructions.txt

3. **Copy The GameData folder to the Gamedata folder of your KSP Install folder**

   Extras
   GameData
   Changelog.txt
   Credits.txt
   Installation Instructions.txt

   3a.This one

   GameData
   Internals
   KSP_Data
   KSP_x64_Data
   Launcher_Data

4. **I know what you're thinking "Let's fire up KSP and go launch something", well it's not that simple you have to make a choice. If you look at the folders in step 2 you will see an extras folder. It contains the following folders**

   GraduatedPowerResponseConfigs   File folder
   InstantPowerResponseConfigs   File folder
   OldFARFairings   File folder
   ReduceClampSounds (Recommen...   File folder
   Subassemblies for default (proced... File folder
   Subassemblies for legacy FAR com... File folder

5. **You must select one of the power response configs**

GraduatedPowerResponseConfigs — File folder
InstantPowerResponseConfigs — File folder
OldFARFairings — File folder
ReduceClampSounds (Recommen... — File folder
Subassemblies for default (proced... — File folder
Subassemblies for legacy FAR com... — File folder

Open the selected power config and select the GameData Folder

GameData — File folder

Copy this to the same folder in 3a

Optional

If you want to have the interstage engine shrouds working delete KWPatch -interstage.cfg from within KWCommunityFixes folder that's inside the KWRocketry folder inside the GameData folder in 3a

Flags
KWCommunityFixes
Parts
Soundbank
KW Rocketry Version 2.7.txt
KWRocketryRedux.version
MiniAVC.dll

This one

Plugin
Textures
KW_FAR.cfg
KWCommunityFixes.version.old
KWPatch.cfg
KWPatch-1-0-5.cfg
KWPatch-Bulkheads.cfg
KWPatch-Community-Parts.cfg
KWPatch-fairings.cfg
KWPatch-interstage.cfg
KWPatch-mass.cfg
README.txt
README-1-0-5.txt