MIND IT! REHEARSAL CHECKLIST

Run on the real laptop, tablet, phones and TV · about 40 minutes

Date: Tablet: Galaxy Tab Phones:

The automatic checks on the build computer already cover these features. This list is for what only real devices can show: Wi-Fi, sound, vibration, the TV and touch screens. Tick each step; a **NEW** tag marks what changed since the last checklist (build 155).

BEFORE YOU START

1	**Laptop** NEW	Put the four **Mind It!.exe** parts and **Join Mind It - build 160.bat** in one folder → run the .bat → open **Mind It!.exe**: the **main menu** (▶ Prepare tonight's quiz…). Pick a party theme: your host screens take its colours too. Laptop, tablet and phones on the same Wi-Fi. First time only: allow private-network access.	☐
2	**Tablet** NEW	Install **Mind It! for Android (Galaxy Tab).apk** over the old one — nothing is lost (build 160). Laptop main menu → ⟳ **Sync devices**: both show the same games. It opens to the Main Menu as **Mind It!**; **Settings** → **App Update** says it's the newest. Also install it on an **Android phone**: it stays upright and the home screen says "this phone".	☐
3	**Phones**	Two or more phones — ideally one Android and one iPhone.	☐
4	**Rehearsal** NEW	Main menu → **Rehearsal** (nothing is saved) → 🤖 **Bot 1: Pro**. Begin → ▶ **Start the show** (**H** holds a screen). On its turn the bot picks a clue and **says its answer** out loud and on the TV → mark it.	☐
5	**Check Connections**	Next to Begin Game: 📶 **Check Connections** → **Test All Connections**. Laptop, tablet and each joined phone show Connected — and stay Connected over a minute, no flicker; a team without a phone is named in the summary.	☐

TABLET (QUIZMASTER REMOTE)

6	**PIN keypad**	Tablet home → Connect To Laptop → tap the found laptop. The PIN box opens the number keypad. Enter the PIN → it connects.	☐
7	**Reconnect**	Close Mind It! on the tablet and open it again → it goes straight back in without asking for the PIN.	☐
8	**Controls**	Answer card (tap to show) · Correct / Wrong / Pass · the timer tile pauses and starts the laptop's timer. Hosting on the tablet: board and question fit one screen, upright and sideways.	☐
9	**Drop-out**	Turn the tablet's Wi-Fi off for 10 s → "Reconnecting…" / "Connection Lost". Turn it on → it recovers, scores unchanged.	☐

TEAM PHONES

10	**Joining**	Before the game the TV shows the **join QR code**. Each phone scans it and types its team code. The **place card** at the bottom shows place, score and the gap to the team above.	☐
11	**Timer**	During a question the phone shows ⏱ counting down within 1–2 s of the TV, turning gold for the last 10 s.	☐
12	**Vibration**	**Android phones** buzz when their wager opens and when it's their turn to pick (iPhones can't — they just show it).	☐
13	**Blind It! question**	TV shows "BLIND IT!" with the sunglasses, then the wager screen. The phone's number pad + Lock In works; the laptop gets the amount. Then **4 · Rounds & Questions** → **Special Question** → **Rewind It!**, pick one: 🤠 **Spin The Wheel** → the TV wheel lands on 1×–5× → **Show The Question**. In Buzzer Mode the team's phone spins and stops it.	☐
14	**Triple Gamble**	On the team's turn, the "Your chips" row shows Use → confirm → pick a question. TV shows the dice moment and the casino sound; the question can't be passed.	☐
15	**Phoenix**	From Round 2, a last-place team **more than 2,000 behind** gets the 🔥 Phoenix: Use → Confirm → pick. Right = double + 20% of the gap, never past the leader ("PHOENIX RISES!"); wrong = nothing lost. Once per game.	☐
16	**Bottoms Up**	Round 1: Use → choose the designated player → Confirm → pick → answer wrong → ✓ Finished (nothing lost) or ✕ Not finished (normal loss).	☐
17	**Drop-out**	Turn a phone's Wi-Fi off for 10 s → "Connection Lost". Turn it on → back in the game with the same team (no new code).	☐

Continue on page 2

MIND IT! REHEARSAL CHECKLIST

Run on the real laptop, tablet, phones and TV · about 40 minutes

SCORES ON THE TV

18	**Places**	Once scores differ, each TV score card shows its place (1st in gold); the last team's card wears the 😺 cowboy cat.	☐
19	💡 **Hint**	Fast answer: Correct shows ⚡ **+100**. Next turn: that team's phone → 💡 **Use your hint** → **Show my hint** → the hint shows only there; the TV shows 💡; Correct pays half, no ⚡.	☐

PHONE BUZZER MODE

20	**Buzzer Test**	Setup → 3 · Gameplay & Rules → Phone Buzzer Mode → **Buzzer Test**: each phone's tap turns green within about a second. Close it and open it again → taps still register.	☐
21	**Before a buzz**	Open a question: the TV says **Phone Buzzers** · 🔔 **Any Team Can Buzz**; the laptop *and the tablet* show 🔔 **Waiting For A Buzz...** instead of Correct / Wrong. In Buzzer Mode the tablet has no "Up Next" turn line (who answers depends on the buzz).	☐
22	**In the game**	Tap too early → briefly locked. First buzz wins → Correct / Wrong come back, and the laptop says who buzzed first. Wrong → TV "WRONG ANSWER → BUZZERS REOPEN".	☐
23	**Nobody buzzed**	Someone answers out loud without buzzing → laptop: **A different team answered?** → score that team.	☐

MASTERMIND IT!

24	**Wagers**	Wager pad (All in · Half · Nothing) → Lock In. The Mastermind It! question can't be switched once Mastermind It! has started.	☐
25	**Answers**	Answer box shows "⭐ Mastermind It! · wager locked · N s left". Submit → "Answer Locked". Let one phone run out of time: about 2 s later it shows ⏱ **Time's Up** and no longer accepts an answer.	☐
26	**Change a wager**	After the question appears: laptop **Change a wager** (or the tablet's Change) → new amount → the team's phone shows it; the TV keeps it hidden.	☐
27	**Finish**	Step card (Space): mark ✓/✗/0 → ▶ **Reveal all** → standings (top three secret) → awards → 😺 The Rascala! (voice) → podium 3rd, 2nd, winner → 🏁 **End Quiz & save** → main menu.	☐

TV, SOUND AND SAFETY

28	**TV**	Audience View on the TV: the question is readable from the back of the room, with scores along the bottom. With your party theme on, its drawn backdrop sits behind the quiz and never covers the text.	☐
29	**Sounds**	Listen at your usual volume: the intro (**MIND IT!**, explosion, last riff), correct (ding + score pop) / wrong, a phone's BUZZ IN, the whoosh to a new board, the Triple Gamble dice, the Phoenix rise, The Rascala!. Note anything too loud or quiet.	☐
30	**Intermission**	⋯ → ☕ **Intermission** → 2 min: the TV counts down with the standings, quiet theme music plays. Resume fades it out.	☐
31	**Saved game**	Mid-game, close Mind It! on the laptop and open it again; close it once more *without choosing* and reopen → still offered → **Resume saved game** → the same scores, board and teams.	☐
32	**Backup** NEW	⋯ → 💾 **Backups & Restore** → **Back Up Now** → restore it (asks first): all comes back. Tablet: **Settings** → **Backup** → ⬆ **Restore From Backup File**.	☐
33	**Rehearsal end** NEW	End the rehearsal → the bot is gone and Historic Games has no new game (rehearsals aren't saved).	☐
34	**Test Hosting**	Connect Device → **Run Test** → **Ready to host**. Afterwards 📋 **Rehearsal Report** → **Save Report File**.	☐
35	**TV, no cable**	TV browser: **192.168.1.20/tv** → Full Screen → **Test**. Mi Box: Mind It! TV finds the quiz, or its 4-digit code → 📺 **Add a TV**.	☐
36	**Move the quiz**	Laptop **Take Over Tablet Quiz** → approve; back: **Hand Quiz to the Galaxy Tab** → **Host It on This Tablet**. Same scores and teams.	☐
37	**TV sound**	🔊 **Sound On This TV** → OK on the TV remote → the sounds come from the TV, the laptop goes quiet. TV off → back on the laptop.	☐

If something doesn't look right: note the step number, which device (laptop / tablet / which phone / TV), what you did and what happened — a photo or screenshot helps. Send me those notes and the 📋 **Rehearsal Report** file, and I'll fix it.