MIND IT! REHEARSAL CHECKLIST

Run on the real laptop, tablet, phones and TV · about 40 minutes

Date: Tablet: Galaxy Tab Phones:

The automatic checks on the build computer already cover these features. This list is for what only real devices can show: Wi-Fi, sound, vibration, the TV and touch screens. Tick each step; a **NEW** tag marks what changed since the last checklist (build 98).

BEFORE YOU START

1	**Laptop** NEW	Put the three **Mind It!.exe** parts and **Join Mind It - build 152.bat** in one folder → run the .bat → open **Mind It!.exe**. Laptop, tablet and phones on the same Wi-Fi. First time only: let Windows allow private-network access.	☐
2	**Tablet** NEW	Install **Mind It! for Android (Galaxy Tab).apk** over the old one — it updates without losing anything (version 1.69, build 152). It must be called **Mind It!** and open to the Main Menu, with "Enna Rascala....Mind It!" under the logo. **Settings → App Update → Check For Updates** says it's the newest (from build 152 Update downloads and installs inside the app).	☐
3	**Phones**	Two or more phones — ideally one Android and one iPhone.	☐
4	**Rehearsal**	On the laptop: Setup → 🎭 **Rehearsal**. Nothing you do is saved, so try everything freely.	☐
5	**Check Connections** NEW	Next to Begin Game: 📶 **Check Connections → Test All Connections**. Laptop, tablet and each joined phone show Connected — and stay Connected over a minute, no flicker; a team without a phone is named in the summary.	☐

TABLET (QUIZMASTER REMOTE)

6	**PIN keypad**	Tablet home → Connect To Laptop → tap the found laptop. The PIN box opens the number keypad. Enter the PIN → it connects.	☐
7	**Reconnect**	Close Mind It! on the tablet and open it again → it goes straight back in without asking for the PIN.	☐
8	**Controls**	Answer card (tap to show) · Correct / Wrong / Pass · the timer tile pauses and starts the laptop's timer.	☐
9	**Drop-out**	Turn the tablet's Wi-Fi off for 10 s → "Reconnecting…" / "Connection Lost". Turn it on → it recovers, scores unchanged.	☐

TEAM PHONES

10	**Joining** NEW	Before the game the TV shows the **join QR code**. Each phone scans it and types its team code. The header shows team, place and score.	☐
11	**Timer**	During a question the phone shows ⏱ counting down within 1–2 s of the TV, turning gold for the last 10 s.	☐
12	**Vibration** NEW	**Android phones** buzz when their wager opens and when it's their turn to pick (iPhones can't — they just show it).	☐
13	**Blind It! question**	TV shows "BLIND IT!" with the sunglasses, then the wager screen. The phone's number pad + Lock In works; the laptop gets the amount. Then **4 · Rounds & Questions → Special Question → Rewind It!**, pick one: 🤠 **Spin The Wheel** → the TV wheel lands on 1×–5× → **Show The Question**. In Buzzer Mode the team's phone spins and stops it.	☐
14	**Triple Gamble**	On the team's turn, the "Your chips" row shows Use → confirm → pick a question. TV shows the dice moment and the casino sound; the question can't be passed.	☐
15	**Phoenix**	From Round 2, a last-place team **more than 2,000 behind** gets the 🔥 Phoenix: Use → Confirm → pick. Right = double + 20% of the gap, never past the leader ("PHOENIX RISES!"); wrong = nothing lost. Once per game.	☐
16	**Bottoms Up**	Round 1: Use → choose the designated player → Confirm → pick → answer wrong → ✓ Finished (nothing lost) or × Not finished (normal loss).	☐
17	**Drop-out**	Turn a phone's Wi-Fi off for 10 s → "Connection Lost". Turn it on → back in the game with the same team (no new code).	☐

Continue on page 2

MIND IT! REHEARSAL CHECKLIST

Run on the real laptop, tablet, phones and TV · about 40 minutes

SCORES ON THE TV

18	**Places** NEW	Once scores differ, each TV score card shows its place (1st in gold).	☐
19	**Speed bonus** NEW	Answer within the first seconds: the laptop's Correct button shows ⚡ **+100** and the TV adds it.	☐

PHONE BUZZER MODE

20	**Buzzer Test**	Setup → 3 · Gameplay & Rules → Phone Buzzer Mode → **Buzzer Test**: each phone's tap turns green within about a second. Close it and open it again → taps still register.	☐
21	**Before a buzz** NEW	Open a question: the TV says **Phone Buzzers** · 🔔 **Any Team Can Buzz**; the laptop *and the tablet* show 🔔 **Waiting For A Buzz...** instead of Correct / Wrong. In Buzzer Mode the tablet has no "Up Next" turn line (who answers depends on the buzz).	☐
22	**In the game**	Tap too early → briefly locked. First buzz wins → Correct / Wrong come back, and the laptop says who buzzed first. Wrong → TV "WRONG ANSWER → BUZZERS REOPEN".	☐
23	**Nobody buzzed** NEW	Someone answers out loud without buzzing → laptop: **A different team answered?** → score that team.	☐

MASTERMIND IT!

24	**Wagers** NEW	Wager pad (All in · Half · Nothing) → Lock In. The Mastermind It! question can't be switched once Mastermind It! has started.	☐
25	**Answers** NEW	Answer box shows "⭐ Mastermind It! · wager locked · N s left". Submit → "Answer Locked". Let one phone run out of time: about 2 s later it shows ⏱ **Time's Up** and no longer accepts an answer.	☐
26	**Change a wager**	After the question appears: laptop **Change a wager** (or the tablet's Change) → new amount → the team's phone shows it; the TV keeps it hidden.	☐
27	**Finish** NEW	The TV shows the winner podium with each team's correct answers; about 9 s later 😼 **The Rascala!** (the cowboy cat) → Continue ▶. End the game → every phone says **Thanks For Playing!**	☐

TV, SOUND AND SAFETY

28	**TV** NEW	Audience View on the TV: the question is readable from the back of the room, with scores along the bottom. With your party theme on, its drawn backdrop sits behind the quiz and never covers the text.	☐
29	**Sounds** NEW	Listen at your usual volume: the intro (**MIND IT!**, explosion, last riff), correct (ding + score pop) / wrong, a phone's BUZZ IN, the whoosh to a new board, the Triple Gamble dice, the Phoenix rise, The Rascala!. Note anything too loud or quiet.	☐
30	**Intermission** NEW	⋯ → ☕ **Intermission** → 2 min: the TV counts down with the standings, quiet theme music plays. Resume fades it out.	☐
31	**Saved game** NEW	Mid-game, close Mind It! on the laptop and open it again; close it once more *without choosing* and reopen → still offered → **Resume saved game** → the same scores, board and teams.	☐
32	**Backup**	⋯ → 💾 **Backups & Restore** → **Back Up Now**. Restore from that file: it always asks first (Restore Backup), and everything comes back.	☐
33	**Rehearsal end**	End the rehearsal → Historic Games has no new game (rehearsals aren't saved).	☐
34	**Test Hosting**	Connect Device → **Run Test** → **Ready to host**. Afterwards 📋 **Rehearsal Report** → **Save Report File**.	☐
35	**TV, no cable**	📡 **Connect Audience Screen** → type its short address (e.g. **192.168.1.20/tv**) on the TV → Full Screen → **Test** passes.	☐
36	**Move the quiz**	Tablet quiz → laptop **Take Over Tablet Quiz** → approve. Then back: laptop **Hand Quiz to the Galaxy Tab** → tablet **Host It on This Tablet**. Same scores, phones keep their team.	☐
37	**TV sound**	🔊 **Sound On This TV** → OK on the TV remote → the sounds come from the TV, the laptop goes quiet. TV off → back on the laptop.	☐

If something doesn't look right: note the step number, which device (laptop / tablet / which phone / TV), what you did and what happened — a photo or screenshot helps. Send me those notes and the 📋 **Rehearsal Report** file, and I'll fix it.