MIND IT! REHEARSAL CHECKLIST

Run on the real laptop, tablet, phones and TV · about 40 minutes

Date: Tablet: Galaxy Tab Phones:

The automatic checks on the build computer already cover these features. This list is for what only real devices can show: Wi-Fi, sound, vibration, the TV and touch screens. Tick each step; a **NEW** tag marks what changed since the last checklist (build 98).

BEFORE YOU START

1	**Laptop** NEW	Put the three **Mind It!.exe** parts and **Join Mind It - build 134.bat** in one folder → run the .bat → open **Mind It!.exe**. Laptop, tablet and phones on the same Wi-Fi. First time only: let Windows allow private-network access.	☐
2	**Tablet**	Install **Mind It! for Android (Galaxy Tab).apk** over the old one — it updates without losing anything (version 1.69, build 132).	☐
3	**Phones**	Two or more phones — ideally one Android and one iPhone.	☐
4	**Rehearsal**	On the laptop: Setup → 🎭 **Rehearsal**. Nothing you do is saved, so try everything freely.	☐
5	**Check Connections** NEW	Next to Begin Game: 📶 **Check Connections** → **Test All Connections**. Laptop, tablet and each joined phone show Connected — and stay Connected over a minute, no flicker; a team without a phone is named in the summary.	☐

TABLET (QUIZMASTER REMOTE)

6	**PIN keypad**	Tablet home → Connect To Laptop → tap the found laptop. The PIN box opens the number keypad. Enter the PIN → it connects.	☐
7	**Reconnect**	Close Mind It! on the tablet and open it again → it goes straight back in without asking for the PIN.	☐
8	**Controls**	Answer card (tap to show) · Correct / Wrong / Pass · the timer tile pauses and starts the laptop's timer.	☐
9	**Drop-out**	Turn the tablet's Wi-Fi off for 10 s → "Reconnecting…" / "Connection Lost". Turn it on → it recovers, scores unchanged.	☐

TEAM PHONES

10	**Joining** NEW	Before the game the TV shows the **join QR code**. Each phone scans it and types its team code. The header shows team, place and score.	☐
11	**Timer**	During a question the phone shows ⏱ counting down within 1–2 s of the TV, turning gold for the last 10 s.	☐
12	**Vibration** NEW	**Android phones** buzz when their wager opens and when it's their turn to pick (iPhones can't — they just show it).	☐
13	**Daily Double**	TV shows the gold "DAILY DOUBLE!", then the wager screen. The phone's number pad + Lock In works; the laptop gets the amount.	☐
14	**Triple Gamble**	On the team's turn, the "Your chips" row shows Use → confirm → pick a question. TV shows the dice moment and the casino sound; the question can't be passed.	☐
15	**Phoenix**	From Round 2, a last-place team **more than 2,000 behind** gets the 🔥 Phoenix: Use → Confirm → pick. Right = double + 20% of the gap, never past the leader ("PHOENIX RISES!"); wrong = nothing lost. Once per game.	☐
16	**Bottoms Up**	Round 1: Use → choose the designated player → Confirm → pick → answer wrong → ✓ Finished (nothing lost) or ✕ Not finished (normal loss).	☐
17	**Drop-out**	Turn a phone's Wi-Fi off for 10 s → "Connection Lost". Turn it on → back in the game with the same team (no new code).	☐

Continue on page 2

MIND IT! REHEARSAL CHECKLIST

Run on the real laptop, tablet, phones and TV · about 40 minutes

SCORES ON THE TV

18	**Places** NEW	Once scores differ, each TV score card shows its place (1st in gold).	☐
19	**Speed bonus** NEW	Answer within the first seconds: the laptop's Correct button shows ⚡ **+100** and the TV adds it.	☐

PHONE BUZZER MODE

20	**Buzzer Test**	Setup → 3 · Gameplay & Rules → Phone Buzzer Mode → **Buzzer Test**: each phone's tap turns green within about a second. Close it and open it again → taps still register.	☐
21	**Before a buzz** NEW	Open a question: the TV says **Phone Buzzers** · 🔔 **Any Team Can Buzz**; the laptop *and the tablet* show 🔔 **Waiting For A Buzz...** instead of Correct / Wrong. In Buzzer Mode the tablet has no "Up Next" turn line (who answers depends on the buzz).	☐
22	**In the game**	Tap too early → briefly locked. First buzz wins → Correct / Wrong come back, and the laptop says who buzzed first. Wrong → TV "WRONG ANSWER → BUZZERS REOPEN".	☐
23	**Nobody buzzed** NEW	Someone answers out loud without buzzing → laptop: **A different team answered?** → score that team.	☐

FINAL ROUND

24	**Wagers** NEW	Wager pad (All in · Half · Nothing) → Lock In. The Final question can't be switched once the Final has started.	☐
25	**Answers** NEW	Answer box shows "⭐ Final Round · wager locked · N s left". Submit → "Answer Locked". Let one phone run out of time: about 2 s later it shows ⏱ **Time's Up** and no longer accepts an answer.	☐
26	**Change a wager**	After the question appears: laptop **Change a wager** (or the tablet's Change) → new amount → the team's phone shows it; the TV keeps it hidden.	☐
27	**Finish** NEW	End the game → every phone says **Thanks For Playing!**; the TV shows the winner podium with each team's correct answers.	☐

TV, SOUND AND SAFETY

28	**TV**	Audience View on the TV: the question is readable from the back of the room, with scores along the bottom.	☐
29	**Sounds** NEW	Listen at your usual volume: the new intro (**MIND IT!**, explosion, last riff), board, correct / wrong, the Triple Gamble sting, the Phoenix screech. Note anything too loud or quiet.	☐
30	**Intermission** NEW	⋯ → ☕ **Intermission** → 2 min: the TV counts down with the standings, quiet theme music plays. Resume fades it out.	☐
31	**Saved game** NEW	Mid-game, close Mind It! on the laptop and open it again; close it once more *without choosing* and reopen → still offered → **Resume saved game** → the same scores, board and teams.	☐
32	**Backup**	⋯ → 💾 **Backups & Restore** → **Back Up Now**. Restore from that file: it always asks first (Restore Backup), and everything comes back.	☐
33	**Rehearsal end**	End the rehearsal → Historic Games has no new game (rehearsals aren't saved).	☐
34	**Test Hosting**	Connect Device → **Run Test** → **Ready to host**. Afterwards 📋 **Rehearsal Report** → **Save Report File**.	☐
35	**TV, no cable**	📡 **Connect Audience Screen** → type its short address (e.g. **192.168.1.20/tv**) on the TV → Full Screen → **Test** passes.	☐
36	**Move the quiz**	Tablet quiz → laptop **Take Over Tablet Quiz** → approve. Then back: laptop **Hand Quiz to the Galaxy Tab** → tablet **Host It on This Tablet**. Same scores, phones keep their team.	☐
37	**TV sound**	🔊 **Sound On This TV** → OK on the TV remote → the sounds come from the TV, the laptop goes quiet. TV off → back on the laptop.	☐

If something doesn't look right: note the step number, which device (laptop / tablet / which phone / TV), what you did and what happened — a photo or screenshot helps. Send me those notes and the 📋 **Rehearsal Report** file, and I'll fix it.