


Create and Configure the Auto Scaling Group in EC2

Last Updated : 9 Jun, 2026



AWS Auto Scaling automatically scales EC2 instances up or down based on incoming traffic demand. It helps reduce application latency and can be integrated with AWS services like [Amazon DynamoDB](#) and [Amazon Aurora](#).




Benefits of Auto Scaling

- **Dynamic Scaling:** Automatically scales applications up or down based on traffic demand.
- **Pay for What You Use:** Optimizes resource usage and reduces unnecessary cost.
- **Automatic Performance Maintenance:** Maintains application performance during workload changes.

How AWS Auto Scaling Working

AWS autoscaling will scale the application based on the load of application. Instead of scaling manually AWS auto scaling will scale the application automatically when the incoming traffic is high it will scale up the application and when the traffic is low it will scale down the application.




First you should choose which service or an application you want to scale then select the optimization way like cost and performance and then keep track how the scaling is working.


Steps To create Auto Scaling Launch Template

Step 1: Click on the All Services on AWS Dashboard


Step 2: Click on the EC2(Elastic Cloud Computing).




Step 3: Scroll Down and click on the Launch Templates and click on the Create launch template




Step 3: Scroll Down and click on the Launch Templates and click on the Create launch template




Step 4: Type the Template name.




Step 5: Select the Amazon Machine Image.



Step 6: Select the Instance Type and Key pair.



Step 7: Select the Security Group or Create the new one.



Step 7: Select the Security Group or Create the new one.

Network settings [Info](#)

Subnet [Info](#)

Don't include in launch template [Create new subnet](#)

When you specify a subnet, a network interface is automatically added to your template.

Availability Zone [Info](#)

Don't include in launch template [Enable additional zones](#)

Firewall (security groups) [Info](#)

A security group is a set of firewall rules that control the traffic for your instance. Add rules to allow specific traffic to reach your instance.

☒ Select existing security group ☐ Create security group

Security groups [Info](#)

Select security groups [Compare security group rules](#)

default sg-06e2ebabcd16ae6f8 [X](#)

VPC: vpc-034a43ec2832d7f54

Step 8: Click on the Create Launch Template.

Network settings [Info](#)

Subnet [Info](#)

Don't include in launch template [Create new subnet](#)

When you specify a subnet, a network interface is automatically added to your template.

Availability Zone [Info](#)

Don't include in launch template [Enable additional zones](#)

Firewall (security groups) [Info](#)

A security group is a set of firewall rules that control the traffic for your instance. Add rules to allow specific traffic to reach your instance.

☒ Select existing security group ☐ Create security group

Security groups [Info](#)

Select security groups [Compare security group rules](#)

default sg-06e2ebabcd16ae6f8 [X](#)

VPC: vpc-034a43ec2832d7f54

Advanced network configuration

Summary

Software Image (AMI)

Amazon Linux 2023 AMI 2023.11...[read more](#)

ami-0236922087fa98b6e

Virtual server type (instance type)

t2.micro

Firewall (security group)

default

Storage (volumes)

1 volume(s) - 8 GiB

[Cancel](#) [Create launch template](#)

Step 9: Now you can see the template is created. Now, scroll down and click on the Auto Scaling Groups.

Launch Templates (1) [Info](#)

[Search](#)

Launch Template ID	Launch Template Name	Default Version	Latest Version	Create Time	Created By
lt-01cb184ab77aa182d	my-template	1	1	2026-05-22T08:55:30.000Z	arn:aws:iam::548598294183:root

Select a launch template

Auto Scaling

Auto Scaling Groups

Create An Auto Scaling Group Using a Launch Template

Step 1: Click on the Create Auto Scaling group.

Amazon EC2 Auto Scaling

helps maintain the availability of your applications

Auto Scaling groups are collections of Amazon EC2 instances that enable automatic scaling and fleet management features. These features help you maintain the health and availability of your applications.

Create Auto Scaling group

Get started with EC2 Auto Scaling by creating an Auto Scaling group.

[Create Auto Scaling group](#)

Step 2: Type the Auto Scaling group name.

Step 1

Choose launch template [Info](#)

Specify a launch template that contains settings common to all EC2 instances that are launched by this Auto Scaling group.

Name

Auto Scaling group name

Enter a name to identify the group.

my-scaling

Must be unique to this account in the current Region and no more than 255 characters.

Launch template [Info](#)

For accounts created after May 31, 2023, the EC2 console only supports creating Auto Scaling groups with launch templates. Creating Auto Scaling groups with launch configurations is not recommended but still available via the CLI and API until December 31, 2023.

Launch template

Choose a launch template that contains the instance-level settings, such as the Amazon Machine Image (AMI), instance type, key pair, and security groups.

Select a launch template [Create a launch template](#)

Step 5 - optional
Add notifications

Step 6 - optional
Add tags

Step 7
Review

Must be unique to this account in the current Region and no more than 155 characters.

Launch template Info

For accounts created after May 31, 2023, the EC2 console only supports creating Auto Scaling groups with launch templates. Creating Auto Scaling groups with launch configurations is not recommended but still available via the CLI and API until December 31, 2023.

Launch template
Choose a launch template that contains the instance-level settings, such as the Amazon Machine Image (AMI), instance type, key pair, and security groups.

Select a launch template

Create a launch template

Cancel Next

Step 3: Select your Template.

Launch template Info

For accounts created after May 31, 2023, the EC2 console only supports creating Auto Scaling groups with launch templates. Creating Auto Scaling groups with launch configurations is not recommended but still available via the CLI and API until December 31, 2023.

Launch template
Choose a launch template that contains the instance-level settings, such as the Amazon Machine Image (AMI), instance type, key pair, and security groups.

my-template

Create a launch template

Version
Default (1)

Create a launch template version

Description	Launch template	Instance type
-	my-template lt-01cb184ab77aa182d	t2.micro

Step 4: Select the VPC or go with the default VPC and also select the Availability zone.

Network Info

For most applications, you can use multiple Availability Zones and let EC2 Auto Scaling balance your instances across the zones. The default VPC is getting started quickly.

VPC
Choose the VPC that defines the virtual network for your Auto Scaling group.

vpc-034a43ec2832d7f54
172.31.0.0/16 Default

Create a VPC

Availability Zones and subnets
Define which Availability Zones and subnets your Auto Scaling group can use in the chosen VPC.

Select Availability Zones and subnets

- use1-az2 (us-east-1b) | subnet-0b66a455dc2ee1ab3
172.31.80.0/20 Default
- use1-az1 (us-east-1a) | subnet-08acb1db903b9def7
172.31.0.0/20 Default
- use1-az4 (us-east-1c) | subnet-0abf9a1c06de73450
172.31.16.0/20 Default

Create a subnet

Step 5: Skip Integrate with other services

Step 6: Configure the Group size and Scaling policies.

Select as per your requirement:

- Desired: 4
- Minimum: 4
- Maximum: 8

Configure group size and scaling - optional Info

Define your group's desired capacity and scaling limits. You can optionally add automatic scaling to adjust the size of your group.

Group size Info
Set the initial size of the Auto Scaling group. After creating the group, you can change its size to meet demand, either manually or by using automatic scaling.

Desired capacity type
Choose the unit of measurement for the desired capacity value. vCPUs and Memory(GiB) are only supported for mixed instances groups configured with a set of instance types.

Units (number of instances)

Desired capacity
Specify your group size.

4

Scaling Info
You can resize your Auto Scaling group manually or automatically to meet changes in demand.

Scaling limits
Set limits on how much your desired capacity can be increased or decreased.

Min desired capacity
4
Equal or less than desired capacity

Max desired capacity
8
Equal or greater than desired capacity

Step 7: Select the Target tracking scaling policy.

Automatic scaling - optional

Choose whether to use a target tracking policy

No scaling policies

Target tracking scaling policy

Scaling policy name

Target Tracking Policy

Metric type

Average CPU utilization

Target value

50

Instance warmup

60 seconds

☐ Disable scale in to create only a scale-out policy

Step 8: Click on the Create Auto Scaling Group.

Step 5: Add notifications

No notifications

Step 6: Add tags

Tags (0)

Key	Value	Tag new instances
No tags		

Preview code

Cancel

Previous

Create Auto Scaling group

Now you can see the Auto Scaling is creating and it is also creating the desired state of the EC2 Instance

Auto Scaling groups (1)

Name	Status	Launch template / configuration	Instances	Instance health	Desired capacity	Min	Max
my-scaling	Updating capacity	my-template Version Default	0	-	4	4	8

We selected the Desired state equal to 4 and you can see the 4 Instance is Running

Instances (4)

Instance state = running

Name	Instance ID	Instance state	Instance type	Status check	Availability Zone	Public IPv4 DNS	Public IP
	i-02c1d09689b4442df	Running	t2.micro	Initializing	us-east-1c	ec2-98-81-243-81.com...	98.81.243.81
	i-0477ca9c7da887d59	Running	t2.micro	Initializing	us-east-1c	ec2-54-221-43-237.co...	54.221.43.237
	i-0e870aed3c15eb3ff	Running	t2.micro	Initializing	us-east-1b	ec2-100-55-41-16.com...	100.55.41.16
	i-05fc1bfb65c0f061	Running	t2.micro	Initializing	us-east-1a	ec2-3-239-110-131.co...	3.239.110.131