Complete feature reference

A detailed index of V4.0.0 aircraft, synchronized systems and optional equipment.

01
Aircraft
F-16CM / D / I

02
Multicrew
Pilot + WSO

03
Package system
Modular OvGME

01 / AIRCRAFT LINEUP

F-16 variants covered

F-16CM	Single-seat family with selectable additional systems, CPD, supported liveries and compatible stores.
F-16D / Barak	Two-seat family including Block 30, 40, 50 and 52 choices; applicable spine and NS/no-spine model variants.
F-16I Sufa	Two-seat family with Sufa-specific cockpit treatment, CFT options and reworked RWR display.

02 / CONTROLS

How to use each cockpit

0 + 9 / SOLO

Switch front and rear cockpit in singleplayer, when using a dual-seat aircraft.

R / MULTICREW

Request flight-control handover without changing the physical seat.

VERSION LABEL

V4.0.0 is the public release name. Internal development and test build numbers are not separate public versions.

Cold-start synchronization

Power, avionics, engine start and INS across both seats.

03 / CREW POWER & STARTUP

Shared cold-start functions

Main Power	Electrical power switch positions in the supported two-seat startup workflow.
JFS / start	Starter operation and shared engine-start OFF-to-IDLE action.
Avionics power	MMC, ST STA, MFD, UFC, GPS, DL, MAP and MIDS master power where available.
Sensor & weapon	Supported sensor/weapon-power switches, including L/R hardpoint-related switches, FCR and radar altimeter.
IFF Master	Shared IFF Master switch state; this does not claim IFF-code synchronization.
RWR Power	RWR power knob shared between front and rear cockpits; it is not a full threat-display sync.
INS control	INS mode selector, coordinated readiness and simultaneous INS alignment on both clients.

INS PROCEDURE

After the INS alignment is complete, **press RTN (Return) manually** to exit the INS DED page. Both clients run their own native alignment process, even when the mode/sequence is coordinated.

Multicrew flight systems

Flight control, navigation, crew management and ground services.

04 / FLIGHT & ENGINE

Systems coordinating in both directions

Throttle	Throttle-follow behavior from the currently controlling seat, with control handover.
Engine readouts	RPM, fuel flow (including indication), fuel level, engine sound and nozzle open indication.
Speedbrakes	Steering and state follow between the front and rear cockpits.
Landing gear	Gear lever and deployed state, including handovers while lowering/after deployment.
Flight / safety	Master Arm, Laser Arm, Nosewheel Steering and canopy with yellow canopy handle.

05 / MISSIONS & CONTROLS

Weapons, navigation and roles

Flight modes	A-A, A-G and Dogfight changes without requiring full flight-control ownership.
DED / waypoints	Shared waypoint/steerpoint entry, including coordinated changes between seats.
Stores config	Shared CAT I/III stores-related configuration on supported aircraft.
Request Control	Press R; roles swap flight-control authority, not cockpit positions.

REARM / REFUEL - BOTH PLAYERS

Each player must independently request/complete a rearm or refuel through the ground crew on their own PC. Otherwise local fuel/stores can diverge and cause synchronization errors.

Weapons & optional packages

What you may install, enable or select in the loadout.

06 / OVGME PACKAGES

Only two are core requirements.

Core aircraft	DCMii-Project-F-16I_Sufa is needed for the aircraft experience.
Core sounds	DCMii-Project-F-16I Sufa PW-229 Sounds is the paired core sound package.
Optional TGP	Advanced Targeting / custom AN/AAQ-33 targeting pod package.
Optional AGM-154B	Separate mod package; enable if you want that weapon capability.
Optional Python-5	Separate missile package; independent of the other optional add-ons.
Optional SPICE 2000	Separate guided-weapon package; leave disabled to preserve standard compatible bomb choices.

07 / AIRCRAFT EQUIPMENT

Other loadout features

Internal ECM jammer	Can be selected in the loadout on compatible F-16 models; not a statement of ECM cockpit sync.
CFT & fuel tanks	Compatible conformal and external fuel-tank configurations, including variant-specific options.
Mission loadouts	Weapon, CFT and fuel-tank combinations depend on the selected airframe and supported station configuration.

WEAPON COMPATIBILITY

Available add-ons do not imply every mixed weapon, pylon and CFT combination is supported. Use configurations intended for the selected aircraft.

Avionics & visual upgrades

Cockpit displays, RWR, HUD, HMD and liveries.

08 / COCKPIT DISPLAYS

Aircraft-specific improvements



Sufa RWR / in-game

F-16I Sufa RWR
Sufa-style continuous blue ring and center dot, clear lock line, Flare/Chaff counts below the ring and PWR OFF display state. DED CNI uses GRN / RED radio labels.

HUD/HMD rework	Applies across the dual-seat F-16D and F-16I family; optional sharper HUD/HMD lines.
Rear HUD repeater	Live grayscale camera with HUD symbology for supported rear cockpits; **not on Barak Block 30**.
Single-seat CPD	Center Pedestal Display integrated for the supported single-seat aircraft, based on Kaiqi / Pobit work.
Liveries pack	F-16C_50 and F-16D_50 liveries, including Bulgarian, Israeli, Hellenic and Moroccan-themed paint schemes.
Visual maintenance	Further texture and material improvements and updates for current DCS compatibility.

Known limits & quick lookup

Clear scope boundaries and installation references.

09 / INTENTIONALLY NOT SYNCHRONIZED

The limits of native DCS systems

Native SMS counter	The weapon-count display is not synchronized, although actual weapon state can otherwise be represented differently on the clients.
TGP / FCR tracking	Pod/radar cursor and target lock stay local; no cross-seat cursor/lock synchronization.
INS implementation	Controls and alignment workflow are shared, but underlying native alignments progress on each client.
RWR / CMDS / ECM	RWR Power is shared, not all threats; CMDS/ECM system states are not claimed as synchronized.

10 / DISTRIBUTION LOOKUP

Where the files go

Required Main ZIP	Includes DCS_ROOT.zip (six separate OvGME packages) and SAVED_GAMES.zip (Scripts).
Optional livery ZIP	Includes the Liveries top-level folder with F-16C_50 and F-16D_50 skins.
Server support	Use a matching client build and a compatible DCMii multiplayer server.

OPERATIONAL REMINDER

During multiplayer rearm/refuel, the pilot and WSO must **both** do the ground-crew service on their respective clients. See the Beginner's Guide for the crew procedure.

Credits: Digital Combat Mod Integration Intelligence (DCMii) - development/integration; IDF Mods Project - aircraft base; Kaiqi / Pobit - CPD; Roughmaster and Crash - liveries. Thanks to Sylvi and all testers.