

Carnet: 0051316

Eje. 1


red personalizada

10.05.13.0/24

Eje. 3

red personalizada

172.16.0.0/24



```
PC1
Source code and license can be found at vpcs.sf.net.
For more information, please visit wiki.freecode.com.cn.

Press '?' to get help.

Executing the startup file

PC1> ip 172.16.5.2 255.255.255.192 172.16.5.1
Checking for duplicate address...
PC1 : 172.16.5.2 255.255.255.192 gateway 172.16.5.1

PC1> show ip

NAME          : PC1[1]
IP/MASK        : 172.16.5.2/26
GATEWAY        : 172.16.5.1
DNS            :
MAC           : 00:50:79:66:68:00
LPORT         : 10021
RHOST:PORT     : 127.0.0.1:10020
MTU           : 1500
```

Source code and license can be found at vpcs.sf.net.
For more information, please visit wiki.freecode.com.cn.

Press '?' to get help.

Executing the startup file

```
PC2> ip 172.16.5.66 255.255.255.224 172.16.5.65
Checking for duplicate address...
PC1 : 172.16.5.66 255.255.255.224 gateway 172.16.5.65
```

```
PC2> show ip
```

```
NAME       : PC2[1]
IP/MASK     : 172.16.5.66/27
GATEWAY     : 172.16.5.65
DNS         :
MAC         : 00:50:79:66:68:01
LPORT      : 10009
RHOST:PORT  : 127.0.0.1:10008
MTU         : 1500
```

 PC3

Source code and license can be found at vpcs.sf.net.
For more information, please visit wiki.freecode.com.cn.

Press '?' to get help.

Executing the startup file

```
PC3> ip 172.16.5.98 255.255.255.240 172.16.5.97
Checking for duplicate address...
PC1 : 172.16.5.98 255.255.255.240 gateway 172.16.5.97
```

```
PC3> show ip
```

```
NAME       : PC3[1]
IP/MASK     : 172.16.5.98/28
GATEWAY     : 172.16.5.97
DNS         :
MAC         : 00:50:79:66:68:02
LPORT      : 10003
RHOST:PORT  : 127.0.0.1:10002
MTU         : 1500
```

 PC4

Source code and license can be found at vpcs.sf.net.
For more information, please visit wiki.freecode.com.cn.

Press '?' to get help.

Executing the startup file

```
PC4> ip 172.16.5.114 255.255.255.240 172.16.5.113
Checking for duplicate address...
PC1 : 172.16.5.114 255.255.255.240 gateway 172.16.5.113
```

```
PC4> show ip
```

```
NAME       : PC4[1]
IP/MASK     : 172.16.5.114/28
GATEWAY     : 172.16.5.113
DNS         :
MAC         : 00:50:79:66:68:03
LPORT      : 10001
RHOST:PORT  : 127.0.0.1:10000
MTU        : 1500
```

 PC5

Source code and license can be found at vpcs.sf.net.
For more information, please visit wiki.freecode.com.cn.

Press '?' to get help.

Executing the startup file

```
PC5> ip 172.16.5.130 255.255.255.248 172.16.5.129
Checking for duplicate address...
PC1 : 172.16.5.130 255.255.255.248 gateway 172.16.5.129
```

```
PC5> show ip
```

```
NAME       : PC5[1]
IP/MASK     : 172.16.5.130/29
GATEWAY     : 172.16.5.129
DNS         :
MAC         : 00:50:79:66:68:04
LPORT      : 10019
RHOST:PORT  : 127.0.0.1:10018
MTU        : 1500
```

```
PC5> █
```

```

R1
R1(config)#
*Mar 1 00:02:12.815: %LINEPROTO-5-UPDOWN: Line protocol on Interface Serial1/0, changed sta
R1(config)#
*Mar 1 00:02:32.787: %LINEPROTO-5-UPDOWN: Line protocol on Interface Serial1/0, changed sta
*Mar 1 00:02:32.931: %OSPF-5-ADJCHG: Process 1, Nbr 172.16.5.149 on Serial1/0 from LOADING
one
R1(config)#show ip interface brief
^
% Invalid input detected at '^' marker.

R1(config)#show ip interface brief
^
% Invalid input detected at '^' marker.

R1(config)#do show ip interface brief
Interface                IP-Address      OK? Method Status          Protocol
FastEthernet0/0          172.16.5.113    YES manual up              up
FastEthernet0/1          unassigned      YES unset  administratively down down
Serial1/0                 172.16.5.141    YES manual up              up
Serial1/1                 172.16.5.137    YES manual up              up
Serial1/2                 unassigned      YES unset  administratively down down
Serial1/3                 unassigned      YES unset  administratively down down
R1(config)##do show ip interface brief
R1(config)#

```

```

R2
*Mar 1 00:01:40.099: %LINEPROTO-5-UPDOWN: Line protocol on Interface Serial1/3, changed stat
R2(config)#
*Mar 1 00:02:02.959: %LINEPROTO-5-UPDOWN: Line protocol on Interface Serial1/2, changed stat
*Mar 1 00:02:02.963: %LINEPROTO-5-UPDOWN: Line protocol on Interface Serial1/3, changed stat
R2(config)#
*Mar 1 00:02:12.939: %LINEPROTO-5-UPDOWN: Line protocol on Interface Serial1/2, changed stat
*Mar 1 00:02:13.067: %OSPF-5-ADJCHG: Process 1, Nbr 172.16.5.149 on Serial1/2 from LOADING t
one
R2(config)#
*Mar 1 00:02:32.959: %LINEPROTO-5-UPDOWN: Line protocol on Interface Serial1/3, changed stat
R2(config)#do do show ip interface brief
do show ip interface brief
^
% Invalid input detected at '^' marker.

R2(config)#do show ip interface brief
Interface                IP-Address      OK? Method Status          Protocol
FastEthernet0/0          172.16.5.65     YES manual up              up
FastEthernet0/1          unassigned      YES unset  administratively down down
Serial1/0                 unassigned      YES unset  administratively down down
Serial1/1                 172.16.5.138    YES manual up              up
Serial1/2                 172.16.5.145    YES manual up              up
Serial1/3                 172.16.5.153    YES manual up              up
R2(config)#

```

```

R3
*Mar 1 00:01:46.203: %LINK-3-UPDOWN: Interface Serial1/3, changed state to up
*Mar 1 00:01:46.319: %LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0, change
*Mar 1 00:01:46.927: %LINEPROTO-5-UPDOWN: Line protocol on Interface Serial1/0, changed stat
*Mar 1 00:01:47.067: %LINEPROTO-5-UPDOWN: Line protocol on Interface Serial1/2, changed stat
*Mar 1 00:01:47.207: %LINEPROTO-5-UPDOWN: Line protocol on Interface Serial1/3, changed stat
R3(config)#
R3(config)#
*Mar 1 00:02:02.871: %OSPF-5-ADJCHG: Process 1, Nbr 172.16.5.141 on Serial1/0 from LOADING t
one
*Mar 1 00:02:03.031: %OSPF-5-ADJCHG: Process 1, Nbr 172.16.5.153 on Serial1/2 from LOADING t
one
R3(config)#
*Mar 1 00:02:13.027: %LINEPROTO-5-UPDOWN: Line protocol on Interface Serial1/3, changed stat
R3(config)#
*Mar 1 00:03:12.999: %LINEPROTO-5-UPDOWN: Line protocol on Interface Serial1/3, changed stat
R3(config)#do show ip interface brief
Interface                IP-Address      OK? Method Status          Protocol
FastEthernet0/0          172.16.5.97     YES manual up              up
FastEthernet0/1          unassigned      YES unset  administratively down down
Serial1/0                 172.16.5.142    YES manual up              up
Serial1/1                 unassigned      YES unset  administratively down down
Serial1/2                 172.16.5.146    YES manual up              up
Serial1/3                 172.16.5.149    YES manual up              up
R3(config)#

```

```

R5(config)#exit
R5#
*Mar 1 00:02:19.007: %SYS-5-CONFIG_I: Configured from console by console
R5#
*Mar 1 00:02:23.703: %LINEPROTO-5-UPDOWN: Line protocol on Interface Serial1/0, c
R5#
*Mar 1 00:02:53.675: %LINEPROTO-5-UPDOWN: Line protocol on Interface Serial1/0, c
R5#do show ip interface brief
^
% Invalid input detected at '^' marker.

R5#do show ip interface brief
^
% Invalid input detected at '^' marker.

R5#show ip interface brief
Interface                IP-Address      OK? Method Status          Protoc
FastEthernet0/0          172.16.5.1      YES manual up              up
FastEthernet0/1          unassigned      YES unset  administratively down down
Serial1/0                 172.16.5.158    YES manual up              up
Serial1/1                 unassigned      YES unset  administratively down down
Serial1/2                 unassigned      YES unset  administratively down down
Serial1/3                 172.16.5.154    YES manual up              up
R5#

```



R4

```
R4(config)#! Ruta estatica directa a la LAN de PC1 (vecino R5)
R4(config)#ip route 172.16.5.0 255.255.255.192 172.16.5.158
R4(config)#! Ruta por defecto hacia la zona OSPF (a travis de R3)
R4(config)#ip route 0.0.0.0 0.0.0.0 172.16.5.149
R4(config)#exit
*Mar  1 00:02:14.087: %LINK-3-UPDOWN: Interface FastEthernet0/0, changed state to up
*Mar  1 00:02:14.683: %LINK-3-UPDOWN: Interface Serial1/0, changed state to up
*Mar  1 00:02:14.831: %LINK-3-UPDOWN: Interface Serial1/3, changed state to up
*Mar  1 00:02:15.087: %LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0,
R4(config)#exit
*Mar  1 00:02:15.687: %LINEPROTO-5-UPDOWN: Line protocol on Interface Serial1/0, change
*Mar  1 00:02:15.835: %LINEPROTO-5-UPDOWN: Line protocol on Interface Serial1/3, change
R4(config)#exit
R4#sh
*Mar  1 00:09:13.859: %SYS-5-CONFIG_I: Configured from console by console
R4#show ip interface brief
Interface                IP-Address      OK? Method Status          Protocol
FastEthernet0/0          172.16.5.129    YES manual up              up
FastEthernet0/1          unassigned      YES unset  administratively down down
Serial1/0                 172.16.5.157    YES manual up              up
Serial1/1                 unassigned      YES unset  administratively down down
Serial1/2                 unassigned      YES unset  administratively down down
Serial1/3                 172.16.5.150    YES manual up              up
R4#
```