


Windows Lab 6


By Jai Pandey (260840140011)

Question 1

Open Server Manager > Manage > Add Roles and Features



Select Server Roles > Web Server (IIS) > Add Features



Confirm Installation

Add Roles and Features Wizard

DESTINATION SERVER
master.tfsi.com

Confirm installation selections

Before You Begin
Installation Type
Server Selection
Server Roles
Features
Web Server Role (IIS)
Role Services
Confirmation
Results

To install the following roles, role services, or features on selected server, click Install.

☒ Restart the destination server automatically if required

Optional features (such as administration tools) might be displayed on this page because they have been selected automatically. If you do not want to install these optional features, click Previous to clear their check boxes.


Web Server (IIS)

- Management Tools
 - IIS Management Console
- Web Server
 - Common HTTP Features
 - Default Document
 - Directory Browsing
 - HTTP Errors
 - Static Content
 - Health and Diagnostics
 - HTTP Logging
 - Performance
 - Static Content Compression
 - Security
 - Request Filtering


[Export configuration settings](#)
[Specify an alternate source path](#)

< Previous Next > **Install** Cancel


Server Manager > Tools > Internet Information Services (IIS) Manager



Right Click on Sites > Add Website



Create folders for each websites, on C:\\inetpub\\
Add index.html for each one of them



Fill out the information for our website

Add Website ? X

Site name: Application pool:

Content Directory

Physical path:

Pass-through authentication

Binding

Type: IP address: Port:

Host name:

Example: www.contoso.com or marketing.contoso.com

☒ Start Website immediately

Similarly, create entries for all of them


Connections

- Start Page
- MASTER (TFS)\Administrator
 - Application Pools
 - Sites**
 - Default Web Site
 - learn.phoenix.lab
 - www.micromax.lab
 - www.webhost.lab

Sites

Name	ID	Status	Binding	Path
Default Web Site	1	Started (ht...	*:80 (http)	%SystemDrive%\inetpub\wwwroot
learn.phoenix.lab	2	Started (ht...	learn.phoenix.lab on 192.168.200...	C:\inetpub\phoenix.lab
www.micromax...	3	Started (ht...	www.micromax.lab on 192.168.20...	C:\inetpub\micromax.lab
www.webhost.lab	4	Started (ht...	www.webhost.lab on 192.168.200...	C:\inetpub\webhost.lab

Add forward lookup zones for each website





Add an A record with the following details:

The 'New Host' dialog box is shown with the following fields and options:

- Name (uses parent domain name if blank):** learn
- Fully qualified domain name (FQDN):** learn.phoenix.lab.
- IP address:** 192.168.200.100
- ☒ Create associated pointer (PTR) record
- ☐ Allow any authenticated user to update DNS records with the same owner name

Buttons at the bottom: Add Host, Cancel


Verification (Client)




Question 2

We need to disable VMware's Virtual DHCP server


Go to Edit > Virtual Network Editor



Click on "Change Setting" button



Select the NAT type adaptor
Then uncheck use local DHCP service



The screenshot shows the 'Virtual Network Editor' window. At the top, there is a table listing three virtual networks: VMnet0 (Bridged), VMnet1 (Host-only), and VMnet8 (NAT). VMnet8 is selected. Below the table are buttons for 'Add Network...', 'Remove Network', and 'Rename Network...'. The 'VMnet Information' section shows 'NAT (shared host's IP address with VMs)' selected. Under this, 'Connect a host virtual adapter to this network' is checked, and the 'Host virtual adapter name' is 'VMware Network Adapter VMnet8'. The option 'Use local DHCP service to distribute IP address to VMs' is checked and highlighted with a red rectangle. At the bottom, there are input fields for 'Subnet IP' (192.168.200.0) and 'Subnet mask' (255.255.255.0), and a row of buttons: 'Restore Defaults', 'Import...', 'Export...', 'OK', 'Cancel', 'Apply', and 'Help'.

Name	Type	External Connection	Host Connection	DHCP	Subnet Address
VMnet0	Bridged	Auto-bridging	-	-	-
VMnet1	Host-only	-	Connected	Enabled	192.168.224.0
VMnet8	NAT	NAT	Connected	Enabled	192.168.200.0

Buttons: Add Network..., Remove Network, Rename Network...

VMnet Information

☐ Bridged (connect VMs directly to the external network)

Bridged to: Automatic Automatic Settings...

☒ NAT (shared host's IP address with VMs) NAT Settings...

☐ Host-only (connect VMs internally in a private network)

☒ Connect a host virtual adapter to this network


Host virtual adapter name: VMware Network Adapter VMnet8

☒ Use local DHCP service to distribute IP address to VMs DHCP Settings...


Subnet IP: 192.168.200.0 Subnet mask: 255.255.255.0

Buttons: Restore Defaults, Import..., Export..., OK, Cancel, Apply, Help


Open Server Manager > Manage > Add Roles and Features




Select Server Roles > DHCP service > Add Features



Restart the machine after installation



Go to Server Manager > DHCP (sidebar) > More..(Banner)



Click on Complete DHCP configuration

The screenshot shows a window titled "All Servers Task Details and Notifications". It displays a list of tasks. The first task is "Post-deployment Configuration" with a status of "Not Sta..." and a message "Configuration required for DHCP Server at MA...". The "Action" column for this task shows a link "Complete DHCP configuration", which is highlighted with a red rectangle. Below this, there is a section for notifications, showing a notification "Launch the DHCP post-install wizard" with a time stamp of "9/15/2026 12:26:37 AM".

Status	Task Name	Stage	Message	Action	Notifications
⚠	Post-deployment Configuration	Not Sta...	Configuration required for DHCP Server at MA...	Complete DHCP configuration	1

Status	Notification	Time Stamp
ℹ	Launch the DHCP post-install wizard	9/15/2026 12:26:37 AM

Click on Skip AD authorization and commit

The screenshot shows the "DHCP Post-Install configuration wizard" window, specifically the "Authorization" step. The left sidebar has "Authorization" selected. The main area is titled "Specify the credentials to be used to authorize this DHCP server in AD DS." and contains three radio button options: "Use the following user's credentials" (with a text box containing "TFS\\Administrator"), "Use alternate credentials" (with a text box and a "Specify..." button), and "Skip AD authorization" (which is selected and highlighted with a red rectangle). At the bottom of the window, there are four buttons: "< Previous", "Next >", "Commit" (highlighted with a red rectangle), and "Cancel".

Authorization

Description

Authorization

Summary

Specify the credentials to be used to authorize this DHCP server in AD DS.

☐ Use the following user's credentials

User Name: TFS\\Administrator


☐ Use alternate credentials

User Name: Specify...


☒ Skip AD authorization

< Previous Next > Commit Cancel


Click on close



Go to DHCP Manager (Server Manager > Tools > DHCP)
Right click on IPv4 and select New Scope



Enter Scope Name and Description



New Scope Wizard

Scope Name
You have to provide an identifying scope name. You also have the option of providing a description.


Type a name and description for this scope. This information helps you quickly identify how the scope is to be used on your network.

Name:

Description:

< Back Next > Cancel

Enter IP address range for DHCP Pool and enter CIDR in length box



New Scope Wizard

IP Address Range
You define the scope address range by identifying a set of consecutive IP addresses.

Configuration settings for DHCP Server

Enter the range of addresses that the scope distributes.

Start IP address:

End IP address:

Configuration settings that propagate to DHCP Client

Length:

Subnet mask:

< Back Next > Cancel

Skip adding Exclusions and Delay

New Scope Wizard

Add Exclusions and Delay

Exclusions are addresses or a range of addresses that are not distributed by the server. A delay is the time duration by which the server will delay the transmission of a DHCP OFFER message.

Type the IP address range that you want to exclude. If you want to exclude a single address, type an address in Start IP address only.

Start IP address: End IP address:

Excluded address range:

Subnet delay in milli second:

< Back **Next >** Cancel

Keep the default lease duration

New Scope Wizard

Lease Duration

The lease duration specifies how long a client can use an IP address from this scope.

Lease durations should typically be equal to the average time the computer is connected to the same physical network. For mobile networks that consist mainly of portable computers or dial-up clients, shorter lease durations can be useful. Likewise, for a stable network that consists mainly of desktop computers at fixed locations, longer lease durations are more appropriate.


Set the duration for scope leases when distributed by this server.

Limited to:

Days: Hours: Minutes:

< Back **Next >** Cancel

Click on next



New Scope Wizard

Configure DHCP Options

You have to configure the most common DHCP options before clients can use the scope.

When clients obtain an address, they are given DHCP options such as the IP addresses of routers (default gateways), DNS servers, and WINS settings for that scope.

The settings you select here are for this scope and override settings configured in the Server Options folder for this server.


Do you want to configure the DHCP options for this scope now?

☒ Yes, I want to configure these options now

☐ No, I will configure these options later

< Back Next > Cancel

Enter your gateway address



New Scope Wizard

Router (Default Gateway)

You can specify the routers, or default gateways, to be distributed by this scope.

To add an IP address for a router used by clients, enter the address below.

IP address:

< Back Next > Cancel

Add ADDS server IP as the primary DNS and the gateway as the secondary DNS

New Scope Wizard

Domain Name and DNS Servers
The Domain Name System (DNS) maps and translates domain names used by clients on your network.

You can specify the parent domain you want the client computers on your network to use for DNS name resolution.

Parent domain:

To configure scope clients to use DNS servers on your network, enter the IP addresses for those servers.

Server name:

IP address:

Add
Remove
Up
Down

192.168.200.100
192.168.200.2

< Back Next > Cancel

Click on Next

New Scope Wizard

WINS Servers
Computers running Windows can use WINS servers to convert NetBIOS computer names to IP addresses.

Entering server IP addresses here enables Windows clients to query WINS before they use broadcasts to register and resolve NetBIOS names.

Server name:


IP address:

Add
Remove
Up
Down


To change this behavior for Windows DHCP clients modify option 046, WINS/NBT Node Type, in Scope Options.

< Back Next > Cancel


Activate Scope




The scope was created successfully



Click on the DHCP domain and click on Action > Authorize




Right click on IPv4 and refresh




Verification (Client)

Open network connections (WIN + R) > ncpa.cpl

Select Network Interface > Properties > IPv4 > Obtain IP address automatically, Obtain DNS Server address automatically




Right click on Network Interface, Status > Details




Question 3


To add virtual HDD, in VMWare select Edit virtual Machine Settings




Click on ADD




Select Hard Disk the then click on next




Specify Disk Capacity (Select store in a single file)




Hard Disk for added successfully




Go to Server Manager > Tools > Computer Manager




Go to Computer Manager > Storage > Disk Management




Initialize Disk as GPT Partition Style



Click on the unallocated space and click on New Simple Volume



Specify the volume size of the first partition



New Simple Volume Wizard

Specify Volume Size
Choose a volume size that is between the maximum and minimum sizes.

Maximum disk space in MB: 30702


Minimum disk space in MB: 8

Simple volume size in MB: 15360

< Back Next > Cancel

This screenshot shows the 'Specify Volume Size' step of the 'New Simple Volume Wizard'. It displays the maximum disk space (30702 MB) and minimum disk space (8 MB). The 'Simple volume size in MB' is set to 15360 MB using a spin box. The 'Next >' button is highlighted.

Assign a letter for that Drive



New Simple Volume Wizard

Assign Drive Letter or Path
For easier access, you can assign a drive letter or drive path to your partition.

☒ Assign the following drive letter: Z


☐ Mount in the following empty NTFS folder: Browse...

☐ Do not assign a drive letter or drive path

< Back Next > Cancel

This screenshot shows the 'Assign Drive Letter or Path' step of the 'New Simple Volume Wizard'. The 'Assign the following drive letter' option is selected, with the letter 'Z' chosen from the dropdown menu. The 'Next >' button is highlighted.

Select the File system for that partition, here we will user FAT32



New Simple Volume Wizard

Format Partition
To store data on this partition, you must format it first.

Choose whether you want to format this volume, and if so, what settings you want to use.

☐ Do not format this volume

☒ Format this volume with the following settings:

File system: FAT32

Allocation unit size: Default


Volume label: FAT32 FS

☒ Perform a quick format

☐ Enable file and folder compression

< Back Next > Cancel

Confirm changes and click on finish



New Simple Volume Wizard

Completing the New Simple Volume Wizard

You have successfully completed the New Simple Volume Wizard.


You selected the following settings:

- Volume type: Simple Volume
- Disk selected: Disk 1
- Volume size: 15360 MB
- Drive letter or path: Z:
- File system: FAT32
- Allocation unit size: Default
- Volume label: FAT32 FS
- Quick format: Yes


To close this wizard, click Finish.

< Back Finish Cancel

Partition one was successfully created.




Choose the unallocated space and create a new volume but select ReFS as the file system.




Question 4


Go to Server Manager > Manage > Remove Roles and Features




Select the Active Directory Domain Service



Click on Remove Features



Now click on "Demote this domain controller"



In the ADDS Config, select Force the removal of this domain controller

The screenshot shows the 'Active Directory Domain Services Configuration Wizard' window. The title bar includes the Windows logo, the text 'Active Directory Domain Services Configuration Wizard', and standard window controls. The main window has a light blue header with the title 'Credentials' on the left and 'TARGET SERVER master.tfsi.com' on the right. A left-hand navigation pane contains links: 'Credentials' (highlighted in blue), 'Warnings', 'Removal Options', 'New Administrator Passw...', 'Review Options', 'Demotion', and 'Results'. The main content area is titled 'Supply the credentials to perform this operation'. It shows 'TFSI\Administrator (Current user)' with a 'Change...' button. Below this is a checkbox labeled 'Force the removal of this domain controller', which is highlighted with a red square. A warning icon (yellow triangle with an exclamation mark) is next to the text: 'No other domain controller could be contacted. Proceeding will cause any Active Directory Domain Services changes that have been made on this domain controller to be lost. To proceed anyway, confirm that this is the last domain controller in the domain.' Below this is another checkbox labeled 'Last domain controller in the domain'. At the bottom of the main area is a warning icon and text: 'The server will be automatically restarted after the demotion operation. Role removal needs to be performed after the restart.' and a link 'More about removal credentials'. The bottom of the window has a grey bar with four buttons: '< Previous', 'Next >', 'Demote', and 'Cancel'.

Active Directory Domain Services Configuration Wizard

Credentials

TARGET SERVER
master.tfsi.com

Credentials

Warnings

Removal Options

New Administrator Passw...

Review Options

Demotion

Results

Supply the credentials to perform this operation

TFSI\Administrator (Current user) [Change...](#)

☐ Force the removal of this domain controller

⚠ No other domain controller could be contacted. Proceeding will cause any Active Directory Domain Services changes that have been made on this domain controller to be lost. To proceed anyway, confirm that this is the last domain controller in the domain.

☐ Last domain controller in the domain

⚠ The server will be automatically restarted after the demotion operation. Role removal needs to be performed after the restart.

[More about removal credentials](#)

< Previous Next > Demote Cancel

Check the proceed with removal sections and click on Next

The screenshot shows the 'Active Directory Domain Services Configuration Wizard' window. The title bar includes the Windows logo, the text 'Active Directory Domain Services Configuration Wizard', and standard window controls. The main window has a light blue header with the title 'Warnings' on the left and 'TARGET SERVER master.tfsi.com' on the right. A left-hand navigation pane contains links: 'Credentials', 'Warnings' (highlighted in blue), 'New Administrator Passw...', 'Review Options', 'Demotion', and 'Results'. The main content area is titled 'The domain controller currently hosts the following role(s):'. It lists several roles: 'PDC emulator', 'RID operation master', 'Domain Naming operation master', 'Infrastructure operation master', 'Schema operation master', 'Domain Name System (DNS) Server', and 'Global Catalog'. Below this list is a warning icon (yellow triangle with an exclamation mark) and text: 'The roles hosted by the domain controller are required for Active Directory Domain Services functionality. If you proceed, some Active Directory Domain Services operations may be impacted.' Below this is a checkbox labeled 'Proceed with removal', which is checked. At the bottom of the main area is a link 'More about removal options'. The bottom of the window has a grey bar with four buttons: '< Previous', 'Next >', 'Demote', and 'Cancel'.

Active Directory Domain Services Configuration Wizard

Warnings

TARGET SERVER
master.tfsi.com

Credentials

Warnings

New Administrator Passw...

Review Options

Demotion

Results

The domain controller currently hosts the following role(s):

- PDC emulator
- RID operation master
- Domain Naming operation master
- Infrastructure operation master
- Schema operation master
- Domain Name System (DNS) Server
- Global Catalog


⚠ The roles hosted by the domain controller are required for Active Directory Domain Services functionality. If you proceed, some Active Directory Domain Services operations may be impacted.

☒ Proceed with removal


[More about removal options](#)

< Previous Next > Demote Cancel


Review changes and click on Demote.



Your server & clients that were part of ADDS will be forcefully signed off.



Verification



After opening Server Manager again, we can see ADDS is missing.

