1A PyTorch Installation

August 10, 2024

1 PyTorch Installation

A walkthrough to install PyTorch for Python 3.6. If you already have PyTorch on your machine and feel confident in your installation, you can go ahead and skip this notebook.

For the purposes of this tutorial, I'm recommending using Anaconda as your Python distribution and for managing your environments. If you'd rather use some other distribution or version of Python and feel confident in your abilities, you may also choose to just follow the instructions here: https://pytorch.org/get-started/locally/.

1.0.1 Install Anaconda

Download and install Anaconda. A more detailed version of the below steps specifically for Windows (macOS and Linux instructions are similar) can be found here if you need additional assistance.

- 1. Go to the Anaconda install page and click on the Python 3.7 installer matching your operating system (e.g. Windows, macOS, Linux) and system architecture (likely 64-bit X86).
- 2. Open the installer from your downloads folder and run it by double clicking on it.
- 3. Follow the installer's instructions.

Note: there is an option at one point to add Anaconda to PATH. While the installer recommends against this option (it's possible it may interfere with your other software), we typically recommend doing so, as it makes accessing Anaconda commands easier. The rest of this tutorial assumes that this option has been selected.

1.0.2 Set-up a conda environment

1. Open a Command Prompt (Windows) or a terminal (macOS or Linux)

Note: If you chose not to add Anaconda to PATH during Anaconda installation above, you will need to use the Anaconda Command Prompt instead.

- 2. Create a conda environment for PyTorch: Shell conda create -n pytorch python=3.6
- 3. Activate your new environment:

conda activate pytorch

- 4. Install some supporting dependencies Shell conda install h5py imageio jupyter matplotlib numpy tqdm
- 5. Install either the CPU version or GPU version of PyTorch:

CPU: (Recommended as sufficient for this class) "'Shell # Windows/Linux conda install pytorch torchvision cpuonly -c pytorch

macOS conda install pytorch torchvision -c pytorch ""

GPU: (You'll also need to install some Nvidia software) "'Shell # Windows/Linx, assuming CUDA 10.1 conda install pytorch torchvision cudatoolkit=10.1 -c pytorch

macOS # Trickier. May require installing from source. See PyTorch docs. "'

Note: If you have GPUs available, you should use the GPU version for any serious research or application, as it can be significantly faster. For the purposes of this demo though, the CPU version is sufficent.

1.0.3 Verify PyTorch Installation

1. While in your pytorch environment, enter the Python shell with:

python

Verify that your python version says Python 3.6.[x].

2. Enter this program into your Python shell:

```
import torch
print(torch.__version__)
x = torch.rand(2, 3)
print(x)
```

Your command line should return something like:

```
1.3.1
tensor([[0.3651, 0.7264, 0.9823],
[0.5398, 0.2145, 0.3616]])
```

The version returned will depend on what the current stable version of PyTorch is when you perform your install. As long as it's 1.[x].[y], these notebooks should work fine. The numbers in the tensor x will be random, so as long as the print returns a 2x3 tensor of random values, you're in good shape.

```
[1]: import torch
  print(torch.__version__)
  x = torch.rand(2,3)
  print(x)
```

```
1.4.0
tensor([[0.1169, 0.0445, 0.9100],
[0.0701, 0.8356, 0.3706]])
```

[]:[